

CA NetMaster® File Transfer Management

User Guide

Release 12.1



Second Edition

This Documentation, which includes embedded help systems and electronically distributed materials, (hereinafter referred to as the "Documentation") is for your informational purposes only and is subject to change or withdrawal by CA at any time.

This Documentation may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of CA. This Documentation is confidential and proprietary information of CA and may not be disclosed by you or used for any purpose other than as may be permitted in (i) a separate agreement between you and CA governing your use of the CA software to which the Documentation relates; or (ii) a separate confidentiality agreement between you and CA.

Notwithstanding the foregoing, if you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all CA copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to CA that all copies and partial copies of the Documentation have been returned to CA or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, CA PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL CA BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF CA IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is CA.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2012 CA. All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

CA Technologies Product References

This document references the following CA Technologies products:

- CA 7 Workload Automation (CA 7 WA)
- CA ACF2™ for z/OS (CA ACF2)
- CA NetMaster® File Transfer Management (CA NetMaster FTM)
- CA SOLVE:FTS
- CA SYSVIEW® Performance Management (CA SYSVIEW)
- CA TCPaccess™ Communications Server (CA TCPaccess CS)
- CA TCPaccess™ FTP Server
- CA Top Secret® for z/OS (CA Top Secret)
- CA XCOM™ Data Transport®

Contact CA Technologies

Contact CA Support

For your convenience, CA Technologies provides one site where you can access the information that you need for your Home Office, Small Business, and Enterprise CA Technologies products. At <http://ca.com/support>, you can access the following resources:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- CA Support policies and guidelines
- Other helpful resources appropriate for your product

Providing Feedback About Product Documentation

If you have comments or questions about CA Technologies product documentation, you can send a message to techpubs@ca.com.

To provide feedback about CA Technologies product documentation, complete our short customer survey which is available on the CA Support website at <http://ca.com/docs>.

Contents

Chapter 1: Getting Started	11
Log On	11
If Region Initialization Is Still in Progress.....	12
If the System Image Is Still Being Loaded.....	12
Log Off	12
Your Password.....	13
Change Your Password.....	13
Authority Levels	14
The Menus.....	15
Access Functions	16
Select an Option.....	16
Specify a Path.....	17
Specify a Shortcut	18
Lists.....	19
Scrolling.....	19
Search for an Item.....	20
Data Entry Panels	21
UPDATE Mode.....	21
Enter Data	21
Validate and File Data	22
Move Between Panels.....	22
Work with Definitions in the Knowledge Base.....	25
Add a Definition	25
Browse Definitions	26
Update Definitions	26
Copy Definitions	26
Delete Definitions	27
Online Help.....	27
Tip of the Day.....	27
Help About a Panel.....	28
Help About Fields on a Panel	28
Help for a Message	28
Work in Two Windows	29
Split Screens.....	29
Swap Screens	29

Chapter 2: Managing File Transfer Resources

31

File Transfer Status Monitor.....	32
Access the File Transfer Status Monitor	32
List Monitors Associated With a Specific Manager	33
Change the Type of Information Displayed.....	33
Display Information About File Transfer Resources.....	34
Monitor File Transfer Schedules	37
Acknowledge a Failure Status	37
Display the Next Time a Schedule Starts Monitoring.....	38
Display Selective Schedules on the File Transfer Status Monitor	38
Update an Active Schedule	38
Schedule Forecasting	39
Forecast Types	39
Forecast File Transfer Schedules	40
Interpret the Status of File Transfer Schedules.....	41
Interpret the Status of Supporting File Transfer Resources	42
Interpret File Transfer Status Monitor Fields.....	43
Interpret Colored Resources and Messages	43
Activate and Inactivate a File Transfer Resource	44
Activate a File Transfer Resource	44
Inactivate a File Transfer Resource	44
Issue Commands to a File Transfer Resource.....	45
Issue Commands to a Remote CONNECT:Direct Region	45
Display a CA XCOM Data Transport Control Library Member	46
Display the MAXLOC, MAXREM, and MAXTASK Parameters	46
List and Manage CA XCOM Data Transport Transfer Requests.....	46
XCMGR Transfer Requests	47
Manage Transfer Requests	48
CONNECT:Direct Security Considerations	48
Confirm Your CONNECT:Direct Signon Details.....	49
Clear Your CONNECT:Direct Signon Details.....	49
Display a CONNECT:Direct Network Map	50
Display the Initialization Parameters of a CONNECT:Direct Region	50
List and Manage CONNECT:Direct Processes	50
List Processes	51
Manage Processes.....	52
List and Manage TCP/IP Connections.....	53
Drop a Connection	53
List CONNECT:Mailbox Batches.....	53
Manage CONNECT:Mailbox Batches	54
Initiate an Auto Connect	55

Monitor CONNECT:Mailbox Resources	55
Display CONNECT:Mailbox Monitors	56
List and Manage CONNECT:Mailbox VSAM Batch Files.....	56
Maintain VSAM Batch Files Using the Assisted REORG Facility	57
Monitor Your File Transfer Environment Using the Graphical Monitor	58

Chapter 3: Monitoring Active File Transfers 59

File Transfer Monitor	59
Display Active File Transfers.....	60
How to Display the Estimated Completion Time	60
Filter File Transfers	60
Apply a Filter to the File Transfer Monitor.....	61
Apply a File Transfer Monitor Filter from a List	61
Create a New File Transfer Monitor Filter	62
Sort Active File Transfers.....	63
Change the List Format	63
Apply a List Format to the File Transfer Monitor	64
Apply a List Format from a Selection List	64
Create a New List Format.....	65
Set Up the File Transfer Monitor in Your User Profile.....	66

Chapter 4: Managing Alerts 67

Alert Monitor	68
Access the Alert Monitor.....	68
Sort Alerts.....	69
Filter Alerts	69
Change the Display Format	69
Change the Alert Monitor Profile Using the User Profile Menu	70
How to Work with Alerts.....	70
Display Alert Details	71
Print Alert Details	71
Access the Transient Log from the Alert Monitor	71
Raise a Trouble Ticket for an Alert	72
Add Operator Notes to an Alert	72
Close Alerts.....	73
Display Alert History	73

Chapter 5: Using Logs 75

Display the File Transfer Log	75
Browse the File Transfer Log Online	75

Suppress CONNECT:Direct Messages Logged to the File Transfer Log	76
Access Activity Log from the File Transfer Log	76
Display an Activity Log.....	77
Browse the Activity Log Online	77
Suppress Messages Logged to the Activity Log	78
Record Additional Information in the Activity Log	78
Display a Transient Log.....	78
Set Criteria to Display Logged Messages Selectively.....	79
Display User-defined Log Messages.....	80
Obtain Help on a Logged Message.....	80
Print a Transient Log	81
Reset a Transient Log.....	81
Change Logging Options.....	81
Merge Transient Logs.....	82
Transient Logs From Different Time Zones	82
Size of a Merged Transient Log	82

Chapter 6: Using Monitors 83

Monitor Services and Resources	83
Control Services and Resources	84
Graphical Monitor	85
Interpret the Graphical Monitor Display.....	86
Access the Graphical Monitor	86
Operations From the Graphical Monitor	86
Change to a Different Default Icon Panel.....	88
Use the Status Monitor	88
Interpret the Status Monitor Display	89
Organize the Information on the Status Monitor	89
Change to a Different Status Monitor Filter.....	92
Change Your Default Status Monitor Profile.....	93
Use Commands in the Status and Graphical Monitors	94
Find Out More About Monitored Services and Resources.....	94
Remove the User-defined Extended Display	94
Access Extended Functions	94
Reply to a WTOR Message	95
Browse or Update the Definition of Monitored Services and Resources	95
Override the Operation Mode	96
Override the Service and Resource States	96
Modify the Scheduled Operations Changes for a Monitored Item	97
Control Manual Services and Resources	98
Acknowledge a Link Failure	99

Respond to the Initialization Status Panel	100
Respond to the Database Synchronization Panel	100
Recover a Failed Resource	101
Recover From Failed Automation	101
Obtain Operations Statistics.....	102
Obtain the Operations Statistics of a Monitored Service or Resource	102
Interpret the Statistics	103

Chapter 7: Using Operator Console Services 105

Operator Console Services	105
Access OCS	105
OCS Panel	106
Command Line	106
Operating Mode Indicators	106
Roll Delete Area	106
Non-roll Delete Area	107
Roll-delimiter Line	107
Title Line	107
Time Display	107
Run Multiple OCS Panels	107
Set Window IDs	108
Function Keys	109
Conversational Function Keys	109
Prefix and Suffix Function Keys	109
Assign Your Own Values to Function Keys	110
Specify Commands to Function Keys	111
Specify Function Keys Using NCL Procedures	112
Use Commands in OCS	113
Command Authority Levels	113
Abbreviate Commands.....	113
Reuse Commands.....	114
Rename Commands	115
Monitor and Control in OCS	116
Control Message Presentation Speed	116
Unwrap Messages	117
Clear the OCS Window	118
Receive Non-roll Delete Messages	118
Hide NRD Messages	119
Restore Hidden NRD Messages	119
Delete NRD Messages	119
Use NRD Messages with ROF Sessions.....	120

Interpret Messages and Codes to Help Monitor Your Region	120
Issue Commands	120
Issue Commands in Background Environments	121
Issue Commands at Specified Times	122
Execute or Start NCL Processes from OCS.....	126
Execute NCL Processes Serially	126
Execute NCL Processes Concurrently	127
NCL Identifiers.....	127
Execute an NCL Process from a Serial or Concurrent Process	127
Start REXX Programs from OCS	128
Issue System Commands from Your Console	129
Use the SYSCMD Facility	129

Chapter 8: Using WebCenter **131**

WebCenter Features	131
Set Up Your Web Browser.....	132
Set Up Internet Explorer	132
Set Up Firefox.....	134
Log On to WebCenter.....	135
CA SYSVIEW Integration	136

Chapter 9: Using Print Services **137**

Print Services Manager	137
Access PSM.....	137
List Entries in the Print Queue.....	138
Display the Output of a Print Request	138
Confirm Printing	139
Select the Printer	139

Index **141**

Chapter 1: Getting Started

These topics explain how to access and navigate the product's 3270 interface, and the major components of that interface.

This section contains the following topics:

[Log On](#) (see page 11)

[Log Off](#) (see page 12)

[Your Password](#) (see page 13)

[The Menus](#) (see page 15)

[Access Functions](#) (see page 16)

[Lists](#) (see page 19)

[Data Entry Panels](#) (see page 21)

[Work with Definitions in the Knowledge Base](#) (see page 25)

[Online Help](#) (see page 27)

[Work in Two Windows](#) (see page 29)

Log On

To access your product, you must log on to it through a region. The logon procedure is the same whether you are logging on in a single system or a multisystem environment. Before you can log on to a region, you need a user ID and password. Ensure that your system administrator has defined your user ID to the region and has allocated the relevant level of authority.

Note: You may have access to one or more regions. This depends on whether your organization has set up a single system or a multisystem environment.

To log on to your product

1. Use your installation defined method for establishing SNA sessions to connect to the ACB name of the region.

For example, enter **LOGON APPLID(acb-name)**, using the ACB name of the region.

2. Enter your user ID and password on the displayed logon panel.

The Primary Menu appears.

Note: When you first log on to a region, the region uses a default profile for your primary menu. You can update the profile to change the format of the menu. To update the profile, enter **PROFILE** at the command prompt.

If Region Initialization Is Still in Progress

If the Initialization in Progress panel appears on your screen instead of the primary menu, the initialization of the region is still in progress. Press F3 (Exit) to exit to the primary menu.

Note: For information about the initialization process, see the *Installation Guide*.

If the System Image Is Still Being Loaded

If the local system image is still being loaded, the primary menu contains the **LS** option. You can select this option to monitor the loading process. You can also perform functions that do not depend on an active local image.

Note: For information about system image loading, see the *Administration Guide*.

Log Off

To log off from the region, enter **=X** at the prompt. This terminates your current window.

If you are at the primary menu, enter **X** at the prompt to terminate your current window.

Note: You can have two windows for each logon to a region. If you have two windows, repeat the procedure to terminate the remaining window to log off from the region.

More information:

[Work in Two Windows](#) (see page 29)

Your Password

Your password is verified by the User Access Maintenance Subsystem (UAMS).

The subsystem lets you change your password, or prompts you to change your password when it has expired after a period of time. You can change your password at any time after you log on to a region. The change becomes effective the next time you log on to the region.

Note: Your installation might have linked UAMS with an external security system, such as CA ACF2, CA Top Secret, and Resource Access Control Facility (RACF). If this is the case, your system administrator will tell you of any special considerations that apply when changing your password.

In a multisystem environment, the administrator might have set up the environment for the synchronization of UAMS user definitions and passwords. Changed passwords are then synchronized across connected regions.

Change Your Password

To change your password

1. Enter **/CHGPWD** at the prompt.

The User Password Maintenance panel appears.

2. Complete the following fields:

Current Password

Specifies your current password.

New Password

Specifies your new password.

Retype your new password, and press F3 (File).

The system changes your password.

Note: If UAMS synchronization is enabled, a Linked Regions UAMS Update Report panel appears when you save your changed password. The panel reports the success or failure of the password change in the connected regions.

Authority Levels

Your user ID in UAMS determines your level of access to your product, the functions you can perform, and the commands you can issue.

If you attempt to perform an unauthorized function or issue an unauthorized command, an error message appears, telling you that you are not authorized to perform that function or issue that command.

The Menus

The user interface includes several menus. The region issues an error message if you try to use a function that you are not authorized to use.

Note: In a multisystem environment, the Service Administration menu and the System Console Consolidation menu are not applicable in subordinate regions.

The menu panels have the following hierarchy. Shortcuts to the menu options are shown in parentheses.

M Monitors

- A** Alert Monitor (ALERTS)
- R** Resource Monitor (RMON)
- S** Service Monitor (SMON)
- G** Graphical Monitor (GMON)
- FT** File Transfer Resource Monitor (FTMON)
- AFT** Active File Transfer Monitor (AFTMON)

H Historical Data

- A** Alert History (ALHIST)
- FT** File Transfer History (FTHIST)
 - B** Browse Event and Transfer Details
 - P** Print Event and Transfer Details or Summaries
 - EX** Extract File Transfer Events to Dataset
 - BS** Browse Schedule Details
 - SF** Schedule Forecast
 - PS** Print Schedule Details or Summaries
 - ER** File Transfer Exception Reporting
 - FTL** File Transfer Log (FTLOG)

L Activity Log

U User Service

- M** Display Product Message Help
- P** Password/Details Change for your User (CHGPWD)
- UP** Update Your User Profile
- B** Review Broadcasts

O Operator Console Services

A Administration and Definition

A Alert Monitor Administration (ALADMIN)

R Resource Administration (RADMIN)

S Service Administration (SADMIN)

E Event Administration (EADMIN)

G Graphical Monitor Administration (GADMIN)

M Multi-System Support Administration (MADMIN)

FT File Transfer Administration (FTADMIN)

AS Automation Services Administration (ASADMIN)

SS Security and System Services (SS)

C Customizer (CUSTOM)

Access Functions

To access functions through the user interface menus, do *one* of the following:

- Select an option from each menu that leads to the function.
- Specify a path.
- Specify a shortcut.

Select an Option

You select an option by entering the option code at the prompt. For example, entering **M** at the prompt on the primary menu takes you to the Monitors primary menu.

If you specify a collapsed or expanded menu format in your profile, you can expand or collapse the displayed menu hierarchy. In these formats, you can also place your cursor beside a required option and press Enter to select it.

Note: For more information, press F1 (help) from the primary menu.

Specify a Path

You can jump to the panel of a function directly by specifying the exact path to that panel. Construct the path by linking the options you need with periods. Depending on which panel you start from, you can display a panel that:

- Is lower in the panel hierarchy
- Is higher in the panel hierarchy
- Requires input data

Lower in the Panel Hierarchy

If you start from a menu and want to access a panel lower in the panel hierarchy, specify the path as it is. For example, if you are at the primary menu and want to change your password, type **U.P** at the prompt and press Enter.

Higher in the Panel Hierarchy

If you want to access a panel that requires you to pass through a panel higher up in the panel hierarchy, you must precede the path specification with the equals sign (=). The = character brings you back to the primary menu and then to the required panel. You can specify such a path at any prompt. For example, if you are at the Alert Monitor and want to change your password, enter **=U.P** at the prompt and press Enter.

To return to the primary menu, enter **==**.

Input Data

If you want to access a panel that requires you to enter data, you can enter the data by separating them from the path by a semicolon (;).

For example, if you are at the primary menu and want to access the alert history for the linked region PROD2, type **H.A;PROD2** at the prompt and press Enter.

Some panels have more than one input field for entering data. You should use the correct number of semicolons to identify the field.

For example, you must use two semicolons if you want to enter *data_2* in the second field:

option_1.option_2;;data_2

Specify a Shortcut

Note: The PMENUCONTROL parameter group controls the shortcuts. Your administrator can disable shortcuts or change the shortcut character.

You can jump to the panel of a function directly by using shortcuts. You can specify the shortcut at a prompt in one of the following ways:

- Specify `/shortcut-name` to retain the current panel on return.
- Specify `=/shortcut-name` to close the current panel and return to the primary menu on exit.

An entry on a menu can have an associated shortcut, displayed in turquoise.

Note: If you do not remember a shortcut, enter `/` or `=/` to list the shortcuts and then select one.

`/shortcut-name`

Important! If the current panel provides automatic updates and you no longer need this information, use `=/shortcut-name` rather than a nested shortcut. This saves storage and resources because the region does not need to maintain a display that you no longer need.

To select the function you want, enter its corresponding shortcut, preceded by the slash (`/`) character, at a prompt.

When you access a function by using its shortcut, your current panel is retained. When you press F3 to exit out of the function, this panel, with any updates, is restored. By using shortcuts, panels can be nested to a maximum of 64 levels.

For example, to access the Alert Monitor History Menu, enter `/ALHIST` at the prompt on your current panel. When you are finished with the menu, press F3 to redisplay your previous panel.

`=/shortcut-name`

When you have finished with your current panel, you can access the next function by prefixing the shortcut call with the equals (`=`) sign. This goes directly to the function without retaining the current panel and closes all other nested panels in this window.

For example, to access the Alert Monitor History Menu without retaining the current panel, enter `=/ALHIST` at the prompt on your current panel. When you are finished with the menu, press F3 to display the primary menu.

Access a Function That Does Not Have a Shortcut

You can combine a shortcut with option codes to form a path to access a function that does not have a shortcut itself.

For example, to access the alert history, you can enter the **/ALHIST.B** path.

Lists

Lists comprise a series of items that you can select or against which you can perform actions. The panel shows the actions that you can perform on the listed items.

There are four types of list:

Action Lists

Let you apply *actions* to one or more listed items. Enter the required action code beside the appropriate records.

Single Selection Lists

Let you select one item from a list (for example, the list of valid values for a data entry field) by doing *one* of the following:

- Entering the **S** (Select) action code beside the item
- Moving the cursor to a position anywhere in the line containing the item you want to select and pressing Enter

Multiple Selections Lists

Let you select one or more items in a list (for example, the list of panels used to customize your user profile).

Numbered Lists

Let you select a single item from the list by entering the appropriate number at the prompt (for example, the list of valid values for a data entry field).

Scrolling

If the listed information cannot fit onto the screen, use scrolling to access the off-screen information. You can scroll vertically and horizontally.

Scroll Vertically

Use the F8 (Forward) or F7 (Backward) function key to scroll the displayed information by the amount displayed at the Scroll prompt.

The following table shows valid scroll amounts.

Scroll Amount	Action
C (or CSR)	If scrolling forward, the line on which the cursor is currently positioned is moved to the top of the screen. If scrolling backward, the line on which the cursor is currently positioned is moved to the bottom of the screen.
D (or DATA)	The display is scrolled one full page, less one row, in the specified direction. If scrolling forward, the last line of the current page appears as the first line on the next page. If scrolling backward, the first line on the current page appears as the last line on the next page.
H (or HALF)	The display is moved half a page in the specified direction.
M (or MAX)	The display is moved to the beginning or the end of the displayed information, depending on the function key (Forward or Backward) used.
P (or PAGE)	The display is moved one full page in the specified direction.
<i>n</i>	The display is moved <i>n</i> lines in the specified direction. If you enter a temporary scroll amount at the command prompt (for example, Command ==> 5), then when you press the F7 (Backward) or F8 (Forward) function key, the displayed information is scrolled by the specified value once only.

Scroll Horizontally

Use the F11 (Right) or F10 (Left) function key to scroll the displayed information to the right or to the left.

Search for an Item

You can search for specific items in the retrieved information by using the F5 (Find) function key or the LOCATE command.

F5 (Find) Function Key

The F5 (Find) function key lets you find text in the retrieved information. Enter the text you want to find, and press F5. If the text contains more than one word, enclose the text in quotation marks.

You can press F5 again to find the next instance of the text.

For some lists, you can enhance the Find function in the following ways:

- Expand the search beyond the columns currently displayed by using the FMODE command
- Change the number of records searched between prompts by using the F PROMPT command

Note: For information about the FMODE and F PROMPT commands, see the online help.

LOCATE Command

The LOCATE command enables you to locate a particular record in a list. Enter **LOCATE** or **L** followed by a text string mask. The command locates the first record name that matches the mask.

Data Entry Panels

Resource definitions are displayed and maintained through a sequence of panels on which you enter the data for that resource.

UPDATE Mode

Many definition panels enable authorized users to switch from the BROWSE mode to the UPDATE mode by pressing F4 (Edit). You can then edit the displayed information.

Enter Data

On a color screen, mandatory fields that you must complete are colored white. Optional fields, which you can complete as and when required, are colored turquoise. Both types of fields can be prompted fields that provide you with a list of valid values, from which you can choose one item.

Prompted Fields with a List of Valid Values

Many fields on the data entry panels are linked to lists containing the values that you can choose for the field. These fields are called prompted fields. Most, but *not* all, prompted fields are identified by a plus sign (+).

Enter ? in a prompted field to display the value list, which can be a numbered list or a single select list.

You can prefix the question mark (?) with one or more characters. The displayed list is then restricted to values that start with those characters. For example, enter **S?** to display a list of values that start with S.

Validate and File Data

During data entry, you can press Enter to validate your data. Validation also occurs when you:

- Access another panel (for example, when you press F8 (Forward) to access the next panel)
- Save your entered data (for example, when you press F3 (File) to save a definition)

When you finish entering data, you can do *one* of following:

- Press F3 (File) to save the data and exit the panel.
- Press F4 (Save) to save the data and remain on the panel. When adding definitions, this enables you to quickly create other similar definitions, minimizing the typing required.
- If you do *not* want to save the data, press F12 (Cancel) to exit the panel.

Move Between Panels

Some functions lead to a series of data entry panels (for example, when you update a resource definition).

You can use *one* of the following methods to move through these panels, depending on what you need to do:

- Select all panels.
- Select specific panels from the Panel Display List.
- Select a panel from another panel.
- Select a panel from the Index Menu.
- Save a sequence of definition panels for repeated access.

Select All Panels

You may want to access every panel. All panels are listed on a Panel Display List (for example, the panel that lists the resource definition panels). Enter **S** next to the name of the panel you want to access first, or enter the number that identifies that panel in the panel sequence at the command prompt (for example, 1 for the first panel). The selected panel appears.

Press F8 (Forward) to scroll forward to the next panel; press F7 (Backward) to scroll backward to the previous panel.

When you finish entering data, press F3 (File) to save the data. Press F12 (Cancel) if you decide not to save the data.

Select Specific Panels from the Panel Display List

You may want to access certain panels only (for example, when you want to update only certain parts of a resource definition). All the panels required for a definition are listed on a Panel Display List. Type **S** next to the names of the panels you want to access. After you complete your selections, press Enter to display the first panel you selected. Then press F8 (Forward) to scroll forward through the panels you selected. Press F7 (Backward) to scroll backward through the panels you selected.

When you finish entering the data, press F3 (File) to save the data. Press F12 (Cancel) if you decide not to save the data.

Select a Panel from Another Panel

If you want to skip to a panel that is not next in the sequence, and you know the sequence number of the panel you want, enter that number at the command prompt. The required panel appears.

Select a Panel from the Index Menu

From some data entry panels, you can press F11 (Panels) to display the Index Menu panel. This menu lists all the panels available for that function. Use the Index Menu if you want to jump to a panel but do not know its place in the panel sequence.

Note: If you have selected two or more panels previously, pressing F11 (Panels) displays a list of the selected panels only. You can press F6 (AllPanel or SelPanel) to switch between the full list and the partial list.

Save a Sequence of Definition Panels for Repeated Access

On a definition list panel, you can select more than one definition. You can then work on the selected definitions in sequence. Each definition can contain a number of definition panels. Normally, the list of panels appears on your screen for you to select each time you access a new definition. However, if you want to browse or update the same panels for each selected definition, you can save the list of panels you want, as shown in the following procedure.

As you move through the sequence of selected definitions, the panels appear on your screen according to the saved list. You do not have to select the panels again when you move on to the next definition.

To save the resource definition panels for repeated access

Note: The following procedure uses resource definition panels as examples.

1. Enter the `=/RADMIN.R.STC` path.
The Started Task List panel appears.
2. Type **B** (Browse) or **U** (Update) next to the definitions you want to access, and press Enter.
Note: You can use the F7 (Backward) or F8 (Forward) function keys to scroll through the list.
The Panel Display List window appears.
3. Type **S** next to the panels you want, and press F4 (SaveSeq).
The system saves the list of selected panels.
4. Press Enter.
The first selected panel appears.

Note: When you finish with one definition, the panels for the next definition appear in the same sequence.

Work with Definitions in the Knowledge Base

Depending on your security settings, you can add, browse, update, copy, and delete the definitions in the knowledge base.

If you have several regions connected together, changes to the knowledge base in one region are automatically propagated to the knowledge bases in the other regions (that is, the knowledge bases are synchronized).

Note: For information about multisystem support, see the *Administration Guide*.

Important! You should restrict the update of a definition to a single focal point region. Updating the same definition from more than one region may cause the linked knowledge bases to become unsynchronized.

The activity log contains an audit trail of definition maintenance activities, identifying the time an activity occurs and the user responsible for that activity. The information is also displayed on the definition list panels. You can press F11 (Right) to view the information.

Add a Definition

To add a definition

1. Access the list that displays the type of definitions you want to add.
For example, if you want to add a definition for a started task, you can enter the **=/RADMIN.R.STC** path to access the list of definitions.
2. Add the definition in one of the following ways:
 - Press F4 (Add)
 - Update a copy of another definition

Note: To see the new definition, press F6 (Refresh) to update the list. You may also need to scroll the list to view the new addition.

Browse Definitions

To browse the details of a definition in read-only mode

1. Access the list of definitions.
2. Enter **B** beside the definition you want to browse.

The definition appears.

Note: To browse more than one definition, type **B** beside all the definitions you want to browse and press Enter. If you select multiple definitions, pressing F3 (Exit) when viewing a definition exits the current definition and calls up the next definition.

Update Definitions

To update a definition

1. Access the list of definitions.
2. Enter **U** beside the definition you want to update.

A panel appears displaying the fields you can update. A definition can have multiple panels.

3. Update the required fields, and press F3 (File).

The definition is saved.

Note: To update more than one definition, type **U** beside all the definitions you want to update and press Enter.

Copy Definitions

Copy a definition if you want to create a similar definition.

To copy a definition

1. Access the list of definitions.
2. Enter **C** beside the definition you want to copy.

Change the value in the field that uniquely identifies the new copy, update the other fields as required, and press F3 (File).

The new definition is saved.

Note: When you make a copy of a definition, the F4 (Save) function key lets you continue creating independent copies of that definition. In Step 3, instead of pressing F3, press F4. The definition remains open, and you can perform Step 3 again to define a new copy. To copy more than one definition, type **C** beside all the definitions you want to copy and press Enter.

Delete Definitions

To delete definitions

1. Access the list of definitions.
2. Type **D** beside the definitions you want to delete, and press Enter.

A confirmation panel or message appears.

Important! If the confirmation prompt is a message, only one confirmation message appears even if you are deleting more than one definition.

Important! If you want to cancel the operation, you must press F12 (Cancel) before the next step.

3. Press Enter.

The selected definitions are deleted.

Online Help

Online help is provided for panels and messages.

Context-sensitive help is available at different levels. When you are viewing a help panel, pressing F1 (Help) takes you to the next level of help available. Pressing F3 (Exit) takes you back to the previous level, or exits from help and returns you to the application. Pressing F4 (Return) exits help and returns you to the application immediately.

Tip of the Day

The region displays a tip about using the product at the bottom of the primary menu.

To display the detailed tip, place the cursor on the tip and press F1 (Help).

Help About a Panel

Panel-based online help includes information about what each panel is used for, how to complete the fields, the actions you can perform, and the use of available function keys. Use this online help to supplement the information in this guide while you are working in the region.

Press F1 (Help) to retrieve the online help for a given panel. When you are viewing a help panel, you can press F6 (HelpHelp) to find out how to use the help facility.

If the block of help text you require splits across two panels, use the arrow keys to move the cursor to the top or the bottom of the block and press F8 (Forward) or F7 (Backward) to bring the block into view.

Help About Fields on a Panel

Many panels provide field-level online help.

To retrieve the online help for an input field, move your cursor to the field and press F1 (Help).

Help for a Message

While you are working in the region, you receive messages that advise you of various events. These messages might be providing information only (for example, informing you that an update was successful). They might also alert you to errors (for example, if you try to enter an action that is not valid for a resource).

Each message has detailed online help text associated with it. Access the help text for a particular message in *one* of the following ways:

- If you are at a panel and a message appears in red on the third line of that panel, move the cursor to that line and press F1 (Help).
- If you receive a message referring you to the activity log for more detail, enter **/LOG** at the prompt to display the activity log.
- If you are using the activity log, a Command Entry panel, or Operator Console Services (OCS), you can do *one* of the following:
 - Move the cursor to the line displaying the message, and press F1 (Help).
 - Type the message ID at the prompt, and press F1 (Help).
- If you are viewing a transient log, enter **H** beside the message.
- You can also enter **/CODES** to display the Messages and Codes Menu that enables you to obtain help on messages and on miscellaneous error codes.

Work in Two Windows

You can divide your physical screen into two logical windows. Each window operates independently of the other, enabling you to perform multiple functions concurrently.

To open a second window in the region, press the F2 (Split) or F9 (Swap) function key.

When one window takes up the entire screen, the other window is considered *closed*.

Split Screens

Using the SPLIT command, you can perform the following actions:

- Split your screen horizontally and have one window above the other. Move the cursor to a row where you want to split screens, and press F2 (Split).
- Split your screen vertically and have two windows side by side. Move the cursor to any column on the bottom row, and press F2 (Split).
- Return a split screen to single window display in one of the following ways:
 - Move the cursor to the first line on your screen, and press F2 (Split) to minimize the window. The window containing the cursor disappears, and the other window expands to full size.
 - Enter =X to exit one of the windows. Your session with that window ends.

Swap Screens

Using the SWAP command, you can perform the following actions:

- Reverse the dimensions of the active window if you have two windows open and both are visible on the screen, and switch between them.
- Open a second full-screen window if you are currently operating with a single window open, and then switch between them.

To swap two full-screen windows

1. Display one of the panels.
2. Press F9 (Swap).
The primary menu appears.
3. Proceed to the second panel you require and press F9 (Swap).
The first of your swap-panels appears.
4. Press F9 (Swap) to switch between the two swap-panels.

Chapter 2: Managing File Transfer Resources

This section contains the following topics:

- [File Transfer Status Monitor](#) (see page 32)
- [Monitor File Transfer Schedules](#) (see page 37)
- [Schedule Forecasting](#) (see page 39)
- [Interpret the Status of File Transfer Schedules](#) (see page 41)
- [Interpret the Status of Supporting File Transfer Resources](#) (see page 42)
- [Activate and Inactivate a File Transfer Resource](#) (see page 44)
- [Issue Commands to a File Transfer Resource](#) (see page 45)
- [Display a CA XCOM Data Transport Control Library Member](#) (see page 46)
- [Display the MAXLOC, MAXREM, and MAXTASK Parameters](#) (see page 46)
- [List and Manage CA XCOM Data Transport Transfer Requests](#) (see page 46)
- [CONNECT:Direct Security Considerations](#) (see page 48)
- [Display a CONNECT:Direct Network Map](#) (see page 50)
- [List and Manage CONNECT:Direct Processes](#) (see page 50)
- [List and Manage TCP/IP Connections](#) (see page 53)
- [List CONNECT:Mailbox Batches](#) (see page 53)
- [Monitor CONNECT:Mailbox Resources](#) (see page 55)
- [List and Manage CONNECT:Mailbox VSAM Batch Files](#) (see page 56)
- [Monitor Your File Transfer Environment Using the Graphical Monitor](#) (see page 58)

File Transfer Status Monitor

The file transfer status monitor displays the status of the resources defined in the loaded system image.

The resources displayed on the panel depend on the filter selected for the file transfer status monitor. The default filter (FILETRANSFER) displays all of the file transfer resources defined in your region.

SOLVPROD----- Status Monitor : File Transfer Resources -----FT1-0001							
Command ==>				Scroll ==> PAGE			
S=Status L=Log D=Display A=Act T=Term DB=Database ?=List Cmds							
System	Class	Resource	Desired	Actual	Mode	Logical	Ovr
FT1	CDMGR	ALCDUNX1	ACTIVE	ACTIVE	MANUAL	OK	
FT1	CDMGR	DECD1	ACTIVE	ACTIVE	MANUAL	OK	
FT1	CDMON	DECD1.ALCDUN	ALCDUNX1	AVAILABLE AT 09.33			
FT1	CDMON	DECD1.HOLDQ	QUEUE(HOLD) STATUS(ANY) CNT(10) AT 14.20				
FT1	CDMON	DECD1.LISTEN	LISTENER TASK FOUND AT 14.34				
FT1	CDMON	DECD1.RETRYQ	QUEUE(TIMER) STATUS(RETRY) CNT(1) AT 14.34				
FT1	CDMON	DECD1.TCPCON	0 CONNECTIONS CHECKED. ALL OK AT 14.39				
FT1	CDMON	DECD1.TIMERQ	QUEUE(TIMER) STATUS(ANY) CNT(0) AT 14.04				
FT1	CDMON	DECD1.TRANSF	NO TRANSFERS FOUND AT 14.36				
FT1	FTPMGR	FTPSVR	ACTIVE	ACTIVE	MANUAL	OK	
FT1	FTPMON	FTPSVR.LISTE	LISTENER TASK FOUND AT 14.53				
FT1	FTPMON	FTPSVR.TCPCO	0 CONNECTIONS CHECKED. ALL OK AT 15.53				
FT1	FTSCHD	ALCARDSCHEDL	PROC 14.30 REQ:0069 COMP:0001 FAIL:0000				
FT1	FTSMGR	CAFTS1	UNABLE TO COMMUNICATE WITH CAFTS1 14.50				
FT1	FTSMON	CAFTS1.CAAR	UNABLE TO COMMUNICATE WITH CAFTS1 14.50				
FT1	XCMGR	XC3000	ACTIVE	ACTIVE	MANUAL	OK	
FT1	XCMON	XC3000.STALL	NO TRANSFERS FOUND AT 14.05				
F1=Help		F2=Split	F3=Exit	F4=Add	F5=Find		
F7=Backward		F8=Forward	F9=Swap	F11=Right			

Access the File Transfer Status Monitor

To access the file transfer status monitor

1. Enter **M** at the prompt on the NetMaster : Primary Menu.

The Monitors : Primary Menu appears. The menu lists the monitors you can select.

2. Enter **FT**.

The file transfer status monitor displays the status of the resources.

Note: You can also use the /FTMON shortcut to access the monitor.

More information:

[Use the Status Monitor](#) (see page 88)

List Monitors Associated With a Specific Manager

You can view resources associated with a resource manager (owner resource).

To list resources associated with a specific manager

1. Enter **Z** beside a listed resource on the file transfer status monitor.

The Status Monitor : Owner panel appears.

Change the Type of Information Displayed

The file transfer status monitor displays fields or extended messages. The fields display resource state and mode of operation information. Whereas, extended messages display information *about* the state of a resource—extended display messages are specified in the definition of a resource.

Remove the Display of all Extended Display Messages

To remove the display of all extended display messages

1. Enter **EXTDISP OFF** at the command prompt on the file transfer status monitor.

Extended display messages are removed.

Display Extended Display Messages

To display extended display messages

1. Enter **EXTDISP ON** at the command prompt on the file transfer status monitor.

Extended display messages are displayed.

Display Information About File Transfer Resources

You can display information about a selected resource. The information that appears depends on the type of the selected resource.

To display information about a resource

1. Enter **D** beside the resource on the file transfer status monitor.

Note: If a Signon Details panel appears, you must [confirm your CONNECT:Direct signon details](#) (see page 49).

The following table lists the information displayed for a particular resource type:

Resource Type	Information Displayed
CA XCOM manager (XCMGR class)	The Command Entry panel appears. It displays information about the selected CA XCOM region. The display action that is executed when you enter the D command is defined in your resource definition.
CA XCOM transfer request monitor (XCMON class)	A panel appears that lists the requests with the monitored status. You can issue commands against those requests.
CA XCOM stalled transfer monitor (XCMON class)	A panel appears that lists the active transfer requests. You can issue commands against those requests.
CA XCOM TCP/IP connections monitor (XCMON class)	An action list appears for the monitored TCP/IP connections.
CA XCOM TCP/IP listener task monitor (XCMON class)	Status details appear for the monitored TCP/IP listener task.
CA XCOM remote node monitor (XCMON class)	Status information appears for the monitored remote nodes.
CONNECT:Direct manager (CDMGR class)	The Command Entry panel appears. This panel displays information about a managed local CONNECT:Direct for MVS or CONNECT:Direct for z/OS region, or about the link to a managed remote CONNECT:Direct application. The display action that is executed when you enter the D command is defined in your resource definition.

Resource Type	Information Displayed
CONNECT:Direct queue and status monitor (CDMON class)	A panel appears that lists the processes associated with the selected queue. You can issue commands against those processes.
CONNECT:Direct transfer monitor (CDMON class)	A panel appears that lists the processes associated with the Exec queue. You can issue commands against those processes.
CONNECT:Direct TCP/IP connections monitor (CDMON class)	An action list appears for the monitored TCP/IP connections.
CONNECT:Direct TCP/IP listener task monitor (CDMON class)	Status details appear for the monitored TCP/IP listener task.
CONNECT:Direct remote node monitor (CDMON class)	The log of the process that checks the availability of the node appears.
CONNECT:Mailbox VSAM file server (STC class)	The Command Entry panel appears. This panel displays information about a managed local CONNECT:Mailbox VSAM file server application. The display action that is executed when you enter the D command is defined in your resource definition.
CONNECT:Mailbox (CMMGR)	The Command Entry panel appears. This panel displays information about a managed local CONNECT:Mailbox application. The display action that is executed when you enter the D command is defined in your resource definition.
CONNECT:Mailbox Auto Connect Queue monitor (CMMON)	A panel appears listing any queued Auto Connects.
CONNECT:Mailbox BSC Line monitor (CMMON)	A panel appears listing BSC lines used by CONNECT:Mailbox file transfer sessions.
CONNECT:Mailbox SNA Sessions monitor (CMMON)	A panel appears listing the batches in CONNECT:Mailbox SNA file transfer sessions with the monitored remote sites.

Resource Type	Information Displayed
DASD (DASD class)	The Command Entry panel appears. This panel displays information about the DASD. The display command that is executed when you enter the D command is defined in your resource definition.
FTP manager (FTPMGR class)	The Command Entry panel appears. This panel displays information about a managed FTP server region. The display action that is executed when you enter the D command is defined in your resource definition.
FTP connections monitor (FTPMON class)	An action list appears for the monitored TCP/IP connections.
FTP listener monitor (FTPMON class)	Status details appear for the monitored TCP/IP listener port.
FTP remote node monitor (FTPMON class)	The results of the check on the availability of the node appear.
File transfer schedule (FTSCHD class)	A list of monitored files that have completed or failed transfer appears.
FTS manager (FTSMGR class)	The Command Entry panel appears. This panel displays information about the monitoring status of the local CA SOLVE:FTS application, about the managed CA SOLVE:FTS region on the local system, or about the link to a managed remote CA SOLVE:FTS region. The display action that is executed when you enter the D command is defined in your resource definition.
FTS link monitor (FTSMON class)	The Command Entry panel appears. This panel displays information about the link.
Started task (STC class)	The Command Entry panel appears. This panel displays information about the started task. The display command that is executed when you enter the D command is defined in your resource definition.

Resource Type	Information Displayed
Tape (TAPE class)	The Command Entry panel appears. This panel displays information about the tape unit. The display command that is executed when you enter the D command is defined in your resource definition.

More information:

[List and Manage CA XCOM Data Transport Transfer Requests](#) (see page 46)

[List and Manage TCP/IP Connections](#) (see page 53)

[List and Manage CONNECT:Direct Processes](#) (see page 50)

Monitor File Transfer Schedules

File transfer schedules are FTSCHD class resources.

The display of these resources on the status monitor is color coded. Typically, green indicates that files are arriving according to the schedule, while yellow or red suggests problems that require your attention.

To monitor and diagnose a file transfer schedule whose status indicates a problem

1. Enter **L** next to the schedule.

The transient log for the schedule appears, listing messages that indicate what events have occurred for the schedule.

2. Enter **S** next to the message that indicates the problem.

The activity log appears, listing the messages at the time when the problem occurred. These messages can provide you with more information about the problem.

More information:

[Using Logs](#) (see page 75)

Acknowledge a Failure Status

If the status of a schedule appears in red and you know that it is no longer a problem, enter **OK** beside it to set its status color to green.

Display the Next Time a Schedule Starts Monitoring

To find out when a schedule will next start monitoring, enter **NXT** beside it.

A message in the following format appears in the extended display area:

NEXT START ON *day_of_week date AT time*

Note: The command does not change the state of the schedule.

Display Selective Schedules on the File Transfer Status Monitor

You can display only those schedules you want to monitor as follows:

If you want to display ...	Enter ...
All file transfer schedules only	FILTER FTSCHD at the command prompt.
Active schedules only	FILTER ACTSCHEDS at the command prompt.
All active and failed schedules	FILTER SCHEDULEMON at the command prompt.

If you want to remove a particular schedule from your monitor, enter **OFF** beside it. The schedule is stopped and removed from the monitor, but reappears at its next start time.


Update an Active Schedule

You cannot update the definition of a schedule while it is active. If you have to update an active schedule, you must stop it. To stop an active schedule, enter **OFF** beside it. You can then update its definition through the File Transfer Schedule List panel (panel path **/ADMIN.R.FTSCHD**).

Schedule Forecasting

Schedule forecasting enables you to determine when to expect file transfers matching the criteria of an existing file transfer schedule. You can select any combination of systems and date/time ranges to define a criteria. Impacted schedules are listed for analysis.

The following diagram illustrates how file transfer processes are matched to a schedule.



In this example:

- File transfer processes 1 and 5 are not impacted because they are not active during the specified criteria.
- File transfer processes 2, 3, 4, and 6 are impacted because they are active during the specified criteria.

Forecast Types

There are two sets of forecast:

- Forecast by time
- Forecast by system

Forecast File Transfer Schedules

When you schedule system maintenance, you may want to know how it affects file transfers. Forecasting lets you find out whether any file transfers are affected during that time on those systems you plan to maintain.

To forecast file transfer schedules

1. Enter **/FTHIST.SF**.

The Schedule Forecast Facility appears.

2. Specify the range of date and time over which you want to make the forecast, and then press F5 (SysImage).

A list of system images appears.

3. Enter **S** beside the images where you want to make the forecast, and then press F3 (Exit).

You are returned to the previous panel with the specified criteria.

4. Press F6 (Action).

A list of schedules forecasted for the specified criteria appears.

Note: For more information about the list, press F1 (Help).

Interpret the Status of File Transfer Schedules

CA NetMaster FTM uses extended display messages to indicate the status of file transfer schedules.

The message has the following format:

xxxx hh.mm REQ:nnnn COMP:nnnn FAIL:nnnn

xxxx

Displays the following stages of file transfer monitoring:

- PREP—pre-processing
- PROC—processing
- POST—post-processing
- END—end of monitoring

hh.mm

Displays the time of the last status update.

REQ:nnnn

Displays the required number of files to be transferred for the schedule.

COMP:nnnn

Displays the number of completed transfers.

FAIL:nnnn

Displays the number of failed transfers.

Interpret the Status of Supporting File Transfer Resources

Supporting file transfer resources include the following classes of resources:

- CDMGR and CDMON (CONNECT:Direct manager and monitor)
- CMMGR and CMMON (CONNECT:Mailbox manager and monitor)
- DASD (DASD)
- FTPMGR FTPMON (FTP manager and monitor)
- FTSMGR and FTSMON (FTS manager and monitor)
- STC (Communications Server tasks, CA TCPaccess CS tasks, and CONNECT:Mailbox VSAM file server)
- TAPE (tape units)
- XCMGR and XCMON (CA XCOM manager and monitor)
- FTSCHD (File Transfer Schedule)

The statuses of resources appear in the following ways:

- File transfer status monitor fields
- Extended display messages
- Colored resources and messages

Interpret File Transfer Status Monitor Fields

The status of a resource can be determined by observing the displayed status fields.

Note: Extended display must be disabled to view the status fields.

The default status fields are as follows:

Desired

This field displays the desired state of the file transfer resource. The desired states can be ACTIVE or INACTIVE.

Actual

This field displays the actual state of the file transfer resource. The actual state of the resource can be ACTIVE, STARTING, STOPPING, INACTIVE, DEGRADED, FAILED, or UNKNOWN.

Mode

This field displays the mode in which the resource is operating. The modes can be AUTOMATED, MANUAL, or IGNORED. When in AUTOMATED mode, the resource is controlled by the region. When in MANUAL or IGNORED mode, the resource is controlled by you.

Logical

This field specifies the logical state of the region. The displayed logical state is determined by the state of the Desired, Actual, and Mode fields for the file transfer resource. The logical state can be UNKNOWN, INERROR, FAILED, ATTENTION, DEGRADED, PENDING, STARTING, STOPPING, or OK.

Note: The determination of a logical state can be customized by your system administrator. To view the method used to determine the logical state of the resources in your region, enter **/ASADMIN.A** at the command prompt and view the mode attributes tables.

Interpret Colored Resources and Messages

Each file transfer resource appears in a color which reflects its logical state. Resources that appear in green are in a logical state of OK. The color in which extended messages appear is specified in the resource definition. Extended messages overwrite the status monitor fields. If resources appear in a color other than green, they may require attention.

To view the colors assigned to particular states

1. Enter **/ASADMIN.A** at the command prompt.
The logical state attributes table appears.

Activate and Inactivate a File Transfer Resource

You can manually activate or inactivate a file transfer resource. Manual activation and inactivation is available only when the defined resource is in the MANUAL operation mode.

Note: For information about operation modes, see the online help on resource definitions.

To determine the mode of operation for a particular resource, observe its Mode field on the file transfer status monitor.

Note: You can activate a monitor resource only if its owner manager is active.

Activate a File Transfer Resource

To activate a resource

1. Enter **A** beside the resource.
A confirmation message appears.
2. Press Enter to confirm the activation.
The resource is activated.

Note: The A command executes the activation command specified in the Activation Details panel of the resource definition. For more information, see the online help on resource definitions.

Inactivate a File Transfer Resource

To inactivate a resource

1. Enter **T** beside the resource.
A confirmation message appears.
2. Press Enter to confirm the inactivation.
The resource is inactivated.

Note: The T command executes the inactivation command specified in the Inactivation Details panel of the resource definition. For more information, see the online help on resource definitions.

Issue Commands to a File Transfer Resource

You can use the **CMD** command to issue commands to the following file transfer resources from your file transfer status monitor:

- Managers
- TCP/IP provider

Example: Display Statistics of a **CONNECT:Direct** Region

To display the statistics of a **CONNECT:Direct** region

1. Enter **CMD** beside the desired CDMGR resource at the file transfer status monitor.
The **CONNECT:Direct** Commands panel appears.

2. Enter **CMD INQUIRE STATISTICS** at the command prompt.

The current status of the selected **CONNECT:Direct** statistics logging facility appears.

Note: The Commands panel is profiled to display write-to-operator (WTO) messages generated by the file transfer resource. For example, if you issue **CMD** against a **CONNECT:Direct** manager resource, the panel updates with any WTO messages generated by the **CONNECT:Direct** region for which the manager resource is defined.

Issue Commands to a Remote **CONNECT:Direct** Region

If you enter **CMD** beside a remote **CONNECT:Direct** CDMGR resource, the Command Entry panel appears.

To issue **CONNECT:Direct** commands to **CONNECT:Direct** running on a remote system

1. Enter the **CONNECT:Direct** command at the command prompt on the Command Entry panel.

The command is issued.

Note: For available commands, see the user's guide for the **CONNECT:Direct** product to which you want to issue commands.

Display a CA XCOM Data Transport Control Library Member

You can display information about a CA XCOM Data Transport region, such as a control library member.

To display the control library member of a CA XCOM Data Transport region

1. Enter **LST** beside the XCMGR resource.

The XCOM : List Display appears.

Note: You can use the DIS and ENA commands to disable and enable control library members.

Display the MAXLOC, MAXREM, and MAXTASK Parameters

You can display information about a CA XCOM Data Transport region, such as MAXLOC, MAXREM, and MAXTASK parameters.

To display the parameters

1. Enter **INQ** beside the XCMGR resource.

The parameters appear.

Note: To change these parameters, enter **DFT** beside the resource.

List and Manage CA XCOM Data Transport Transfer Requests

You can list monitored CA XCOM Data Transport transfer requests.

To list the requests

1. Enter **D** beside an XCMON resource on the file transfer status monitor.

The requests are displayed.

2. (Optional) To refresh the list, press F6 (Refresh).

XCMGR Transfer Requests

You can enter any of the following commands beside an XCMGR resource to list its transfer requests:

VA

Displays all requests.

VAC

Displays requests that are active.

VH

Displays requests that are held.

VI

Displays requests that are inactive.

VS

Displays requests that are suspended.

Manage Transfer Requests

You can manage the listed CA XCOM Data Transport requests by using the following actions:

A (Alter)

Modifies the details of a request.

D (Delete)

Deletes a request.

H (Hold)

Holds a pending transfer.

R (Release)

Releases a held transfer.

R (Resume)

Resumes a suspended transfer.

SP (Suspend)

Suspends an active transfer.

T (Terminate)

Stops and purges an active transfer immediately.

V (View) or S

Displays a panel that provides details of a request.

CONNECT:Direct Security Considerations

When you use any function that requires authorized access to CONNECT:Direct, you must confirm your CONNECT:Direct signon details. This is necessary only once during each session for each CDMGR defined; however, if you use the CLR command to clear your security access, you need to reconfirm your signon details the next time you use one of these functions.

Confirm Your CONNECT:Direct Signon Details

The first time (within a session) you enter a command needing security confirmation, a Signon Details panel appears:

```
.- CONNECT:Direct Signon Details -----  
|  
| User ID ..... USER1  
| Password .....  
| Case Sensitive ..... NO          (Yes/No)  
| Press F6 to Confirm or F12 to Cancel  
|  
-----
```

To confirm your signon details

1. Complete the following fields:

User ID

Specifies your user ID.

Password

Specifies your password in the correct case.

Case Sensitive

Specifies whether the password is case sensitive.

2. Press F6 (Confirm).

You can then continue your processing.

Clear Your CONNECT:Direct Signon Details

After you confirm your CONNECT:Direct signon details for a particular CDMGR resource during a session, you retain your security access to that CDMGR for the duration of the session; however, if you do not want to leave your CONNECT:Direct security access available, you can clear it.

To clear your CONNECT:Direct security access

1. Enter **CLR** (Clear) next to the CDMGR for which you have confirmed your signon details.

A message appears, confirming that your signon details have been cleared.

Note: If you clear your security access, you are prompted to confirm your signon details again the next time you want to use a function requiring authorized access to CONNECT:Direct.

Display a CONNECT:Direct Network Map

To display the network map of a CONNECT:Direct region:

1. Enter **NM** beside a CDMGR resource at the file transfer status monitor.

The Specify A NETMAP Node Name panel appears.

2. Complete the following field:

Node Name

Specifies the name of the node you want to display:

- * displays all nodes in the network map for this manager resource.
- *prefix** displays a range of nodes that have the same prefix in the network map for this manager resource.
- *nodename* displays a specific node contained in the network map for this manager resource

Press F6 (Action).

The nodes are displayed.

Display the Initialization Parameters of a CONNECT:Direct Region

To display the initialization parameters of a CONNECT:Direct region

1. Enter **IIP** beside the desired CDMGR resource at the file transfer status monitor.

The results of the INQUIRE INITPARMS command appear.

List and Manage CONNECT:Direct Processes

You can display processes for a CONNECT:Direct resource on the file transfer status monitor. The processes displayed are those associated with the monitored CONNECT:Direct queue.

You can also monitor processes of a particular status in a specific queue type. The process status type is specified in the resource definition.

Note: When you use any function that requires authorized access to CONNECT:Direct, you must confirm your CONNECT:Direct signon details.

List Processes

You can list processes in CONNECT:Direct queues that are monitored by CA NetMaster FTM.

To list **CONNECT:Direct** processes

1. Enter **D** beside a CDMON queue monitor.

The processes appear.

You can also enter commands beside a CDMGR resource to list its queued processes. For example, the VH command lists processes in the Hold queue. To view the commands available for listing queued processes, enter **?** beside the CDMGR resource.

Manage Processes

You can manage the listed CONNECT:Direct processes by using the following actions:

C (Change)

Modifies the parameters of a process that is not executing. You can also release a held process or restart a failed process using this command.

D (Delete)

Deletes a process that is not executing from the queue.

DF (Delete/Force)

Forcibly terminates and deletes the process from the Exec queue.

DH (Delete/Hold)

Terminates a process on the CONNECT:Direct for NT executing queue and moves it to the hold queue.

FP (Flush Process)

Terminates an executing process.

FPF (Flush Process Force)

Force terminates an executing process.

H (Hold)

Places a process that is not executing on the Hold queue.

R (Release)

Releases a held process.

SP (Suspend Process)

Terminates execution and places an executing process on the Hold queue.

Note: Not applicable to processes on distributed systems.

SPF (Suspend Process Force)

Force terminates an executing process and places that process on the Hold queue.

Note: Not applicable to processes on distributed systems.

V (View)

Displays a panel that provides details of the selected process. An F6 (Refresh) function key is available on that panel for you to refresh the displayed information.

List and Manage TCP/IP Connections

The TCP/IP : Connection List displays information about the current state of active connections for the monitored CA XCOM Data Transport, CONNECT:Direct, or FTP region. You can investigate problems occurring on any listed connection by using the actions on the TCP/IP : Connection List. These actions can be used as tools to investigate a file transfer problem.

To list TCP/IP connections

1. Do *one* of the following:
 - Enter **D** beside a TCP/IP connections monitor resource.
 - Enter **VIP** beside a CDMGR or FTPMGR resource.

The TCP/IP : Connection List appears.

Drop a Connection

Where an error condition exists (for example, the connection seems to have stalled), it may be necessary to drop that connection and have the user reconnect. You must have the appropriate security level to drop a connection.

To drop a connection

1. Enter **Z** beside the connection on the connection list.

A confirmation dialog appears.
2. Press Enter to confirm.

A message informing you that the connection has been dropped appears, and the connection is highlighted as having been dropped.

List CONNECT:Mailbox Batches

You can list and manage CONNECT:Mailbox batches from the file transfer status monitor.

To list CONNECT:Mailbox batches

1. Enter **DIR** beside a CMMGR resource on the Status Monitor.
2. Enter the required mailbox ID and press F6 (Action).

The Mailbox Batch List appears.

Manage CONNECT:Mailbox Batches

To manage CONNECT:Mailbox batches you can issue the following line commands against one or more batches:

I

Invokes an end of batch agent request

C

Initiates an Auto Connect request

S

Provides an explanation of the status flags

R

Sets the status flag to allow the batch to be requested by a remote site, or transmitted by a host-initiated Auto Connect

D

Sets the status flag to show the batch has been deleted

T

Sets the status flag to indicate that the batch has been transmitted

E

Sets the status flag to indicate that the batch was extracted by the EXTRACT utility

M

Sets the status flag to indicate that the batch is available for multiple transmissions

The following commands turn the corresponding status flags off:

NR

ND

NT

NE

NM

To issue any of these line commands against all listed batches, at the command prompt, enter **All x**, where x is one of the following commands:

R

D

T

E

M

Initiate an Auto Connect

You can start a host-initiated Auto Connect from the file transfer status monitor. By using the CON command you can override the *CONNECT record parameters specified in your Options Definitions File (ODF).

To initiate an Auto Connect

1. Enter **CON** beside a CMMGR resource on the status monitor.

The File Transfer : Auto Connect panel appears.

2. Complete the following fields:

List Name

Specifies the list name for the Auto Connect. The name must be defined in the ODF.

Mailbox ID

Specifies the mailbox ID of the batches to send.

User Batch ID

Specifies the user batch ID of the data to send.

Press F6 (Action).

Batches are transmitted according to your selection.

Note: You can also issue the CON command from the Mailbox Batch List command line.

Monitor CONNECT:Mailbox Resources

You can display CONNECT:Mailbox monitors from the status monitor. The following CONNECT:Mailbox monitors are available:

ACQUEUE

Displays the Auto Connect Queue monitor. From here you can display all of the queued Auto Connects associated with a CONNECT:Mailbox manager and delete a queued Auto Connect queue.

SNASESS

Displays SNA Sessions monitor. From here you can display all the SNA sessions associated with a CONNECT:Mailbox manager.

BSCLINES

Displays BSC Lines monitor. From here you can display all BSC lines associated with a CONNECT:Mailbox manager, start a line, and stop a line.

Display CONNECT:Mailbox Monitors

To display CONNECT:Mailbox monitors

1. Enter **Z** beside the required CONNECT:Mailbox manager on the status monitor.
The selected monitor appears.
2. Enter **D** beside the CONNECT:Mailbox monitor that you want.
The panel lists the details applicable to the selected monitor.

List and Manage CONNECT:Mailbox VSAM Batch Files

As batches are added and deleted from the VSAM batch queues, it may be necessary to recover space. You can monitor and maintain VSAM files from the VSAM File Statistics panel.

To access the VSAM File Statistics

1. Enter **VSS** next to the required CMMGR resource from the resource monitor.
The VSAM File Statistics panel appears.

The following table lists available commands and the file types the commands can be issued against:

Command	Description	File Type
A	Allocates a VSAM file to CONNECT:Mailbox	VBQ, VLF
AC	Allocates and assigns a data file as a current collection file or logging file to CONNECT:Mailbox	VBQ, VLF
D	Deallocates a file from CONNECT:Mailbox	VBQ, VLF
LC	Executes and displays the results of an IDCAMS LISTCAT report	All types
AR	Displays the Assisted REORG Facility panel	VBQ, VLF

Note: You cannot deallocate a VBQ and VLF file if it is the current collection or log file.

Maintain VSAM Batch Files Using the Assisted REORG Facility

To use the Assisted REORG Facility

1. Enter **AR** beside the required VSAM file and press F6 (Confirm).

The Summary of Execution Status panel appears detailing the default data set names to be used during the reorganization

Note: If the file has not been deallocated, you are prompted to deallocate the file.

2. Press F6 (Confirm).

The reorganization is executed.

3. Do *one* of the following:

- Press F6 (AutoExec) to reorganize automatically
- Enter **E** (Execute) beside each task to manually execute each task.

As each task completes, the status field is updated and the task is highlighted.

Note: The status can be:

- Pending Review—user input required if the defaults are not acceptable
- Pending—waiting for execution
- In Progress—the task is in progress
- Error—the task ended in error and is highlighted in red
- Done—the task completed successfully and is highlighted in white

4. Press F3 (Exit)..

Fix a Task That Ends in Error

If a task ends in error

1. Enter **B** beside the task that has ended in error.
Browse the results of the task.
2. Enter **R** beside the task to reset the default values of the task.
3. Make changes to the task, as required, and press F6 (AutoExec).

Note: If the reorganization is stopped manually before all tasks are complete, a warning message is issued indicating the next task to be completed or the last completed task. You may need to complete the remaining tasks offline.

Monitor Your File Transfer Environment Using the Graphical Monitor

The graphical monitor lets you monitor file transfer resources by groups. For example, suppose you are transferring files for different organizations and you want to group these transfers by organization. You can group the transfers for each organization in a resource group and attach the group to an icon on a panel that can be displayed on the graphical monitor. The icons then enable you to monitor the file transfers by organization.

You create resource groups, icons, and icon panels from the Graphical Monitor : Administration Menu. After you have created an icon panel, you can display it on the graphical monitor.

Note: For information about how to customize the graphical monitor, see the *Administration Guide*.

More information:

[Access the Graphical Monitor](#) (see page 86)

[Change to a Different Default Icon Panel](#) (see page 88)

Chapter 3: Monitoring Active File Transfers

This section contains the following topics:

[File Transfer Monitor](#) (see page 59)

[Display Active File Transfers](#) (see page 60)

[How to Display the Estimated Completion Time](#) (see page 60)

[Filter File Transfers](#) (see page 60)

[Sort Active File Transfers](#) (see page 63)

[Change the List Format](#) (see page 63)

[Set Up the File Transfer Monitor in Your User Profile](#) (see page 66)

File Transfer Monitor

The active file transfer monitor lists all of the active file transfers in your environment. From this list you can perform the following actions:

- Select a specific file transfer, and:
 - Display the details of the transfer.
 - Exclude the file transfer from the list.
 - Display the estimated completion time with ETA monitoring (*not* available to FTP transfers using IBM's Communications Server).
 - Terminate the transfer (CA XCOM Data Transport, CONNECT:Direct, or CA TCPaccess FTP Server transfers only). Users belonging to the \$RMBUSER and \$RMMON user groups cannot terminate a transfer.

Transfer termination and ETA monitoring require the definition of the manager for the region that provides the file transfer events.

- Filter transfers so that only those that meet specific criteria are listed.
- Sort the listed transfers.
- Change the list format to suit your specific needs.
- Define a monitoring profile to suit your specific needs.

Note: Monitoring is not available for the following file transfers:

- Host-initiated CONNECT:Mailbox Auto Connect transfers
- CONNECT:Direct for Windows NT transfers
- CONNECT:Direct for UNIX transfers

Display Active File Transfers

To display active file transfers

1. Enter **/AFTMON** at the prompt.
The File Transfer Monitor panel appears.

How to Display the Estimated Completion Time

The ETA monitor displays the progress of a selected file transfer. The ETA displays:

- The number of bytes, blocks, or records transferred
- The time taken on the transfer so far
- The percentage completed
- The estimated time for the transfer to complete
- An optional graphic fuel gauge of the transfer's progress (set by the \$RF FTMONITOR parameter group)

To display the estimated completion time for a file transfer

1. Enter **M** beside the active file transfer on the File Transfer Monitor panel.
The display is updated to acknowledge that ETA monitoring has been requested. This is followed by confirmation that it has started.
2. (Optional) If the monitor does not know the size of the file being transferred, you are prompted for the size. Enter the estimated size of the file in the units of measurement used by the file transfer.

Important! If you are monitoring a compressed file, specify its estimated compressed size. If the estimated size is exceeded, the monitor displays 99% until the transfer is complete. If this occurs, turn the monitor off, re-enter the file size, and start monitoring again.

Filter File Transfers

You can filter the file transfers so that only those that meet the criteria you set are listed. You can apply an existing filter or create a new one.

Apply a Filter to the File Transfer Monitor

To apply a file transfer monitor filter, use the FILTER command.

This command has the following format:

`FILTER filtername.`

filtername

Specifies the name of the filter that you want to use.

Example: FILTER Command

To apply a filter called PRODSOURCE, use the command FILTER PRODSOURCE.

Apply a File Transfer Monitor Filter from a List

To select and apply a filter from a list of file transfer monitor filters

1. Enter **FILTER** at the File Transfer Monitor panel command prompt.
The File Transfer Monitor Filter List panel appears.
2. Select the required filter and press Enter.
The File Transfer Monitor panel appears showing the name of the applied filter.

Create a New File Transfer Monitor Filter

To create a new file transfer monitor filter

1. Enter **/FTADMIN.F** at the command prompt.
The File Transfer Monitor Filter List panel appears.
2. Press F4 (Add).
The File Transfer Monitor Filter panel appears.
3. Complete the following fields:

Name

Specifies the name of the filter.

Description

Briefly describes the filter.

Create the filter in the Filter Expression section of the panel.

Note: To determine the valid values for a field, type ? in the field and press Enter.
For more information about creating a filter expression, press F1 (Help).

Press F3 (File).

The filter is saved.

Sort Active File Transfers

You can sort the list of file transfers to three levels. You can sort on the following fields:

- **JOBNAME**—the file transfer product job name
- **PRODUCT**—the file transfer product
- **SRCADDR**—the source address or node
- **SRCFNAME**—the source data name
- **STARTTIME**—the start time
- **SYSTEM**—the NetMaster region which originated the event
- **TGTADDR**—the target address or node
- **TGTFNAME**—the target data name
- **USER**—the initiating user ID
- **XFRID**—the file transfer ID

To sort the contents of the list, use the **SORT** command. The format of the **SORT** command is **SORT *field, field, field***.

For example, to do a primary sort on the source address, with a secondary sort on the time that the transfer started, use the command: **SORT SRCADDR, STARTTIME**

The default sort order is by **STARTTIME**.

Change the List Format

The list format specifies the appearance of the active file transfer monitor. You can use the default list format, apply an existing list format, or create a new one. The default list format is:

- Active file transfers appear in green.
- File transfers that fail appear in red and remain visible for 30 minutes.
- Completed file transfers appear in blue and remain visible for 2 minutes.

Note: To change the amount of time file transfers remain visible, you must customize the **FTMONITOR** parameter group.

Apply a List Format to the File Transfer Monitor

To apply a list format, use the FORMAT command.

This command has the following format:

FORMAT *formatname*

formatname

Specifies the name of the format.

Example: FORMAT Command

To apply a list format called OPER01, use the command FORMAT OPER01.

Apply a List Format from a Selection List

To select and apply a list format from a list

1. Enter **FORMAT** at the File Transfer Monitor panel command prompt.

The Lists panel appears.

2. Select the required format from the list of formats.

The File Transfer Monitor panel appears in the new list format.

Create a New List Format

To create a new list format

1. Enter **/FTADMIN.L** at the command prompt.

The List Definition List panel appears.

2. Press F4 (Add).

The List Definition panel appears.

3. Complete the following fields:

List Name

Specifies the name of the list.

Description

Briefly describes the list.

Service Procedure

Specifies the name of the NCL procedure that is executed when a list appears using this definition.

Press F8 (Forward) three times.

The List Format panel appears.

4. Specify the headings, as you would like them to appear on the monitor. These lines are the heading lines.

Specify the corresponding variables beneath the headings. Specify the variables in a single line. These lines are the entry lines. See the online help for a list of valid variables.

Press F3 (Exit).

The list format is saved.

Set Up the File Transfer Monitor in Your User Profile

You can specify your default monitor filter, the list format, and the sort criteria for the active file transfers in your user profile.

To update your profile for the active file transfer monitor

1. Enter **/AFTMON** at the command prompt.
The File Transfer Monitor panel appears.
2. Enter **PROFILE** at the command prompt.
The File Transfer Monitor Profile panel appears.
3. Complete the following fields:

File Transfer Monitor Filter

Specifies the name of the filter. To select from a list of filters, enter **?**.

Monitor List Format

Specifies the name of the format. To select from a list of formats, enter **?**.

Transfer Sort Criteria

Specifies the fields on which to sort the list. The fields are listed in sort order.
To select from a list of fields, enter **?**.

Press F3 (File).

The File Transfer Monitor panel appears with the monitor filter, the list format, and the sort criteria applied. The monitor defaults to these values each time it is started.

Chapter 4: Managing Alerts

This section contains the following topics:

[Alert Monitor](#) (see page 68)

[Access the Alert Monitor](#) (see page 68)

[Sort Alerts](#) (see page 69)

[Filter Alerts](#) (see page 69)

[Change the Display Format](#) (see page 69)

[Change the Alert Monitor Profile Using the User Profile Menu](#) (see page 70)

[How to Work with Alerts](#) (see page 70)

[Display Alert Details](#) (see page 71)

[Access the Transient Log from the Alert Monitor](#) (see page 71)

[Raise a Trouble Ticket for an Alert](#) (see page 72)

[Add Operator Notes to an Alert](#) (see page 72)

[Close Alerts](#) (see page 73)

[Display Alert History](#) (see page 73)

Alert Monitor

The Alert Monitor provides an integrated, correlated event notification system that indicates to operators that a problem has occurred and that some action needs to be taken. Such alerts, known as active alerts, are displayed on the Alert Monitor.

The Alert Monitor refreshes your screen each time an alert arrives. The clock in the title line indicates when the screen was refreshed last.

The title line of the Alert Monitor includes a total indicator, which shows the total number of alerts and the total number of alerts of each severity level. For example, (43: 5 23 8 7) means that there are a total of 43 alerts, comprising 5 severity one, 23 severity two, 8 severity three, and 7 severity four. Each severity level appears in a different color. The following illustration shows an example:

```
PROD1 (23.53.32)----- Alert Monitor (43: 5 23 8 7 ) -----Link: *MULTIPLE*
Command ==>                                           scroll ==> PAGE

          S/B=Browse T=Track N=Notes A=Analyze TT=TroubleTicket C=Close ?=More
Time      Description                                Resource                                Track
23 51 27  IPNODE: RINGRTT 261 ms 48% below HOURL VAL CL 02
```

The Alert Monitor can initiate actions such as starting recovery procedures and creating trouble tickets, either automatically or manually.

In a multisystem environment, you can monitor active alerts from all linked regions in a focal point region. You can monitor only local active alerts in a subordinate region.

Alerts that were raised before the region was shut down are not displayed on the Alert Monitor when the region restarts, but are displayed on the Alert History panel. The alert history contains information about all alerts.

Access the Alert Monitor

The Alert Monitor lets you know of problems that have occurred in your environment. You can then take appropriate action based on the alert information.

To access the Alert Monitor

1. Enter **/ALERTS** at the prompt.

The monitor appears displaying any alerts.

You can also access the Alert Monitor by issuing the AL command against a resource from a resource monitor. The monitor displays the alerts for that resource.

Sort Alerts

Alerts are color coded by severity. They are sorted in order of severity, then time—the most severe alerts are listed first, then, in each category of severity, the most recent of the alerts are listed first.

To change the sort order, use the **SORT** command.

To list the column fields by which you can sort, enter **SORT ?**.

Filter Alerts

You can restrict the alerts displayed by using filters. When you apply a filter, the filter name appears on the right of the Alert Monitor and the totals in the title line reflect the number of alerts displayed under the filter.

To filter alerts, enter the following command at the command prompt:

```
FILTER filter_name
```

To remove the applied filter, enter **FILTER NONE**.

Note: To display a selection list of filters, enter **FILTER**.

Change the Display Format

Display format determines what and in what order information columns are displayed.

To change the alert monitor format, enter the following command at the command prompt:

```
FORMAT format_name
```

To return to the default format, enter **FORMAT DEFAULT**.

Note: To display a selection list of formats, enter **FORMAT**.

Change the Alert Monitor Profile Using the User Profile Menu

To change your alert monitor profile using the User Profile Menu

1. Enter **=U.UP** from any panel.
The Panel Display List appears.
2. Enter **S** beside Alert Monitor Profile.
The Alert Monitor Profile panel appears.
3. Complete the following fields:

Monitor List Filter

Specifies the name of the default filter.

Monitor List Format

Specifies how and what is displayed.

Alert Sort Criteria

Specifies the order in which the alerts are displayed.

Press F3 (File).

The changes to your user profile are saved.

How to Work with Alerts

The Alert Monitor displays the alert when it arrives. An alert can be closed automatically by the region (when it recognizes that the problem that caused the alert no longer exists) or manually by the operator. When an alert is closed, it is removed from the active alert monitor. However, it is still accessible from the Alert History panel.

Typically, when an alert arrives, do this:

1. Enter **B** (Browse) beside the alert to find out whether any suggested recommended actions are provided.
2. Enter **A** (Analyze) beside the alert to diagnose it. Diagnosis displays additional information for some alerts.
3. Enter **T** (Track) beside the alert to indicate to other users that you will be working on it. Your user ID is displayed in the Track column.
4. Perform any necessary actions to remove the alert condition. For information about actions, press F1 (Help).
5. Enter **N** (Notes) beside the alert to view or record notes that provide future reference information about this alert in the alert definition.
6. Enter **C** (Close) beside the alert after the alert condition is resolved.

Display Alert Details

The Alert Display describes an active alert and provides information about its generation time and its identity. An alert comes with the following information:

- General information such as severity level, the source of the alert, update history, and number of occurrences
- Possible causes of the alert and any recommended actions

To display the Alert Display

1. Enter **B** or **S** beside an alert on the Alert Monitor panel.

The Alert Display appears.

Note: For information about the fields, press F1 (Help).

Print Alert Details

To print details about the displayed alert

1. Enter **PRINT** at the command prompt.

The Confirm Printer panel appears.

2. Specify your printing requirements, and then press F6 (Confirm).

The details are sent to the printer.

Access the Transient Log from the Alert Monitor

If a monitored resource generates an alert, you can access the corresponding transient log for the affected resource from the Alert Monitor.

To access the transient log

1. Enter **TL** beside the alert.

The transient log appears.

Raise a Trouble Ticket for an Alert

If your system administrator has implemented the interface for raising a trouble ticket, you can request a trouble ticket as defined to your region.

Note: For information about how to implement the trouble ticket interface, see the *Administration Guide*.

To raise a trouble ticket

1. Enter **TT** next to the alert.
The Alert Monitor : Trouble Ticket Details panel appears.
2. Enter the details of the trouble ticket and press F6 (Confirm).
The trouble ticket is raised.

Add Operator Notes to an Alert

You can add notes to an alert for future reference. For example, you may want to leave the next operator some notes about an alert that has not been closed. Notes are also added automatically to provide a history of the actions performed on the alerts.

When an alert is closed, the severity and description of the alert are added to the notes so that you can easily identify which alert has been closed. When an alert severity changes, the description is added to the alert notes.

To add notes to an alert

1. Enter **N** beside the alert.
The Alert Notes panel appears.
2. Press F4 (Add).
The panel becomes editable.
3. Enter your notes about the alert, and press F3 (File) when you have finished.
The notes are saved with the alert.

Note: For information about how to use the editor, see the online help.

Close Alerts

Alerts can be closed automatically by the region or manually.

For example, an alert might be generated because a monitoring threshold is exceeded. When the condition is corrected, the alert is closed automatically. Another alert might be a reminder alert and needs to be closed manually.

To close an alert

1. Enter **C** beside the alert.

The alert is closed.

To close multiple alerts

1. Enter **CLOSE** at the Command prompt.

The Valid Value List panel appears.

2. Select ALL to close all displayed alerts or a severity level to close alerts with that level.

The Command Confirm panel appears.

3. Press F6 (Confirm).

The targeted alerts are closed and removed from the monitor.

Display Alert History

The alert history lists all alerts, both active and closed, that occurred during a predefined period.

To view the alert history

1. Press F4 (History) from the alert monitor.

The alerts for the current date appear. If you want to display the alerts for the other dates, use the DATE command (for example, DATE *yymmdd*).

Note: For more information about the command, see the online help.

2. (Optional) Enter **N** beside an alert to view the history of actions performed on it.

The Alert Notes panel appears.

Note: The length of time an alert is kept in the alert history log is set by your administrator.

Chapter 5: Using Logs

You can access various logs to assist in solving problems.

This section contains the following topics:

[Display the File Transfer Log](#) (see page 75)

[Display an Activity Log](#) (see page 77)

[Display a Transient Log](#) (see page 78)

[Change Logging Options](#) (see page 81)

[Merge Transient Logs](#) (see page 82)

Display the File Transfer Log

The file transfer log provides an historical view of file transfer related activities for the selected file transfer region. One file transfer log is created for each CA NetMaster FTM region. This means that if multiple CA XCOM Data Transport, CONNECT:Direct, FTP server, and CA SOLVE:FTS regions are defined to a system image, all messages generated by those regions are saved to one file transfer log.

To display the file transfer log

1. Do *one* of the following:
 - Enter **FTL** beside a listed file transfer resource on the file transfer status monitor to display the file transfer log entries for that resource.
 - Enter **FTLOG** at the command prompt to display the whole file transfer log.

Note: You can ignore failure messages due to a \$RF* CONNECT:Direct process. These messages are the results of polling a defined CONNECT:Direct remote node (CDMON resource of type REMOTE-NODE).

Browse the File Transfer Log Online

The aids available for you to browse the file transfer log online are similar to those available for [browsing the activity log online](#) (see page 77).

Suppress CONNECT:Direct Messages Logged to the File Transfer Log

You can suppress CONNECT:Direct messages from being logged to the file transfer log using the CDEVENTS parameter group. You can specify which type of CONNECT:Direct messages are logged to the file transfer log.

Note: For more information, see the *Administration Guide*.

More information:

[Suppress Messages Logged to the Activity Log](#) (see page 78)

Access Activity Log from the File Transfer Log

You can find out about other activities that were occurring at the time a file transfer message is logged by accessing the activity log.

To access the activity log from the file transfer log

1. Place the cursor on the message you want to query and press F4 (ActLog).
The activity log appears.

Display an Activity Log

The activity log provides a historical view of the system activities associated with all resources monitored by the region. It records all commands, responses to commands, and messages that occur in your regions. You can display an activity log from the Historical Data : Primary Menu or OCS. By accessing the activity log, you can browse through recent activity to assist you in locating information and analyzing problems.

To display the activity log in the current region

1. Enter **H** at the command prompt on the primary menu.
The Historical Data : Primary Menu appears.
2. Enter **L**.
The activity log appears with the last logged activities. A message also displays the day, date, and time when the region was last initialized.
3. Press the F8 (Forward) and F7 (Backward) function keys to scroll through the log for the current day and for previous days.

Note: You can also enter the **/LOG** shortcut at the command prompt to display the current activity log

If you want to access the log in a linked region, identify the region in the Link Name field on the Historical Data : Primary Menu.

Browse the Activity Log Online

The following aids are available to help you use the activity log:

- Forward and backward scroll
- Various display formats
- Highlighting log records
- Log filter to restrict the records displayed
- Positioning by date or time, either absolute or relative
- Positioning by labels set in the log
- Searching forward or backward for text
- Selective printing of log records

Note: For detailed information about these aids, see the online help.

Suppress Messages Logged to the Activity Log

You can suppress messages logged to the activity log using EventView rules. This lets you log only those messages generated by file transfer resources.

Note: For more information, see the *Administration Guide*.

More information:

[Suppress CONNECT:Direct Messages Logged to the File Transfer Log](#) (see page 76)

Record Additional Information in the Activity Log

You can use the LOG command to record additional information in the log that is outside the scope of that recorded by default. For example, enter the following at the prompt:

```
LOG PRODUCTION LINK TO LOS ANGELES DOWN FOR MAINTENANCE
```

This produces the following entry in the log for the time the command was issued:

```
LOG ENTRY : PRODUCTION LINK TO LOS ANGELES DOWN FOR MAINTENANCE
```

You can record a message up to 256 characters long.

Display a Transient Log

The transient log provides a real-time view of the activity associated with a particular resource. You can display the transient log from your monitor. This log and the activity log contain messages and other information associated with a resource. The logs help you diagnose problems (for example, resource failure).

To display the transient log

1. Enter **L** beside a resource on the monitor.
The Transient Log Browse panel appears for the selected resource. The panel displays messages in chronological order.
2. (Optional) Enter **L** beside a message in the transient log to access the activity log to see what was happening in the system at that time.

Set Criteria to Display Logged Messages Selectively

When you access the transient log of a resource, you are profiled to view all messages logged for that resource. You can limit the number of messages you see in the current session by profiling for certain criteria.

To set profile values

1. Enter the **PROFILE** command at the prompt.
A panel appears displaying the current profile setting.
2. Change the settings, as required.

Note: For information about the settings, see the online help.

You can also supply the profile values directly by using the command operands. The syntax of the PROFILE command is:

```
PROFILE [[SEV={1|2|3|4|5|6}]
        [NCLID=ncl-process-identifier]
        [PROC=ncl-procedure-name]] |
        [RESET=YES]
```

You can profile messages according to the following:

SEV

Determines how critical the messages are. For example, specify **SEV=1** to see only the most critical messages or **SEV=4** to see the messages of severity levels 1 through 4.

NCLID

Specifies the ID of the NCL process that issued the messages you want to see. The NCL processes are created when NCL procedures are executed. The region creates NCL processes when performing automation tasks.

Each NCL process has a unique ID, so you can use the NCLID operand to differentiate between executing copies of the same NCL procedure if, for example, the same NCL procedure was run more than once in a given period.

The region processes resources asynchronously, and a number of NCL processes for the resource may be active at the same time. Messages raised by these NCL processes intermingle in the transient log. You can use the NCLID operand to view the messages raised by a particular NCL process (that is, to view the messages for a particular task).

PROC

Specifies the name of the executing NCL procedure that issued the messages you want to see.

You can use the asterisk (*) wildcard character to include more than one NCL procedure. The wild card represents any single character except at the end of a string when the wild card represents one or more characters.

RESET

Specify **RESET=YES** to reset the profile to view all available messages.

Display User-defined Log Messages

A user-defined log message can be specified for a resource on the Define Event Related Actions panel when the resource is defined.

If you want to see only these messages in the transient logs, enter **UL** beside the resource.

Obtain Help on a Logged Message

You can obtain more information about product messages in a transient log through help.

To display the detailed help text associated with a message in the transient log

1. Enter **H** beside the message.

The help text appears.

Print a Transient Log

To print a transient log

1. Enter **P** beside a resource to print its transient log.

The Generate a Report panel appears, which lets you print a default report or an extended report of the resource's transient log.

2. Specify your printing requirements.
 - To print the default report (TRANSIENTLOG), ensure that the displayed information is satisfactory.
 - The extended report contains additional fields that display the S (severity), Nclid (NCL ID), and Proc (procedure) for each item in the transient log. To print the extended report, enter ? in the Report Name field, and then select TRANSX.

Press F6 (Action).

The log report is printed.

Reset a Transient Log

When you do not need the messages in the transient log anymore, you can clear the messages by resetting the log.

To reset the transient log of a resource

1. Enter **LR** beside the resource.

Its transient log is cleared of all messages.

Change Logging Options

Logging options for a resource are specified on the Automation Log Details panel when the resource is defined. These options determine how and what information is logged.

Note: For more information about resource logging, see the *Administration Guide* and the *Reference Guide*.

Merge Transient Logs

For a resource, instead of displaying only the messages logged for that resource, you can display a merged transient log that also includes the messages logged for the resources belonging to it. To identify the owner of a message, the merged log contains the following additional information: the system image name and version, the class name, and the resource name.

Important! This command may take some time to execute and consume many system resources.

To display a merged transient log

1. Enter **LC** beside the resource.

The merged transient log appears.

Note: The log display may extend over several screens. Use the F7 (Backward) and F8 (Forward) function keys to scroll through the screens. To refresh the log, press F6 (Refresh).

To print a merged transient log

1. Enter **PC** beside the resource.

The PSM : Confirm Printer panel appears.

2. Specify your printing requirements, and press F6 (Confirm).

The log report is printed.

Transient Logs From Different Time Zones

When transient logs from different time zones are merged, all dates and times refer to the local time zone.

Size of a Merged Transient Log

The size of the merged transient log is limited by the size of the transient log of the selected resource. The size of the transient log is specified in the Automation Log Details panel of the definition. When the merged log becomes full, the oldest messages are replaced by the new messages.

Chapter 6: Using Monitors

Various monitors let you keep track of defined resources. General usage of these monitors is described here.

This section contains the following topics:

[Monitor Services and Resources](#) (see page 83)

[Control Services and Resources](#) (see page 84)

[Graphical Monitor](#) (see page 85)

[Use the Status Monitor](#) (see page 88)

[Use Commands in the Status and Graphical Monitors](#) (see page 94)

[Acknowledge a Link Failure](#) (see page 99)

[Respond to the Initialization Status Panel](#) (see page 100)

[Respond to the Database Synchronization Panel](#) (see page 100)

[Recover a Failed Resource](#) (see page 101)

[Recover From Failed Automation](#) (see page 101)

[Obtain Operations Statistics](#) (see page 102)

Monitor Services and Resources

The status monitor and graphical monitor enable you to monitor at the service and resource levels in your environment in real time.

You can monitor the services and resources from any of the connected focal point regions. From subordinate regions, you can monitor locally-managed resources only. Logs can be used to display the messages associated with a service or resource and therefore with system activity, and authorized users can define filters and profiles that enable the viewing of information about specific services and resources.

The two monitors enable you to monitor the service and resource activities from two different viewpoints. Use the status monitor to view the status of *individual* services and resources, and the graphical monitor to view the status of *groups* of services and resources.

Control Services and Resources

A monitored service or resource can operate in the AUTOMATED operation mode, the MANUAL operation mode, or the IGNORED operation mode. In the AUTOMATED operation mode, the region has control of the service or resource but you can still indirectly influence the operation of that service or resource. In the MANUAL operation mode, you have direct control of the service or resource. The IGNORED operation mode is the same as the MANUAL operation mode except that the logical state of the affected service or resource is always set to OK (used typically when the state of the service or resource is of no interest).

From the monitors, you can perform the following:

- You can override the operation mode or the desired state of a service or resource, thus indirectly influencing its behavior.
- You can, if authorized, change the active knowledge base information dynamically without having to shut down the region. For example, a service level agreement might have changed and you need to update the resource availability to reflect the change.
- You can start or stop a service or resource that is in the MANUAL operation mode.

Graphical Monitor

The graphical monitor displays groups of resources as graphical images called *icons*. This monitor uses display attributes to alert you to changes in the status of the represented groups. Changes in an icon are caused by changes in the members in the group. Thus, if an icon changes color, you can look at its members to see what is causing the change.

The display attributes of an icon reflect the status of the represented member that is in the worst state. The attributes are controlled by the display attribute tables, except that icons do not use the highlighting attribute, as all icons appear in reverse video. The display attributes can be customized by a user with the appropriate authority.

Note: For information about the default display attributes and how to change them, see the *Administration Guide*.

An icon is associated with a group of resources, or a panel, as follows:

Group of Resources

A group, when represented by an icon, enables items managed by the region to be presented with a service-driven operations perspective.

When you issue the Z (Zoom) command against an icon associated with a group, the members in the group are listed. You can then monitor the individual resources.

When you issue an operations command against an icon associated with a group, the command acts on all the members.

Important! Issuing commands that return responses against a group with many resources results in many panels that you have to scroll through.

Panel


When you issue the Z (Zoom) command against an icon associated with a panel, a panel of component icons is displayed. For example, an icon may represent all the resources in the system EASTTEST. When you select the icon, a panel of icons is displayed. The component icons may contain specific types of resources. Each of these icons may be associated with another panel or with a group of resources. You can follow a very specific path leading directly to any resource that is causing the problem.

You cannot issue operations commands against an icon associated with a panel.

Interpret the Graphical Monitor Display

Icons on the graphical monitor group resources together. Icons can group different types of resources, and can group resources from different systems.

Typically, each icon is identified by a name. You can enter commands in the command entry window. The following shows an icon and the information it contains.

RESOURCES	Icon Name
Tot:22	
Ok:9	
	Command Entry Window
All	
TAPE	
9999	User-defined Information

An icon may display other information (for example, the resource states).

Access the Graphical Monitor

To access the graphical monitor

1. Enter **/GMON** at the prompt.
The Graphical Monitor appears.

Operations From the Graphical Monitor

From the graphical monitor, you can do the following:

- Use the Z (Zoom) command to view the status of the resources attached to an icon
- Issue commands to solicit information about, or to modify the behavior of, all the resources attached to an icon

Use the Z (Zoom) Command

Use the graphical monitor to get a high level view of the monitored resources. If an icon indicates a failure, issue the **Z** command from the icon command entry window to access the icon components and find the problem.

Zooming to the Status Monitor

If the icon is associated directly with a list of resources, the Monitor panel is displayed. This panel contains only those resources defined to the selected icon.

Use the Monitor panel to check the status of resources to see which resources are causing the problem. You can then perform status monitor actions, access the logs, or issue line commands to locate the source of the problem.

Zooming to an Icon Panel

If the icon is associated with a panel, the panel is displayed. This panel contains icons that are subsets of the main icon. For example, the icon containing all resources in EASTTEST may change to red, indicating a problem. You can zoom to the next panel of icons to see which icon has caused the main icon to change color. Select any icons that have changed state to see which resources are causing the problem. When you display the monitor, the status of the individual resources appears.

Use Other Commands

You can enter line commands in the command entry field of an icon that directly represents a group of resources (that is, an icon that is *not* pointing to another icon panel). To list commonly used commands, enter **?**; to list all available commands, enter **??**.

A command acts on all the members of the group.

When you use a command on a group, a Confirm Command panel may appear (depending on a setting in the DISPLAYS region parameter group).

The panel advises you of the number of members in the group. You can:

- Press F6 (Action) to confirm the command.
- Press F5 (Zoom) to list the members if you decide that you do not want to issue the command against all the members. The list enables you to issue the command against individual members.
- Press F12 (Cancel) if you change your mind and do not want to issue the command.

Change to a Different Default Icon Panel

When you access the graphical monitor, the type of information available is determined by your default icon panel.

To change the panel

1. Enter **PROFILE** at the prompt.
A Profile panel appears. This panel contains a field that enables you to change your default icon panel for the monitor.
2. To select a new default, enter **?** in the Panel Name field.
A list of available panels appears.
3. Select the required panel by entering **S** beside the panel name.
4. Do one of the following:
 - Press F3 (File) to save the new default and return to the graphical monitor.
 - Press F4 (Save) to save the new default and remain on the panel.
 - If you change your mind and do *not* want to change the default, press F12 (Cancel) to return to the graphical monitor without saving the changes.

Note: If you want to view a different icon panel temporarily, use the F5 (Panel) function key or the PANEL command.

Use the Status Monitor

The status monitor displays services and resources line by line, and uses color and highlighting to notify you of changes in their states. The display attributes and the display format can be customized by a user with the appropriate authority.

Note: For information about the default display attributes and the display formats, and how to customize them, see the *Administration Guide*.

If a state change occurs for a service or resource that is off the display area, a message is displayed to alert you of the change.

From the status monitor you can enter commands against resources and services. The commands vary depending on your product and the class of the resource.

Interpret the Status Monitor Display

The default status monitor display format provides the following information:

- The name of the system image that contains the service or resource.
- The name of the service or resource and its class.
Note: Resources of the INTNL class with names in the form xx(*) are dynamic resources that provide communications between regions.
- The operation mode, desired state, actual state, and logical state (as applicable).
- The override flag that indicates whether normal operation is overridden.

Note: For information about override flags, see the online help.

A blinking service or resource indicates that the region is performing an automated action on it.

You are notified of changes in the status of monitored items that are not in view.

Organize the Information on the Status Monitor

You can enter the following commands at the prompt to organize the information on the status monitor.

COLS {1|2|3|4|5}

Use this command to display the services and resources in up to five columns across your screen. For example, enter **COLS 5** to display in the 5-column format. This command is useful if there is more than one panel of services and resources.

EXTDISP {OFF|ON}

Use this command to control the display of user-defined extended displays. User-defined extended displays, if they exist, overwrite the last four columns of the normal status monitor display.

For example, the status line for a tape unit contains a text string that provides information about a tape mounting operation.

FORMAT {?|*format-name*}

Use this command to change the way information is displayed on your screen for a particular columns setting. If you do not know the name of a format, enter **FORMAT** and select it from the displayed list of format definitions.

Notes:

- The product supplies a number of predefined formats. If authorized, you can define your own formats from the List Definition List panel. To access the list, enter **/ASADMIN.L** at the prompt. For information about how to define status monitor formats, see the *Administration Guide*.
- If you updated the current format, enter the **REFORMAT** command to make the updates effective in the current session.

SORT *operand*

Use this command to sort the services and resources displayed on your screen in a particular order. *operand* can be one of the following:

?

Displays a list of available operands to use with the SORT command. Enter the number of the operand. The sort is in the order you specified. See the following SORT operands for a description of the types of sorts.

ACTSTAT

Enables you to sort the services or resources by the actual state according to the following in descending order of ranking: UNKNOWN, FAILED, INACTIVE, DEGRADED, STOPPING, STARTING, and ACTIVE.

CLASS

Enables you to sort the services and resources by the class number in numeric order.

CLSNAME

Enables you to sort the services and resources by the class name in alphabetic order.

DSTACUR

Enables you to sort the services and resources by the desired state according to the following in descending order of ranking: ACTIVE, INACTIVE, and UNKNOWN.

LOGSTAT

Enables you to sort the services and resources by the logical state according to the ranking in the logical state attributes table.

MODECUR

Enables you to sort the services and resources by the operation mode according to the following in descending order of ranking: IGNORED, MANUAL, and AUTOMATED.

NAME

Enables you to sort the services and resources by the name in alphanumeric order.

OBJID

Enables you to sort the services and resources by the object ID that comprises (in order) the system image name, the system image version, the class number, and the name.

SYSNAME

Enables you to sort the services and resources by the system image name in alphabetic order.

TYPE

Enables you to sort the resources by the resource type in alphabetic order. Services, which do not have the TYPE parameter, are listed at the beginning.

USRKEYW

Enables you to sort the resources by user-defined filter keywords. Services and resources for which filter keywords are currently not applicable are listed at the end.

Filter keywords are defined in the resource definitions. The keywords are message related. That is, a keyword becomes active only if certain messages are received for a resource.

For example, a keyword is specified in the rule for the IEC501A message that requests a tape mounting operation. You can use the USRKEYW operand to group tape units that request tape mounting operations together on the status monitor.

Note: Services and resources that rank the same by *operand* are further sorted by the object IDs.

Change to a Different Status Monitor Filter

Authorized users can create filters to define which services and resources are displayed on the status monitor. Filters are sets of rules stored in the knowledge base that enable you to display a subset of the monitored services and resources. For example, a tape operator may only want to see the tape units in each system, or in a combination of systems. Another operator might want to see only the batch jobs in the production system during his or her shift. A third operator may want to see all the hardware resources for a particular system.

The services and resources you see the first time you access the status monitor depend on the filter specified in your user profile. If no filter is specified, you see all the services and resources for the selected monitor.

You can change your view of displayed services and resources by using a temporary status monitor filter. The filter that you select remains valid for the current monitor session only.

Note: You can also filter the resources on the monitor by using the PREFIX command. The command lets you display only those resources with names that match a specified mask (for example, ****NM** or **REGION*1**).

To select a status monitor filter and change the view of displayed resources

1. Enter one of the following commands at the command prompt of the status monitor:

FILTER

Enter this command to display a list of the available filters. Enter the number that identifies the filter you want to use. Only the services and resources that match the filter are displayed on the status monitor.

FILTER *filter-name*

Enter the name of the filter that you want to use. Only the services and resources that match the filter are displayed on the status monitor.

FILTER NONE

This command removes any filtering. You now see every service and resource for the systems to which you are connected.

The resources, as specified in the filter, appear.

Notes:

- If authorized, you can enter **F** on the Automation Services Administration Menu panel to select the Status Monitor Filters option to create and maintain status monitor filters. You can also use the /ASADMIN.F path to select the Status Monitor Filters option.
- If you updated the current filter, you need to enter the REFILTER command to make the updates effective in the current session.

Change Your Default Status Monitor Profile

When you access the status monitor, the type of information available is determined by your default status monitor profile. The profile specifies the following:

- Filter to use when you first enter each type of status monitor.
- Number of monitored entities to display across the screen and the corresponding display format (if applicable).
- Criteria that determine how the monitored entities are sorted for display.
- Flag that indicates whether to see extended displays.

To change the defaults

1. Enter **PROFILE** at the prompt.

A Profile panel for your current status monitor type appears.

This panel contains fields that enable you to change your default profile for this type of monitor.

2. To select a new default, enter **?** in the appropriate field.

A list of available values appears.

3. Select a value, and press Enter.

4. Do *one* of the following:

- Press F3 (File) to save the new defaults and return to the status monitor.
- Press F4 (Save) to save the new defaults and remain on the panel.
- If you change your mind and do *not* want to change the defaults, press F12 (Cancel) to return to the status monitor without saving the changes.

Use Commands in the Status and Graphical Monitors

You can issue commands to perform various actions from the monitors, depending on your authority level.

Use the **?** command to find a short list of commands (ShortLst) available for the selected resource. For descriptions of the commands, press F1 (Help).

Use the **??** command to find a full list of commands (FullList) available for the selected resource. For descriptions of the commands, press F1 (Help).

Note: While displaying a list of commands, you can press F4 to toggle between the full list and the short list.

Find Out More About Monitored Services and Resources

Use the **D** command to display information about the selected services or resources.

Use the **B** or **S** command to display information about the current and defined states, and the operation mode of selected services and resources. If necessary, you can override the current operation mode and state.

Note: You can also use commands to override the operation mode and the states.

Remove the User-defined Extended Display

If the last columns of a display are overwritten by an extended display and you want to view the original information in those columns, use the **EDR** command. The command removes the extended display temporarily. The extended display re-appears on the next update of the status.

Notes:

- Enter the **EXTDISP {OFF|ON}** command at the prompt to turn the extended display on or off for all the resources. The setting stays for the duration of the session.
- If you want to retain the setting across sessions, specify the setting in your monitor profile.

Access Extended Functions

Use the **XF** command to access any extended functions provided.

Reply to a WTOR Message

When the status indicates that there are outstanding write-to-operator with reply (WTOR) messages waiting to be replied to, enter **W** beside the resource. A Command Entry panel appears listing the WTOR messages.

To reply to a WTOR message

1. Issue the following command at the SYSCMD prompt:

```
REPLY wtor-id,reply-text
```

Browse or Update the Definition of Monitored Services and Resources

Use the **DB** command to browse selected service and resource definitions. Users with the appropriate authority can also update the definitions. The update is effective immediately. For example, you may need to add a new status monitor message.

Important: Resources of the INTNL class with names in the forms DT(*), ET(*), SE(*), and ST(*) are dynamic APPC resources that provide communications between regions. These resources are defined only for the duration of the APPC link. Some products also use dynamic resources of the form xx(*). Do not change these resource definitions.

Note: You can use the F4 (Add) function key or the ADD primary command to add definitions to and the DEL command to delete definitions from the knowledge base. For more information, see help.

Override the Operation Mode

The following commands enable you to modify the operation mode of selected services and resources:

- Use the **MA** command to set the operation mode to AUTOMATED. The region takes control of the affected service or resource.

Note: If the global operation mode is MANUAL, the mode cannot change even though the AUTOMATED override is applied. A G in the Ovr column indicates this condition.

- Use the **MS** command to set the operation mode to AUTOMATED. When the affected service or resource achieves desired state, the mode is set to MANUAL.
- Use the **MI** command to set the operation mode to IGNORED. This mode is the same as the MANUAL mode except that the logical state of the affected service or resource is always set to OK. Use this mode if you are not interested in the state of the service or resource.
- Use the **MM** command to set the operation mode to MANUAL. The region relinquishes control of but continues to monitor the affected service or resource.
- Use the **MR** command to remove the override.

On the status monitor, an M in the Ovr column identifies a service or resource as having an operation mode override.

Override the Service and Resource States

You can override the actual state and the desired state of selected services and resources.

Override the Actual State

Override the actual state only if you believe that the displayed state is wrong. The following commands enable you to modify the actual state of selected services and resources:

- Use the **ASA** command to set the actual state to ACTIVE.
- Use the **ASD** command to set the actual state to DEGRADED.
- Use the **ASF** command to set the actual state to FAILED.
- Use the **ASI** command to set the actual state to INACTIVE.
- Use the **ASU** command to set the actual state to UNKNOWN to recheck the status.

Override the Desired State

The following commands enable you to modify the desired state of selected services and resources:

- Use the **DSA** command to set the desired state to ACTIVE.
- Use the **DSI** command to set the desired state to INACTIVE. If you enter DSI beside a resource or service that has the SVC override flag, a panel is displayed listing the services that might be affected by the action.
- Use the **DSR** command to remove the override.

On the status monitor, a DSA, DSI, G/D, or M/D, in the Ovr column identifies a service or resource as having a desired state override.

If you set the desired state of a service to ACTIVE, then when the service is started (either through automation or by you manually), the service places an ACTIVE desired state override on its members. On the status monitor, an SVC in the Ovr column identifies a service or resource as having a desired state override imposed on it by a service. Similarly, if you set the desired state of a service to INACTIVE, then when the service is stopped, the service removes the ACTIVE desired state override from its members.

Modify the Scheduled Operations Changes for a Monitored Item

Scheduled changes in the operation of a service or resource are defined in an availability map. An availability map defines the desired service or resource status at specific times. If a service or resource is attached to the map and is in the AUTOMATED operation mode, the region will try to ensure that the actual status of the service or resource matches the desired status defined in the map. More than one service or resource can use the same map.

You can modify those changes in one of the following ways:

- Create a map to override any existing requirements.
- Update the attached map. This action, however, also modifies the behavior of other services and resources attached to the map.

Override the Scheduled Operations Changes

Use an overriding map when you want to modify the behavior of a service or resource for a defined period of time only.

Enter **MPO** to create an overriding map that specifies your new requirements. You must specify the map expiry date and time, and the map is deleted automatically at the specified date and time. The scheduled operations changes then revert back to what were specified originally.

You can revert the scheduled operations changes back to what were specified originally, at any time. To do this, enter **MPR**. The command replaces the overriding map by the original map. The command does not, however, delete the overriding map.

Once the map is created, it is available for use by other services and resources. (To attach an overriding map to another service or resource, specify the name of the map in the appropriate definition. You can update the definition by using the DB command from your monitor or through the Definition menus.)

Browse or Update Maps

Important! Updating a map affects the operation of all services or resources attached to the map.

Use the **MAP** command to browse the map for selected service and resource definitions. Users with the appropriate authority can use the **MAP** command to update maps to which selected services and resources are attached. The update is effective immediately.

Control Manual Services and Resources

You have direct control over services and resources that are in the MANUAL or IGNORED operation mode. That is, you can start and stop manual services and resources. You can use these modes of operation when automatic error recovery fails.

Note: For a resource, these operations use the methods specified in the definition for that resource, provided that you have not registered commands that override the supplied commands.

Start Manual Services and Resources

You can start selected services and resources manually. For example, you may want to restart a resource after recovering it from a failure. Ensure that the operation mode of the service or resource you want to start is MANUAL or IGNORED. Use the **A** command to start the services and resources. A message appears prompting you for confirmation. Press Enter to confirm the action. The actual state changes to ACTIVE if the service or resource starts successfully.

Stop Manual Services and Resources Normally

You can stop selected services and resources manually. For example, you might want to stop a resource because its status is degrading and you want to take it out of service. Ensure that the operation mode of the service or resource you want to stop is **MANUAL** or **IGNORED**. Use the **T** command to stop the services and resources. A message appears prompting you for confirmation. Press Enter to confirm the action. The actual state changes to **INACTIVE** if the service or resource stops successfully.

Stop Manual Resources by Force

You can stop selected resources manually by force. For example, in an emergency, you want to stop a resource quickly. The normal stop process can take some time to complete. Ensure that the operation mode of the resource you want to stop is **MANUAL** or **IGNORED**. Use the **TF** command to stop the resources. A message appears prompting you for confirmation. Press Enter to confirm the action. The actual state changes to **INACTIVE** when the resource has stopped.

Acknowledge a Link Failure

When a link between connected regions fails, the resources being monitored through the failed link appear in the **UNKNOWN** state. A failed link can affect a large number of resources and fill your monitor with link failure error states. Use the **ACKLNKFAIL** command to acknowledge that you note the failure and to clear your monitor of the affected resources so that you can better monitor the other resources. The affected resources reappear when the link recovers.

To acknowledge a link failure

1. On your Monitor panel, type **ACKLNKFAIL** at the prompt and press Enter.

The Execute **ACKLNKFAIL** Command panel appears.

The panel displays the list of regions connected to your region. The panel identifies the access method control block (ACB) name of each region and the system image that is active in that region.

2. Type **S** beside the regions affected by the failed link, and press Enter.

A confirmation panel appears.

3. Enter **CONFIRM** in the Response field to execute the command.

The Monitor panel appears with the resources under the control of the selected regions removed from the list of monitored resources.

Respond to the Initialization Status Panel

If the loading of a system image starts in your region while you are using the monitor, your monitor session ends and the Initialization Status panel is displayed. Similarly, if you attempt to access the monitor while the system image is being loaded, the Initialization Status panel is displayed. You can take *one* of the following actions:

- Press F6 (Action) to monitor the loading process.
- Press Enter to refresh the information in the status window.
- Press F3 (Exit) to exit the panel.

You can return to the monitor when the loading process completes.

Respond to the Database Synchronization Panel

If knowledge base synchronization is started for your region while you are using the monitor, your monitor session ends and the Database Synchronization panel is displayed. Similarly, if you attempt to access the monitor while the knowledge base is being synchronized, the Database Synchronization panel is displayed. You can take *one* of the following actions:

- Press F6 (Action) to monitor the synchronization process.
- Press Enter to refresh the information in the status window.
- Press F3 (Exit) to exit the panel.

You can return to the monitor when the synchronization process completes.

Recover a Failed Resource

If a resource fails and no automated recovery action is performed, the resource remains in the FAILED actual state, and you need to recover the resource manually.

To recover a failed resource

1. Ensure that the resource is in the MANUAL operation mode. If the mode is AUTOMATED, enter **MM** beside the resource to set its operation mode to MANUAL. This indicates to other operators that the resource is being attended to.
2. Enter **L** beside the resource to access its transient log. The log provides information about the cause of the problem, which helps you determine the actions to take.
3. Correct the problem, and ensure that the resource can be safely restarted.

Note: You can use the Command Entry facility to issue system commands. Enter **CMD** at the prompt, and issue the SYSCMD command from the Command Entry panel.

4. Enter **CHK** or **RES** beside the resource to reset the status of the resource. If the resource is in the AUTOMATED operation mode, automation restarts for the resource. If the resource is in the MANUAL operation mode, enter **A** beside the resource to start it.

Note: For the differences between the CHK and RES commands, see the online help.

Recover From Failed Automation

Automation fails for a resource in the AUTOMATED operation mode when the region cannot maintain the desired state of the resource. The status monitor displays the resource as having an INERROR logical state.

To recover from failed automation

1. Enter **MM** beside the resource to set its operation mode to MANUAL. This indicates to other operators that the resource is being attended to.
2. To confirm that automation has actually failed, enter **S** beside the resource to access the Modes and States panel. The panel displays the automation status, which should be FAILED.
3. Press F12 (Cancel) to return to the status monitor. Enter **L** beside the resource to access its transient log. The log provides information about the cause of the problem, which helps you determine the actions to take. A likely cause is that the recovery action specified in the resource definition is inappropriate.
4. Correct the problem, and ensure that the resource can be safely restarted.
5. Enter **RES** beside the resource to reset the status of the resource.

Automation restarts for the resource.

Obtain Operations Statistics

You can obtain operations statistics of a service or resource in your region or a connected region on your screen.

Obtain the Operations Statistics of a Monitored Service or Resource

The operations statistics of a service or resource provide information about the message and command traffic in relation to the service or resource, and its actual availability. Use the **ST** command to display the statistics. You can display the statistics from the status monitor or the graphical monitor.

To display the statistics from the status monitor

1. Access a status monitor.
The Monitor panel appears.
2. Enter **ST** beside the service or resource for which you want to display the statistics.
The Statistics panel appears.
3. Press F6 (Refresh) to refresh the statistics.
4. Press F3 (Exit) to exit the panel when you finish browsing the statistics.

Interpret the Statistics

The Statistics panel contains the operations statistics of a service or resource.

It displays the time at which the statistics collection starts. There are two windows. The windows contain statistics on messages and commands, and on the availability of the selected item.

Interpreting the Messages and Commands Statistics

The Messages and Commands window contains the following statistics:

- Messages Processed provides a count of the messages processed by the region on behalf of the service or resource.
- Automation Commands Issued provides a count of the start and stop commands issued by the region on behalf of the service or resource.

Interpreting the Availability Statistics

If the service or resource is available, the Availability window displays the time at which the service or resource became available; if the service or resource is *not* available, the window displays the time at which the service or resource became unavailable.

The window contains the following statistics:

- Availability Percentage indicates the portion of time when the service or resource is available as a percentage.
- Total Time Available gives the number of time units over which the service or resource is available.
- Total Time Unavailable gives the number of time units over which the service or resource is unavailable.
- Number of Times Available gives the number of times the status of the service or resource goes from unavailable to available.
- Number of Times Unavailable gives the number of times the status of the service or resource goes from available to unavailable.

Chapter 7: Using Operator Console Services

This section contains the following topics:

[Operator Console Services](#) (see page 105)

[Access OCS](#) (see page 105)

[OCS Panel](#) (see page 106)

[Run Multiple OCS Panels](#) (see page 107)

[Function Keys](#) (see page 109)

[Assign Your Own Values to Function Keys](#) (see page 110)

[Use Commands in OCS](#) (see page 113)

[Monitor and Control in OCS](#) (see page 116)

[Receive Non-roll Delete Messages](#) (see page 118)

[Interpret Messages and Codes to Help Monitor Your Region](#) (see page 120)

[Issue Commands](#) (see page 120)

[Execute or Start NCL Processes from OCS](#) (see page 126)

[Start REXX Programs from OCS](#) (see page 128)

[Issue System Commands from Your Console](#) (see page 129)

Operator Console Services

Operator Console Services (OCS) lets you enter commands to control and monitor your resources.

OCS uses a formatted display panel called an OCS window to provide an environment for executing commands or NCL procedures. Your command results are returned to the window, with other system information, to provide a console function.

The level of authority granted in your user ID definition limits the actions you can perform in OCS. You control the way your OCS window looks and the way you use it. This set of attributes, privileges, and options is called your *operator profile*.

Certain attributes of your operator profile are controlled by UAMS. Other attributes can be changed using the PROFILE command.

Access OCS

To access OCS

1. Enter **O** at the prompt at the main Primary Menu.

The OCS window appears.

OCS Panel

The OCS panel has two distinct activity areas: a one-line command input area at the bottom of the window, and an output message display area called the roll delete area, which occupies the remaining space above the command line.

Command Line

The command line is the bottom line of the OCS window. The command line is the only display field where input is permitted. The cursor is automatically positioned to the right of the command line prompt when the panel is first displayed. To enter a command, position the cursor in the command line and press Enter.

Operating Mode Indicators

A mode indicator may appear to the left of your command entry area to indicate how the OCS window is currently operating. Values of the operating mode indicators and their meanings are as follows:

M (Monitor)

Terminal has monitor status and receives monitor messages.

P (Paused)

An NCL procedure has paused awaiting the entry of a GO, END, or FLUSH command. The SHOW NCL command gives you further details.

W (Waiting)

An NCL procedure is waiting for specific text to arrive. The SHOW NCL command gives you further details.

Roll Delete Area

When you receive messages as the result of commands entered on the command line, they are reported in the roll delete area with any unsolicited information you are profiled to receive.

Output to the roll delete area is written line-by-line from top to bottom of the screen. When the display area is full, new output messages wrap back to the top of the screen, overwriting the oldest displayed messages first.

Non-roll Delete Area

Any messages requiring a reply are delivered as non-roll delete messages. This means that the messages stay on your screen until you respond. These messages are displayed at the top of an OCS window above the roll delete area. The non-roll delete area is created only when a non-roll delete message is delivered to your OCS window.

Roll-delimiter Line

Messages are written from top to bottom of the screen. The next line for use is filled by a line of underscore (`_`) characters. This line is called the roll-delimiter line. It separates the oldest and newest output displayed. Output below this line is the oldest display information; output above the line is the most recent.

Note: The underscore characters used for this line can be changed using the PROFILE DELCHAR command.

Title Line

The top of the roll delete display area is reserved for a title that can be set or reset by using the TITLE command.

Time Display

The top left of the title line includes the present system time in *hh.mm* format and is automatically updated each time anything is written to the OCS window.

Run Multiple OCS Panels

You can use the [screen-splitting function](#) (see page 29) to run two OCS windows in parallel on the same screen.

You can have one screen window operating in OCS with the other part-screen or window in full-screen mode (for example, as a menu).

Set Window IDs

When two OCS windows are running simultaneously, it helps if you can distinguish each window while executing NCL procedures.

To set a name for each OCS window, enter the OCSID command followed by a 1- to 8-character name at the command prompt on an OCS window and press Enter. The name for each window appears to the right of the line, immediately above the command line.

Example: Set Window ID

To set a window ID of NET01, enter the following command:

```
OCSID NET01
```

After pressing Enter, NET01 appears to the right of the line immediately above the command line.

Note: You can set profile attributes for each OCS window, so that two OCS windows on the same terminal can have different profiles and appearances.

Function Keys

OCS windows have full support for 24 function keys. You can set function keys for each OCS window to suit your requirements. If you are running two OCS windows, each window can have a separate set of function key definitions.

A variety of function keys are available:

- Default (system-wide) function keys
- Immediate function keys
- Conversational function keys
- Prefix function keys
- Suffix function keys
- NCL controlled function keys

The OCS function keys are set to system default values when you enter OCS.

When you redefine a function key, its defined value applies only to the function key settings for your current window, and remains in effect only while your current window is active.

When you press an immediate function key, its assigned value is immediately entered into the system, without the need for further action by you.

Note: To discover the assignment of each function key, use the PF LIST command.

Conversational Function Keys

A conversational function key lets you modify its action before you release it for processing. When you press a conversational function key, its assigned value is displayed in the command line, so you can add to or modify the text. Press Enter to run the command after you modify it.

Prefix and Suffix Function Keys

A prefix function key assigns a set value as a prefix to the line of text where the cursor is located when that function key is pressed (that is, the command line or any other line in the OCS window display area).

Example: Prefix and Suffix Function Keys

The F6 function key is defined using the following command:

```
PF6 PREF,MSG USER1+
```

When you enter a message in the command line saying: SYSTEM DOWN AT 17.00, and press F6, the following command is generated and entered:

```
MSG USER1 SYSTEM DOWN AT 17.00
```

Note: The plus sign (+) leaves a blank after the text before concatenating it with the entered string.

A suffix function key acts like a prefix key, but adds its value to the end of the line of text where your cursor is positioned (that is, the command line or any other line in the OCS window display area).

Assign Your Own Values to Function Keys

You can assign your own values to function keys so that they invoke an NCL procedure or act as the Enter key. If a function key is being used as the Enter key, you can redefine the Enter key to perform an OCS function.

Specify Commands to Function Keys

To redefine function keys, use the PF command. You can specify the new function key value as *one* of the following:

Conversational

The value of the function key appears in the command line so that it can be edited before being issued.

Immediate

The function key performs an immediate function such as Enter.

Suffix

The function key value is placed at the end of an entry in the command line.

Prefix

The function key value is placed at the beginning of an entry in the command line.

Example: Assign a Conversational Function Key

To assign the SHOW NCL command as a conversational function key to the F4 key, enter the following command:

```
PF4 CONV,SHOW NCL=
```

When you press F4 from now on, SHOW NCL= is displayed at the command prompt so that you can add to it before executing it.

Example: Define Multiple Commands

You can use a semicolon as a command separator in the function key value to define multiple commands. When entering the PF command, specify two semicolons.

To define F20 to clear the screen and display users, enter the following:

```
PF20 CLEAR;;SHOW USERS
```

Set Function Keys as Enter Keys

The PF command can set a function key to act as the Enter key. The Enter key is defined as an immediate function key with no associated value.

Example: Define Enter Key

To define PF12 as the Enter key, enter the following:

```
PF12 IMM
```

PF12 acts as the Enter key because there is no entry after IMM. When you press F12, text is executed from the command line as if the Enter key is pressed.

Redefine the Enter Key

You can use the ENTER command to redefine the action of the Enter key.

Important! You must define at least one function key to act as Enter *before* you redefine the Enter key.

Example: Redefine Enter Key to Act as CLEAR Command

To redefine the value of the Enter key to act as the CLEAR command, type the following:

```
ENTER CLEAR
```

The Enter key no longer acts in its standard manner.

Example: Reset Enter Key

To reset the Enter key, type the following text and then press the function key that is defined as Enter:

```
ENTER IMM
```

Specify Function Keys Using NCL Procedures

You can also assign values to a function key from an NCL procedure. By setting the appropriate function keys in an NCL procedure and setting your initial command to execute the NCL procedure on entry to OCS, you can set the function keys for your OCS window.

Use Commands in OCS

OCS windows can be used to enter product commands and monitor the results. Commands are entered on the command line and take effect when you press the Enter key.

You can access a list of all product commands from online help.

To access the list of commands from any OCS window

1. Press F1 (Help).

The OCS Overview panel appears.

2. Enter **S** beside the List of Commands topic.

The commands are listed. You can select any of the commands displayed to get more information about its use and syntax.

Command Authority Levels

All commands are assigned an authority level within the range 0 to 255, zero being the lowest and 255 the highest authority level. The operands on some commands might require a higher authority than the base command itself.

You are allocated a command authority level in your user ID definition, corresponding to the scope of system control you require. Whenever you enter a command, your user ID authority level must be equal to or higher than the authority level of the command entered, otherwise the command is rejected.

This authority level checking also applies to commands executed from NCL processes invoked under your user ID.

Abbreviate Commands

All commands consist of a single command, which can be followed by one or more operands. Most commands can be abbreviated to the smallest number of characters consistent with their being distinguishable from any other product command. For example, the SHOW command can be abbreviated to SH.

Concatenate Commands

Several commands can be entered simultaneously by concatenating them into the same OCS command line and separating each command with a semicolon (;). The concatenated commands are processed from left to right in the order they are entered.

Example: Concatenate Commands

The command string `D LU10;D LU11` is treated by the system as two independent commands:

```
D LU10
D LU11
```

You can use the `CLEAR` command in this manner to clear the display area before the results of the next command are displayed. For example:

```
CLEAR;D BFRUSE
```

If you need to enter a semicolon as part of a command (that is, to use it as part of the command text), you must enter two semicolons instead of one.

To enter the command `a;b`, you must enter `a;;b`. The second semicolon is stripped from the text and the `a;b` string passed to the system as a single command. The remaining semicolon is not regarded as a command separator character.

Command separators are specified by using the `PROFILE CMDSEP` command.

Prevent Command Concatenation

You can prevent command concatenation by using the `CMDSEP` operand of the `PROFILE` command. When `CMDSEP` is set to `NO`, semicolons are not regarded as command separators and are always treated as part of the command string.

You can assign concatenated commands to function keys because the value of the `CMDSEP` operand is overridden by the value that the operand contained when the function key was defined.

Reuse Commands

If you enter a command regularly, you do not need to retype it every time you want to issue the command. There are facilities provided with OCS that let you reuse commands you have previously entered.

More information:

[Use the Command Stack](#) (see page 115)

[Retain Commands on the Command Line](#) (see page 115)

[Copy Display Lines into the Command Line](#) (see page 115)

Use the Command Stack

Each OCS window keeps a stack of the commands most recently entered from its command line. The stack does not include immediate function key entries. The number of entries kept in this stack can be changed by using the PROFILE CMDSTACK command.

You can use the command stack to retrieve previous commands entered and redisplay them on the command line so that they can be modified for re-entry.

Commands are retrieved from the stack using the CS+ or CS- commands. The default system function key series includes settings for the CS+ and CS- commands. These are F10 and F11 respectively. We recommend that you retain these.

Retain Commands on the Command Line

When you execute a command, the command can be retained on the command line so that you can execute it again, or edit the command before executing it again. This facility lets you increment and enter command sequences with minimal effort.

This feature can be turned on or off using the PROFILE CMDKEEP command. When turned off, the command line is cleared as soon as the Enter key is pressed and a command must be retrieved from the command stack if it is required again. When turned on, the command you enter is retained on the command line so that you can enter it again.

Copy Display Lines into the Command Line

To copy a command (or some other message) from an OCS window display area to the command line, put the cursor on the line you want to copy, and enter CS+ or CS- (or press F10 or F11).

The command or message appears in the command line.

Rename Commands

EQUATE commands can be included in initialization procedures to do the following:

- Override or rename standard commands
- Define a series of 1- to 8-character strings for use in place of lengthy command strings

Monitor and Control in OCS

OCS allows you to monitor and control your regions by receiving messages and allowing you to issue commands. Events from your network are sent to your OCS window. You can issue commands to take control of any problems that might occur.

As you receive messages and output from commands, you can control, reorder, or clear output on the screen so that it can be read more easily.

Control Message Presentation Speed

When the bottom line of the display area is filled, the system pauses before wrapping back to the top of the display area to write the next message.

Sometimes, a large number of messages might be sent to the screen within a very short period of time. This causes the display to roll messages faster than you can read them. There are two options you can use to temporarily suspend message delivery or change the way the messages display:

- The HOLD option
- The AUTOHOLD option

Stop Message Flow Manually

To stop the flow of output to the screen at any time, press the Enter key while nothing is in the command line. This freezes the display and no further messages appear until you enter data.

While the screen is frozen, the word HOLDING appears immediately above the command line.

Stop Message Flow Automatically

The default value for automatic hold supplied with your system automatically freezes an OCS window when a message fills the last line and there are messages queued to wrap back to the top of the screen. This is specified by the AUTOHOLD command.

When AUTOHOLD freezes your screen, the caption AUTOHOLD is displayed above the command line. No further messages appear until you input something.

The AUTOHOLD command option is part of your operator profile.

Note: If more unsolicited messages arrive while the screen is in HOLDING or AUTOHOLD mode, the caption above the command line changes to MSG QUED, and the terminal alarm sounds.

Message Queue Holding Limit

Your system queues a limited number of messages for an OCS window while in the HOLDING or AUTOHOLD mode. The queue limit default before any OCS window messages are discarded is 200 messages.

The HOLDING or AUTOHOLD caption above the command line changes to 75% LIMIT, HOLD LIMIT, and then MSGS LOST, as this limit is approached, reached, and then exceeded. Each caption change also sounds the terminal alarm. These conditions vary and update while you actively monitor and release system messages in the OCS window.

You can define the queue limit for each OCS user window by using the PROFILE command.

Contention Delay Interval

One of the characteristics of an OCS window is that your system can send messages to your window at the same time as you are entering a command. These messages are displayed differently depending on the type of terminal you are using:

A Non-SNA Terminal

Any data you have just entered is immediately frozen and any new data entered is ignored while the message writes to the screen. You can then continue to type in your command text when message delivery has finished.

An SNA 3270 Terminal

A contention condition arises. The terminal is seen as being in a send state (because you have started typing on the keyboard), and refuses to accept any output from your system until your input has been sent. However, rather than defer your system, the system interrupts you after a set period and forces the output of a message.

The default contention delay interval is 15 seconds. This is usually long enough to let you complete a standard command input operation.

Unwrap Messages

To resequence or unwrap messages displayed in your OCS window, enter the **ORDER** command.

The OCS messages are redisplayed in the window in chronological order, with the oldest messages at the top of the window.

The ORDER command is assigned to F12 by default.

Note: This command does not affect the HOLDING or AUTOHOLD condition.

Clear the OCS Window

After many messages have appeared in your OCS window, you may want to clear the window before any new messages arrive.

To clear your OCS window, enter the **CLEAR** or **K** command.

Receive Non-roll Delete Messages

Most messages displayed on an OCS window are classified as roll delete messages. This means they are displayed once and eventually roll off the top of the screen as subsequent messages arrive and overwrite them.

When a non-roll delete (NRD) message is delivered to an OCS window, it remains in your OCS window until deleted. The NRD messages are in two categories:

- Those that are remembered by the system and are retained until explicitly deleted by the issuing process
- Those that are only displayed at individual OCS windows until deleted and are not remembered by the system

The non-roll delete area is separated from the roll delete area by a delimiter line. This line is usually a series of dash (-) characters. To change the character, use the PROFILE NRDELCH command.

NRD messages are managed centrally and held in a queue. Your system administrator determines the size of this queue. If there are more NRD messages than this limit, the oldest outstanding NRD message is deleted to remove copies of the message from all affected OCS windows.

However, NRD messages from &WRITE NCL statements are never deleted automatically. It is therefore only possible to exceed the NRDLIM queue depth if large numbers of &WRITE-generated NRD messages exist at the same time.

A warning message is sent to all OCS users with monitor status to notify them when the NRD message queue reaches 75 percent full.

You can hide these messages to allow other message flows to continue in your OCS window, and then reveal them again when you are able to deal with them.

Hide NRD Messages

To remove an NRD message from the OCS display, move your cursor to the line on the screen with the NRD message you want to remove and then press Enter.

The NRD message disappears and the screen is reformatted. Removing NRD messages in this way provides more room for pending NRD messages or a larger roll delete area.

Note: System NRD messages are not deleted from the NRD message queue, only from your OCS window. NRD messages specific to your OCS window are deleted, and cannot be recalled.

Restore Hidden NRD Messages

Hidden NRD messages can be restored by entering the NRDRET command. The oldest hidden NRD messages are returned to the non-roll delete area first, until the area has expanded to its maximum size.

The NRDRET command displays all hidden NRD messages that you are entitled to view, including those that occurred before you entered OCS and any that are still outstanding.

NRDRET can be issued from any environment capable of receiving NRD messages, including NCL &INTCMD environments.

Delete NRD Messages

An NRD message is automatically deleted when *one* of the following conditions is satisfied:

- The condition to which an NRD message refers is satisfied
- An NCL process issues an &NRDDEL NCL statement to delete a specific NRD message
- The NCL process that generated the NRD is terminated

You can only delete NRD messages that are remembered by the system by using the PURGE command.

Use NRD Messages with ROF Sessions

Messages that originate from a remote system carry the NRD message attribute and appear as NRD messages, in the same way as locally-produced messages.

When an INMC link fails and breaks any ROF sessions traveling across it, all NRD messages from that remote system are automatically deleted.

When you close a ROF session to a particular remote system by using the SIGNOFF command, any NRD messages you have received across the ROF session are deleted from your window. Other users displaying the same NRD messages are not affected.

Interpret Messages and Codes to Help Monitor Your Region

The information database provides categories of information about commonly used codes and errors. By accessing the information database from OCS, you can get information about error messages that appear in your OCS window.

To access the information database from OCS, enter **/CODES** at the prompt.

Issue Commands

Being able to issue commands from OCS is an important part of controlling your regions. From OCS you can issue commands to the background processes of your product, and you can set commands to issue automatically, based on a specified time.

Issue Commands in Background Environments

Background environments are internal to your system and services. They process commands submitted to them by users and support system level procedures such as LOGPROC. Each background process has a user ID, but is not associated with any physical terminal.

The following background environments are available:

BSYS

Background system environment

BMON

Background monitor environment

BSVR

Background server environment

BLOG

Background logger environment

You can send commands to these environments for them to execute, as if they were real OCS users by using the SUBMIT command. You can submit commands or NCL procedures. For example, if you want the background system environment to start the procedure MONPROC, enter the following command:

```
SUBMIT BSYS START MONPROC
```

After a command is submitted, its processing is managed by that environment. It is not affected if you log off or leave OCS, and its command authority remains the same as the user ID of the submitter.

Background environment processing is ideal for monitoring an NCL procedure that regularly checks the status of network components. Commands directed to the Background Monitor route the command and its results to all monitor status terminals logged on to the system, and to the activity log. Commands directed to the Background Logger for execution log the command and its results only.

[Timer commands](#) (see page 122) can also be routed to background environments by the SUBMIT command or by the ROUTE operand for the timer command being issued.

Issue Commands at Specified Times

You can issue commands at specified times and at specified intervals. These commands are known as timer-initiated commands. The following timer-initiated commands are available:

AT

Executes commands at a specified time of day. Timer commands use a 24-hour clock with the format *hh.mm.ss*.

Limits: 24.00.00 (midnight)

EVERY

Repeats commands at a given time frequency.

Default: 10 seconds

Timer commands can be entered in OCS, or included in NCL procedures.

A maximum of 9999 concurrent timer commands is supported, and this maximum is the default.

If you log off after issuing a timer command, that command is not executed. However, you can use the ROUTE or KEEP operand when you enter an AT command to specify another user to issue the command in your place. This feature allows you to sign off and have the results of the command returned to you when you sign on again.

The ROUTE and KEEP options are ideal if you are including timer commands for specific operators in the system initialization procedures that are executed automatically during startup.

Timer commands can also be specified with a limit to the number of times they can execute before being automatically purged.

Example: Monitor Users at a Specified Interval

To monitor the users that are logged on to the system every half hour, enter the following command:

```
EVERY .30 CMD=SHOW USERS
```

Also, if you want to remind users of a three o'clock meeting one hour before it starts, enter the following command:

```
AT 14.00 MSG ALL DON'T FORGET MEETING AT 15.00
```

When a timer command executes, the command text is echoed on all applicable terminals as if the command had been entered from those terminals. A unique timer ID prefixes the command text echo and has the following format:

```
#nnnn command_text
```

Display Active Timer Commands

You can display pending timer commands by using the SHOW TIMER command. By default, this command lets you display any timer commands initiated by your user ID. However, by specifying the ALL operand you can display all outstanding timer commands on your system.

Example: Display Active Timer Commands

To find out what timer commands you have initiated, enter the following command:

```
SHOW TIMER
```

Using the example given above, the following is displayed:

```
ID BY INTERVAL -USERID-R LIM CNT K/P ENV P/M TID  NEXT
 4 EV 00:30:00 USER01      0  0 NO PRI YES -   12:29:48
    CMD=SHOW USERS
 5 AT 14:00:00 USER01      0  0 NO PRI YES -   14:00:00
    CMD=MSG ALL DON'T FORGET MEETING AT 15.00
NUMBER OF TIMER COMMANDS DISPLAYED WAS 2.
```

Delete Timer Commands Manually

When you initiate a timer command, the system allocates a unique four-digit number known as the timer ID, or purge ID. This number prefixes all displays resulting from that command, and must be used when manually deleting a timer command.

To delete a timer command manually, use the **PURGE** command.

To delete a timer command created by another user, you require a command authority level of 2 or higher.

Example: Delete Command

To delete an AT timer command, enter the following command:

```
PURGE TIMER=5
```

The value 5 is the purge ID assigned to the AT command.

Delete Timer Commands Automatically

By default, your timer commands remain active only while you are logged onto the system. Before each attempt to execute the command, the system checks that you are still logged on.

If you are no longer logged on to your system, the timer command is automatically deleted, without further execution.

Redirect Timer Commands

If you want your timer-initiated commands to continue to execute after you log off, you can redirect the command results to the background logger, background monitor, or the system background environment.

To redirect the timer command, specify an AT or EVERY command with the KEEP operand.

By default, the KEEP operand requires a command authority level of 2 or higher.

Example: Redirect Timer Commands

To redirect the SHOW USERS command for execution by the background system environment, enter the following command:

```
EVERY .30 KEEP=SYS CMD=SHOW USERS
```

If the KEEP operand is in use, the execution of timer commands continues irrespective of whether you are logged on to the region.

Limit Timer Command Executions

When defining a timer command, you can use the LIMIT operand to specify a limit on the number of times the command is executed. When this limit is reached, the command is automatically purged.

The limit you assign and the number of times a command has already executed are displayed by the SHOW TIMER command.

Example: Limit Timer Command Execution

To limit the number of times the SHOW USERS command is executed to 5, enter the following command:

```
EVERY .30 LIMIT=5 CMD=SHOW USERS
```

When the SHOW USERS command has been executed five times, the timer command is deleted.

Execute a Timer Command Under Another User ID

The ROUTE operand lets you direct a command for execution under another user ID—the target user ID. The operand requires a command authority level of at least 2.

With this option, the timer command is retained even if the target user ID is not logged on. Command execution is bypassed and the time interval reset. The command is attempted again only after the time interval has again elapsed.

Example: Execute Timer Command Under Another User ID

If you want USER02 to execute the SHOW USERS command, enter the following command:

```
EVERY .30 ROUTE=USER02 CMD=SHOW USERS
```

Specify Concatenated Commands in Timer Commands

Concatenated commands can be specified in the command text for a timer command. Separate each command in the concatenation with a colon (:). These are internally translated into normal concatenation characters, that is, semicolons (;), before execution.

Execute or Start NCL Processes from OCS

There is an NCL processing environment for each window of your terminal that allows commands and NCL processes to execute on behalf of that window.

When you use an EXEC or START command to invoke an NCL process, the NCL process executes in the NCL processing environment for the OCS window.

Note: If you enter the EXEC or START command incorrectly, the system attempts to execute the command as if it were an NCL process.

Any NCL process can have a dependent processing environment that lets it issue commands or execute other NCL processes independently using the &INTCMD statement. NCL procedures can also use ROF sessions to collect information from other systems.

Execute NCL Processes Serially

An OCS window can execute a serial stream of NCL processes so that they are invoked one after the other. Serial execution is suitable for processes with a short duration.

To execute NCL processes serially, use the **EXEC** command.

Processes invoked by the EXEC command can issue the &PAUSE statement to wait for further input from the OCS window. The GO, END, FLUSH, and INTQ commands, together with the process's unique identifier, let you communicate with the process.

Example: Execute Processes in Sequence

To execute PROC1 and PROC2 in sequence, enter the following commands:

```
EXEC PROC1  
EXEC PROC2
```

Your OCS window places the two processes in an EXEC queue, which are executed on a first-come, first-served basis. Process PROC1 is scheduled for immediate execution and process PROC2 is queued to execute after PROC1 ends.

Execute NCL Processes Concurrently

An OCS window can execute NCL processes in parallel at the same time.

To execute NCL processes concurrently, use the **START** command. If you enter the name of an NCL procedure by itself, the START command is implied.

Any started procedure can issue an &PAUSE statement to wait for further input from GO, END, and FLUSH commands from the OCS window. These commands, together with the unique identifier for the process, let you communicate with the process explicitly.

Example: Execute NCL Processes Concurrently

To execute PROC1 and PROC2 at the same time, enter the following commands:

```
START PROC1  
START PROC2
```

NCL Identifiers

Each NCL process is allocated a unique identifier that links it to the issuing OCS window. This ensures any &WRITE or &PANEL statements issued by the NCL process (or any other processes it starts or executes), are returned to that window only. If the window is terminated, any queued process is deleted.

Execute an NCL Process from a Serial or Concurrent Process

An NCL process executed from an OCS window (or any process it invokes) can itself issue EXEC or START commands.

If an EXEC command is used to execute an NCL process, the process issuing the command is suspended when the new process starts executing. Only when the new process ends does the issuing process resume processing.

Invoking a process from another process in this way is called nesting. Nesting is an easy way to structure a series of processes.

Note: The &CALL PROC NCL statement is the recommended method for nesting procedure calls.

If a START command is used to execute an NCL process, the new process starts executing immediately. The new process runs concurrently with the invoking process and independently of it. Each process is unaffected by the termination of the other process.

Advantages of Started Procedures

Using the START command to invoke NCL processes has the following advantages:

- You can perform relatively complex, long-term tasks from your OCS window. This does not prevent other operations from performing concurrently.
- You can perform periodic checking of the network status without operator involvement.
- You can operate a large number of independent, slave procedures on behalf of one OCS window. This lets you monitor many different aspects of the same operation, and various procedures need only communicate with you if errors are detected.

Start REXX Programs from OCS

Your region supports the REXX language. A processing environment for each OCS window lets REXX processes execute on behalf of that window.


To start a REXX program from OCS, enter the following command:

```
REXX program_name
```

Note: For information about how your product supports REXX, see the *NetMaster REXX Guide*.

Issue System Commands from Your Console

The SYSCMD facility gives you the ability to issue operating system commands and receive responses without having to use a *real* operating system console; for example, to display the channel path or unit status of a local non-SNA terminal.



Use the SYSCMD Facility

The SYSCMD command has several operands that you can use to enter master console commands, lock a console, or issue a command as if it came from a specific console.

In its most basic form, the SYSCMD command is:

`SYSCMD command-text`

command-text

The command to be entered.

Note: You are restricted in your use of the SYSCMD facility by both your command authority and your user security profile. These are set by your systems administrator.

Enter Master Console Commands

If the command to be entered is usually restricted to the master console, the CON=MASTER operand must be used with the SYSCMD command.

Example

```
SYSCMD CON=MASTER DATA=VARY CPU(0) OFFLINE
```

You must have MASTER authority for this.

Note: This is not necessary if you are using Extended Multiple Console Support (EXTMCS) consoles.

Lock a Console

To ensure that you can issue commands when you need to, you can lock a console to a specific environment using the following operand:

```
OPT=LOCK
```

When you no longer require the console, you should release it, using the following operand, so that it is made available to other SYSCMD users:

```
OPT=REL
```

Simulate Command Issue from a Specific Console

If you want to simulate issuing a command from a specific console that you are not using, enter the following form of the SYSCMD command (where *n* is the console number):

```
SYSCMD CON=n DATA=command-text
```

This can be done from anywhere in the system.

As no console authority checks are made by the SYSCMD facility, the existing authority for the specified console is used.

Note: The form of the SYSCMD command described in the example above is not supported if you are using EXTMCS consoles.

Chapter 8: Using WebCenter

This section contains the following topics:

[WebCenter Features](#) (see page 131)

[Set Up Your Web Browser](#) (see page 132)

[Log On to WebCenter](#) (see page 135)

[CA SYSVIEW Integration](#) (see page 136)

WebCenter Features

WebCenter is a web browser interface that lets you access some or all of the following functions:

- Diagnostics
- Monitoring
- Performance
- History
- ReportCenter
- CA SYSVIEW
- Utilities

If your region has WebCenter enabled, the URL is displayed on the primary menu.

WebCenter is z/OS-hosted. The WebCenter web server runs in the region address space and requires no third-party components.

Problem resolution time is decreased and ease-of-use is increased. Users who are not familiar with accessing mainframe products using a 3270 interface can diagnose problems with their standard web browser.

Each WebCenter page has a Help link in the upper-right corner that you can click for context-sensitive online help.

Set Up Your Web Browser

You can access WebCenter by using Internet Explorer or Firefox.

The WebCenter interface requires the Java Runtime Environment (JRE).

If your organization prevents you from downloading software through the Internet, arrange to have the JRE installed. The JRE is available from <http://www.java.com>.

The JRE is required to be downloaded once only, not once per WebCenter release.

Note: For software requirements on your PC to support WebCenter, see the *Installation Guide*.

Set Up Internet Explorer

If your PC does not have JRE installed, a download dialog prompt appears when you enter web pages containing Java applets.

For IPv6 support, WebCenter requires at least JRE Version 1.5.0_12. If your site has implemented IPv6 and you do not have the required version of JRE, you receive an error dialog instead. The dialog tells you to download Version 1.5.0_12 or later directly from the website.

Important! WebCenter does not work with JRE Version 1.6.0_13 through Version 1.6.0_20.

If your organization permits you to download software from the Internet, you can download and install the Java runtime library. However, this download requires your security settings to permit you to access the website for a once only ActiveX control download.

You can configure the settings through Internet Options from the Tools menu of your browser. On the Security tab, for the web content zone associated with access to the website (usually the Internet), click Custom Level. On the Security Setting dialog that appears, the Download signed ActiveX controls option must not be disabled.

For you to access WebCenter correctly, specify the correct options in Internet Explorer.

To set up Internet Explorer

1. Click Tools, Internet Options.

The Internet Options dialog appears.

2. Click the Security tab.
3. Click the web content zone to which your WebCenter belongs, and then click Custom Level.

The Security Settings dialog appears.

4. Enable the following options:

ActiveX controls and plug-ins

Initialize and script ActiveX controls not marked as safe

Run ActiveX controls and plug-ins

Microsoft VM

Java permissions: High safety

Scripting

Scripting of Java applets

5. Disable the following option:

Miscellaneous

Use Pop-up Blocker

Click OK

6. Click the Privacy Tab, and then click the Sites button.

The Per Site Privacy Actions dialog appears.

7. Complete the following field:

Address Of Web Site

Enter the WebCenter URL.

Click Allow, and then click OK.

8. Click the Advanced Tab.

9. Enable the following option:

Multimedia

Show pictures

If you do not require Sun JRE as your default virtual machine, clear the following option:

Java (Sun)

Use Java 2 *version_number* for <applet>

Click OK.

The options are saved.

Set Up Firefox

If your PC does not have JRE installed, the following alert appears when you access WebCenter:

Java is not enabled in this browser. The Web Interface requires a Java-enabled browser.

Go to the website to download and install the JRE.

For IPv6 support, WebCenter requires JRE Version 1.5.0_12. If your site has implemented IPv6, download Version 1.5.0_12 or later.

Important! WebCenter does not work with JRE Version 1.6.0_13 through Version 1.6.0_20.

For you to access WebCenter correctly, enable the correct options in Firefox.

To set up Firefox

1. Click Tools, Options.

The Options dialog appears.

2. Click Content, and review the following options:

Block pop-up windows

Clear the check box, or click Exceptions to add the WebCenter URL to the allowed sites.

Load images automatically

Select the check box.

Enable JavaScript

Select the check box; click Advanced, and select all the check boxes.

Enable Java

Select the check box.

3. Click Privacy, and review the following option:

Cookies

Accept third-party cookies

4. Click OK.

The options are saved.

Log On to WebCenter

A standard user ID and password are used to access WebCenter.

To log on to WebCenter:

1. Start your web browser and enter the access URL for WebCenter in the Address text box.

The WebCenter login page appears.

Notes:

- The access URL is defined when your product is installed. You can find the value on the primary menu of the mainframe region.

Note: For more information, see the *Installation Guide*.

- To access WebCenter easily and quickly in the future, create a bookmark for WebCenter web access URL in your web browser.

2. Enter your User ID and Password, and click the Log In button.

The initial WebCenter page appears, showing a menu on the left pane.

Note: If your Security Administrator has installed a digital certificate, a dialog appears. Click OK to accept the certificate and continue.

CA SYSVIEW Integration

When the CA SYSVIEW interface is enabled (through the WEBCENTER parameter group), it appears in the WebCenter interface, providing a persistent command interface to CA SYSVIEW.

Any command entered into the Command Text field can be executed, or more specifically, passed to CA SYSVIEW to be executed. CA SYSVIEW in turn passes results back in the form of output that is restricted to the Maximum Lines Returned specified in the Execute a SYSVIEW Command Criteria field.

To improve performance and to cut down on network traffic, the CA SYSVIEW interface restricts the maximum number of lines returned to WebCenter for each command to 2000 lines.

For security reasons, CA SYSVIEW limits execution of certain commands to administrators or users with superuser authority. Because of the nature of the web interface to CA SYSVIEW, it is not possible to identify who is issuing the commands.

This is particularly apparent in the UNIX System Services displays, therefore:

- The output of certain commands such as UDIRTREE or UPROCESS, which rely on a particular user's profile, will vary a little.
- The output of other commands, such as USUPER, which toggles the current user authority to superuser mode, will not work at all.

One additional limitation in the CA SYSVIEW interface is that line commands, or commands that are entered against a particular line of CA SYSVIEW output, are not implemented in WebCenter. However, in many cases, there is a direct CA SYSVIEW command that will produce the desired output. Use the MENU command to navigate through the CA SYSVIEW menus and the HELP command to request help for specific CA SYSVIEW commands.

Chapter 9: Using Print Services

This section contains the following topics:

[Print Services Manager](#) (see page 137)

[Access PSM](#) (see page 137)

[List Entries in the Print Queue](#) (see page 138)

[Confirm Printing](#) (see page 139)

Print Services Manager

Print Services Manager (PSM) lets you control the physical printing of the reports your organization generates on JES or network printers. Output can be viewed online before or after printing and can be redirected to another destination.

PSM provides the following facilities:

Print Spooling

Writes output to a print spool providing more control over output. This facility lets you redirect output to another printer if one is not available.

Centralized Printer Definition Facilities

Supports VTAM (LU1) and JES (SYSOUT) devices and lets you assign printer aliases. This facility also allows the output destination to be a printer exit.

Print Request Control

Lets you hold, release, browse and delete print requests, redirect print requests to another printer, change priorities and numbers of copies, and display the status of requests.

Notes:

- For information about defining and maintaining printers, see the *Administration Guide*.
- References to JES also apply to VOS3's JES3 and JES4 subsystems.

Access PSM

To access PSM

1. Enter **/PSM** at the prompt.

The PSM : Primary Menu appears.

List Entries in the Print Queue

You can list all of the entries that are queued to print, and on which printer they are to print.

To display the entries in the print queue

1. Enter **Q** at the prompt on the PSM : Primary Menu.

The PSM : Output Queue appears.

Note: You can limit the display to the print queue for a specific printer by specifying a printer in the Printer field on the PSM : Primary Menu before entering the Q option.

Display the Output of a Print Request

You can preview the output to see exactly how the print request looks when printed.

Note: Only data lines, not heading lines, are displayed.

To browse the output of a print request, enter **B**, **/**, or **S** next to the required print request on the Output Queue panel.

The details appear.

Example: Browse Output

```

PROD----- PSM : Browse Output -----REQ# 0265
Command ==>                               Scroll ==> PAGE

S A B U Data
  --+---10--+---20--+---30--+---40--+---50--+---60--+---70
N N =====
1 N  COMMAND ENTRY CAPTURE PRINT
1 N =====
2 N  USERID : USER01             NAME : USER NUMBER 1      LO
2 N  DATE   : MON 26-APR-2010
2 N  TIME   : 11.16.39
2 N =====
2 N  pr
1 N  N10601 USERID: USER01 TERMINAL-ID: TERM02
1 N  N10602 NCL PROCEDURE LIBRARY ID: COMMANDS
1 N  N13450 PANEL SERVICES PATH NAME: PANELS
1 N  N10603 AUTHORITY LEVEL IS 82
1 N  N13451 NO EDS PROFILES ACTIVE IN ENVIRONMENT.
1 N  N13433 USER SERVICES PROCEDURE: $USERSER
1 N  N10624 NO NPF COMMAND RESTRICTIONS.
1 N  N10627 PPO MESSAGE DELIVERY DETAILS:
1 N  N10628 ..NO NPF MESSAGE RESTRICTIONS.
F1=Help   F2=Split   F3=Exit   F4=Return   F5=Find   F6=Refresh
F7=Backward F8=Forward F9=Swap   F11=Right

```

Modify a Printer Entry

You can modify a print request to change where and how it is to be printed.

To modify a print request

1. Enter **M** next to the required print request in the PSM: Output Queue.

The PSM : Print Request panel appears.

The PSM : Print Request Panel provides all details about the print request. You can alter some of the fields on the panel.

Confirm Printing

When you send a print request to a printer, the PSM : Confirm Printer panel appears. This panel is used to confirm the printer name, the number of copies, and the hold and keep settings that you require for your print request. The fields displayed on the panel are set to the values you used last.

To change any of these fields, overwrite them with the required information, and press F6 (Confirm).

The new information is used to print your request.

Note: For more information about the fields displayed on this panel, press F1 (Help).

Select the Printer

If you do not know what printers are available to send your print request to, you can display a list of active printers.

To select the printer

1. Enter a question mark (?) in the Printer Name field on the PSM: Print Request panel.

The list of active printers appears.

Note: If the list is longer than a full page, use F8 (Forward) and F7 (Backward) to scroll through the list.

2. Enter the selection code at the prompt.

The printer is selected.

Index

A

- accessing
 - alert monitor • 68
 - file transfer status monitor • 32
 - transient logs • 75
- action lists • 19
- actions for CA XCOM Data Transport requests
 - A (Alter) • 48
 - H (Hold) • 48
 - R (Release) • 48
 - R (Resume) • 48
 - S (Suspend) • 48
 - T (Terminate) • 48
 - V (View) • 48
- actions for CONNECT:Direct processes
 - C (Change) • 52
 - D (Delete) • 48, 52
 - DF (Delete/Force) • 52
 - DH (Delete/Hold) • 52
 - F (Flush) • 52
 - FPF (Flush Process Force) • 52
 - H (Hold) • 52
 - R (Release) • 52
 - S (Suspend) • 52
 - SPF (Suspend Process Force) • 52
 - V (View) • 52
- actions for resource definitions, D (Display) • 34
- actions, connection
 - Drop • 53
- activating resources • 44
- active file transfers monitoring • 59
- activity logs
 - browsing online • 77
 - displaying • 77
 - file transfer logs, accessing from • 76
 - record additional information • 78
- adding knowledge base definitions • 25
- alert history • 73
- Alert Monitor
 - accessing • 68
- alerts
 - closure • 73
 - monitoring • 68
 - operator notes • 72

- problem tickets • 72
 - transient log, and • 71
- assisted reorganization facility • 57
- Auto Connect, initiating • 55

B

- browsing knowledge base definitions • 26
- BSC lines monitor, displaying • 56

C

- CA XCOM
 - file transfers, displaying information • 34
 - listing transfer requests • 46
 - managing transfer requests • 48
 - remote nodes, displaying information • 34
- CA XCOM, displaying information about
 - control library member • 46
 - managers • 34
 - TCP/IP connections • 34
 - transfer requests • 34
- canceling changes to a record • 22
- CLOSE command • 73
- commands
 - CONNECT:Direct for Windows NT • 45
 - CONNECT:Direct information, displaying • 48
 - CONNECT:Direct signon details, confirming • 49, 50
 - CONNECT:Mailbox • 54
 - display • 46, 51
 - issuing to a file transfer region • 45
- commands, CA XCOM resources
 - DFT • 46
 - DIS • 46
 - ENA • 46
 - INQ • 46
 - LST • 46
 - VA • 47
 - VAC • 47
 - VH • 47
 - VI • 47
 - VS • 47
- commands, CONNECT:Direct resources
 - CLR • 49
 - CMD • 45
 - FTL • 75

-
- IIP • 50
 - NM • 50
 - VIP • 53
 - commands, CONNECT:Mailbox resources
 - C • 54
 - CON • 55
 - D • 54
 - DIR • 53
 - E • 54
 - FTL • 75
 - I • 54
 - M • 54
 - R • 54
 - S • 54
 - T • 54
 - VSS • 56
 - commands, FTP resources
 - FTL • 75
 - VIP • 53
 - commands, FTS resources
 - FTL • 75
 - commands, specific
 - CMD • 45
 - CON • 55
 - FILTER • 92
 - FTLOG • 75
 - LOCATE • 21
 - PROFILE • 79
 - SPLIT • 29
 - SWAP • 29
 - CONNECT:Direct
 - confirming signon details • 49
 - file transfers, displaying information • 34
 - listing processes • 51
 - managing processes • 52
 - remote nodes, displaying information • 34
 - security considerations • 48, 50
 - CONNECT:Direct resources
 - confirming signon details • 49, 50
 - monitoring • 32
 - CONNECT:Direct, displaying information about
 - managers • 34
 - network map • 50
 - processes • 50
 - queued processes • 34
 - region • 48
 - TCP/IP connection • 34
 - CONNECT:Mailbox batches
 - displaying • 53
 - managing • 54
 - CONNECT:Mailbox monitors, displaying and managing
 - BSC lines • 56
 - SNA sessions • 56
 - CONNECT:Mailbox, displaying information about
 - batches • 53
 - monitors • 55
 - VSAM batch files • 56
 - connections
 - dropping • 53
 - contacting technical support • 3
 - copying knowledge base definitions • 26
 - customer support, contacting • 3
- ## D
- DASD
 - displaying information about • 34
 - monitoring • 32
 - data
 - entry panels • 21
 - validation • 22
 - deleting knowledge base definitions • 27
 - devices
 - dropping a connection • 53
 - DFT command • 46
 - DIS command • 46
 - display commands • 34
 - displaying
 - activity log from the transient log • 78
 - activity logs • 77
 - alert history • 73
 - CA XCOM parameters • 46
 - CONNECT:Direct initialization parameters • 50
 - CONNECT:Direct processes • 50
 - file transfer logs • 75
 - file transfer resources • 33
 - logs • 75
 - TCP/IP connections • 53
 - transient logs • 78
 - displaying information about
 - DASD • 34
 - file transfer schedules • 34
 - started tasks • 34
 - tapes • 34
 - TCP/IP listener • 34
 - displaying information about CA SOLVE:FTS
 - links • 34
-

- managers • 34
- displaying information about CA XCOM
 - file transfers • 34
 - remote nodes • 34
 - transfer requests • 34
- displaying information about CONNECT:Direct
 - file transfers • 34
 - processes • 50
 - queued processes • 34
 - regions • 48
 - remote nodes • 34
- displaying information about CONNECT:Mailbox
 - batches • 53
 - monitors • 55
- displaying information about FTP
 - FTP remote nodes • 34
 - managers • 34
 - servers • 34
- dropping a connection • 53

E

- ENA command • 46
- entering data • 21

F

- fields
 - mandatory • 21
 - optional • 21
 - prompted • 22
- file transfer logs • 75
 - activity log, accessing • 76
 - browsing • 75
 - displaying • 75
 - suppressing messages • 76
- file transfer regions, issuing commands • 45
- file transfer resources
 - activating • 44
 - controlling • 44
 - inactivating • 44
- file transfer schedules
 - displaying information • 34
 - failure acknowledgment • 37
 - forecasts • 39, 40
 - monitoring • 32, 37
 - next schedule display • 38
 - selective display on status monitor • 38
 - status information • 41
- file transfer status monitor, access • 32

- filing data • 22
- FILTER command • 92
- Find function • 21
- Firefox, setup • 134
- FTP managers, displaying information • 34
- FTP remote nodes, displaying information • 34
- FTP servers, displaying information • 34
- FTS links, displaying information • 34
- FTS managers, displaying information • 34
- FTS resources
 - monitoring • 32

G

- graphical monitor • 58

H

- help, online
 - facilities for messages • 80
 - overview • 27
- horizontal scrolling • 20

I

- IBM TCP/IP, monitoring • 32
- inactivating a resource • 44
- Index Menu • 23
- Initialization in Progress panel • 12
- initiating an Auto Connect • 55
- INQ command • 46
- Internet Explorer, setup • 132
- issuing commands to a file transfer application • 45

K

- knowledge base definitions
 - adding • 25
 - browsing • 26
 - copying • 26
 - deleting • 27
 - updating • 26

L

- list types • 19
- listing and managing
 - CA XCOM requests • 46
 - CONNECT:Direct processes • 50
 - TCP/IP connections • 53
- LOCATE command • 21
- locating records • 21

- logging off • 12
- logon • 11
- logs
 - activity • 77
 - displaying • 75
 - file transfer • 75
 - transient • 78
- LST command • 46

M

- managing CA XCOM transfer requests • 48
- managing CONNECT:Mailbox resources
 - monitors • 55
 - VSAM batch files • 56
- managing processes • 52
- mandatory fields • 21
- menus • 15
- messages
 - help for • 28, 80
 - suppressing • 76, 78
- monitoring
 - active alerts • 68
 - active file transfers • 59
- monitors
 - displaying information • 34
 - graphical • 58
 - status • 32
- multiple select lists • 19

N

- navigation
 - menus • 16
 - splitting screens • 29
 - swapping screens • 29
 - toggling between windows • 29
 - working in two windows • 29
- numbered lists • 19

O

- online help
 - messages • 28
 - overview • 27
- optional fields • 21

P

- panels
 - customizing access • 24
 - data entry • 21

- panels, specific
 - Initialization In Progress • 12
 - User Password Change • 13
- passwords
 - changing • 13
- PREFIX command • 92
- primary menu
 - profile • 11
- problem ticket
 - raising for an alert • 72
- processes, CONNECT:Direct
 - listing • 51
 - managing • 50, 52
- PROFILE commands
 - menu format • 11
 - transient log • 79
- prompted fields • 22

R

- records
 - canceling changes • 22
- region, logging on • 11
- resource definitions
 - panel access sequence, customizing • 24
- resources
 - displaying file transfer resources • 33
 - monitoring • 32
- REXX
 - programs, starting from OCS • 128

S

- saving
 - data • 22
- screens
 - splitting • 29
 - swapping • 29
- scrolling • 19
- security
 - CONNECT:Direct • 48, 50
- selecting panels
 - all panels • 23
 - by Index Menu • 23
 - by Panel Display List • 23
 - by sequence number • 23
- signon details, CONNECT:Direct • 49
- single select lists • 19
- SNA sessions monitor, displaying • 56
- SPLIT command • 29

- started task
 - displaying information • 34
- status monitor
 - filter selection • 92
- support, contacting • 3
- suppressing messages
 - activity log • 78
 - file transfer log • 76
- SWAP command • 29
- swapping screens • 29

T

- tapes
 - displaying information • 34
 - monitoring • 32
- TCP/IP connections
 - displaying information • 34
 - dropping • 53
 - listing • 53
- TCP/IP listener, displaying information • 34
- technical support, contacting • 3
- terminating a region • 44
- tip of the day • 27
- toggling between windows • 29
- transfer requests, CA XCOM
 - listing • 46
 - managing • 48
- transient logs • 78
 - displaying an activity log • 78
 - merged • 82
 - message help • 80
 - printing • 81
 - resetting • 81
 - specifying what to display • 79

U

- UPDATE mode, switching to • 21
- updating knowledge base definitions • 26

V

- VA command • 47
- VAC command • 47
- validating data • 22
- vertical scrolling • 20
- VH command • 47
- VI command • 47
- VS command • 47
- VSAM batch files

- assisted reorganization • 57
- displaying • 56
- managing • 56, 57

W

- WebCenter
 - Firefox setup • 134
 - Internet Explorer setup • 132
- Windows NT
 - CONNECT:Direct commands • 45
- working in two windows • 29