

CA OPS/MVS for JES2 13.5
CA RS 2005 Service List

1

Service	Description	Type
S012418	OSF SERVER HANGS WHEN ISSUING IMS COMMANDS VIA THE IMS BMP	PTF
S012622	OPSJES2 INPQ FUNCTION RETURNS 0 JOBS FOR Z/OS 2.4	PTF
S012630	OPS3724T WTO MAY CONTAIN ZERO'S FOR PROGRAM NAME	PTF
S012658	Security or Integrity Problem	PTF
S012673	PASSWORD MASKING IGNORED FOR SECURITY EVENT	PTF
S012676	SOC4 ABEND DURING SHUTDOWN WITH INITADMINUI=YES	PTF
S012722	OPSJES2 NOT DISPLAYING REMOTE PRINTERS	PTF
S012733	POSSIBLE ABEND SOC4 AFTER INSTALLING IBM PTF UJ01558	PTF
The CA RS 2005 service count for this release is 8		

CA OPS/MVS for JES2
CA RS 2005 Service List for CCLXD50

2

FMID	Service	Description	Type
CCLXD50	S012418	OSF SERVER HANGS WHEN ISSUING IMS COMMANDS VIA THE IMS BMP	PTF
	S012622	OPSJES2 INPQ FUNCTION RETURNS 0 JOBS FOR Z/OS 2.4	PTF
	S012630	OPS3724T WTO MAY CONTAIN ZERO'S FOR PROGRAM NAME	PTF
	S012658	Security or Integrity Problem	PTF
	S012673	PASSWORD MASKING IGNORED FOR SECURITY EVENT	PTF
	S012676	SOC4 ABEND DURING SHUTDOWN WITH INITADMINUI=YES	PTF
	S012722	OPSJES2 NOT DISPLAYING REMOTE PRINTERS	PTF
	S012733	POSSIBLE ABEND SOC4 AFTER INSTALLING IBM PTF UJ01558	PTF
The CA RS 2005 service count for this FMID is 8			

Service	Details																		
SO12418	SO12418 M.C.S. ENTRIES = ++PTF (SO12418) OSF SERVER HANGS WHEN ISSUING IMS COMMANDS VIA THE IMS BMP PROBLEM DESCRIPTION: When an IMS command is sent to the OPS/MVS IMS BMP, and the response exceeds the maximum number of lines specified by OPS/MVS parameter REXXMAXQUEUE, OPS13520 message is issued indicating the following: OPS13520 MESSAGE SEND OVERFLOW ERROR, DETECTED AT OPPCSSRU+ At this point the OSF Server hangs waiting for the command response ECB to be posted. The ECB is never posted and eventually, after the number of seconds specified by OPS/MVS parameter OSFWAIT, the server times out and terminates SYMPTOMS: The OPS13520 message and a hung OSF Server. IMPACT: Command responses are not returned to the Rexx exec due to the hung server. CIRCUMVENTION: None. PRODUCT(S) AFFECTED: CA OPS/MVS Base Release 13.0 Related Problem: OPSMVS 1665 Copyright (C) 2020 CA. All rights reserved. R00253-CLX135-SP1 DESC(OSF SERVER HANGS WHEN ISSUING IMS COMMANDS VIA THE IMS BMP). ++VER (Z038) FMID (CCLXD50) SUP (ST12418) ++HOLD (SO12418) SYSTEM FMID(CCLXD50) REASON (ACTION) DATE (20092) COMMENT (<table border="1"> <tr> <td>CA OPS/MVS Base</td><td>Release 13.5</td></tr> </table> -----+----- <table border="1"> <tr> <td>SEQUENCE</td><td>Before issuing IMS commands to the OPS IMS BMP.</td></tr> </table> -----+----- <table border="1"> <tr> <td>PURPOSE</td><td>To prevent OSF Server hangs when using the OPS IMS BMP.</td></tr> </table> -----+----- <table border="1"> <tr> <td>USERS</td><td>All users of the OPS IMS BMP.</td></tr> <tr> <td>AFFECTED</td><td></td></tr> </table> -----+----- <table border="1"> <tr> <td>KNOWLEDGE</td><td>Basic z/OS system programming skills.</td></tr> <tr> <td>REQUIRED</td><td></td></tr> </table> -----+----- <table border="1"> <tr> <td>ACCESS</td><td>Authority to stop and start the OPS IMS BMP.</td></tr> <tr> <td>REQUIRED</td><td></td></tr> </table> -----+----- ***** * STEPS TO PERFORM * ***** - After applying the PTF, use the OPSVIEW 4.1.1 panel to toggle the IMSxxINITBMP parameter from YES to NO to stop the BMP. - Once the BMP is stopped, toggle the IMSxxINITBMP parameter from NO to YES to restart the BMP.	CA OPS/MVS Base	Release 13.5	SEQUENCE	Before issuing IMS commands to the OPS IMS BMP.	PURPOSE	To prevent OSF Server hangs when using the OPS IMS BMP.	USERS	All users of the OPS IMS BMP.	AFFECTED		KNOWLEDGE	Basic z/OS system programming skills.	REQUIRED		ACCESS	Authority to stop and start the OPS IMS BMP.	REQUIRED	
CA OPS/MVS Base	Release 13.5																		
SEQUENCE	Before issuing IMS commands to the OPS IMS BMP.																		
PURPOSE	To prevent OSF Server hangs when using the OPS IMS BMP.																		
USERS	All users of the OPS IMS BMP.																		
AFFECTED																			
KNOWLEDGE	Basic z/OS system programming skills.																		
REQUIRED																			
ACCESS	Authority to stop and start the OPS IMS BMP.																		
REQUIRED																			

CA OPS/MVS for JES2 13.5
CA RS 2005 - PTF SO12418 Details

Service	Details
	Note: The OPS/MVS CCLXLOAD library must be included in the BMP PROC STEPLIB or module OPIMBP must be copied to the IMS RESLIB for the change to be picked up when the BMP restarts.).

Service	Details
S012622	S012622 M.C.S. ENTRIES = ++PTF (S012622) OPJSJES2 INPQ FUNCTION RETURNS 0 JOBS FOR Z/OS 2.4 PROBLEM DESCRIPTION: The OPJSJES2 function is not returning the correct number of jobs for the INPQ keyword after upgrading to z/OS 2.4. SYMPTOMS: The OPJSJES2('I','INPQ','A') function always returns 0 jobs. IMPACT: Automation using the OPJSJES2 function to gather input queue information will fail. CIRCUMVENTION: None. PRODUCT(S) AFFECTED: CA OPS/MVS Base Version 13.0 CA OPS/MVS Base Version 13.5 Related Problem: OPSMVS 1671 Copyright (C) 2020 CA. All rights reserved. R00255-CLX135-SP1 DESC(OPJSJES2 INPQ FUNCTION RETURNS 0 JOBS FOR Z/OS 2.4). ++VER (Z038) FMID (CCLXD50) SUP (S006788 S011878 S012591 ST06788 ST11878 ST12591 ST12622) ++HOLD (S012622) SYSTEM FMID(CCLXD50) REASON (DYNACT) DATE (20093) COMMENT (<pre> +-----+ CA OPS/MVS Base Release 13.5 +-----+-----+ SEQUENCE After APPLY +-----+-----+ PURPOSE To activate load modules updated by this PTF, including load module OPSAEX +-----+-----+ USERS All OPS/MVS users AFFECTED +-----+-----+ KNOWLEDGE Basic z/OS systems programming skills REQUIRED +-----+-----+ ACCESS - Access to OPS/MVS SMP/E Target loadlib CCLXLOAD and any REQUIRED deployed copies - Authority to issue MVS system commands - Authority to stop and start OPS/MVS +-----+-----+ ***** * STEPS TO PERFORM * ***** 1. This PTF updates load module OPSAEX, as well as the other load modules identified by the ++MOD statements contained in this PTF. APPLY of this PTF updates SMP/E Target loadlib CCLXLOAD. </pre>

Service	Details
	2. Copy the updated load modules from SMP/E Target loadlib CCLXLOAD to any other deployed copies, such as a STEPLIB used by the OPS/MVS main address space, a link listed loadlib, etc. 3. If the system library lookaside (LLA) program is managing any updated loadlib, you must refresh LLA by using MVS system command "F LLA,REFRESH" or some equivalent mechanism. 4. TSO users must get out of OPSVIEW. 5. Stop OPS/MVS. 6. If the system link pack area (LPA) contains any updated load module, you must refresh LPA by using MVS system command "SETPROG LPA" or some equivalent mechanism. 7. Start OPS/MVS. 8. TSO users may access OPSVIEW. Depending on how OPSVIEW is accessed, this may require TSO logoff/logon.).

Service	Details		
SO12630	SO12630 M.C.S. ENTRIES = ++PTF (SO12630) OPS3724T WTO MAY CONTAIN ZERO'S FOR PROGRAM NAME PROBLEM DESCRIPTION: The OPS3724T message text may contain zeros in place of the program name or the ruleset.rule name from where the command originated. SYMPTOMS: The OPS3724T message will display x'0000' in place of the program name or ruleset.rule name that is dispatching work to an OSF server. IMPACT: Unable to identify the program name or ruleset.rule that is sending commands to an OSF server. CIRCUMVENTION: None. PRODUCT(S) AFFECTED: CA OPS/MVS Base Version 13.0 CA OPS/MVS Base Release 13.5 Related Problem: OPSMVS 1668 Copyright (C) 2020 CA. All rights reserved. R00256-CLX135-SP1 DESC(OPS3724T WTO MAY CONTAIN ZERO'S FOR PROGRAM NAME). ++VER (Z038) FMID (CCLXD50) PRE (S001859 S004411 S008474 S008999 S010262 S011508) SUP (S000632 ST00632 ST12630) ++HOLD (SO12630) SYSTEM FMID(CCLXD50) REASON (ACTION) DATE (20093) COMMENT (<table border="1"> <tr> <td>CA OPS/MVS Base</td><td>Release 13.5</td></tr> </table> SEQUENCE Before Apply PURPOSE To activate load modules updated by this PTF. USERS All OPS/MVS users AFFECTED KNOWLEDGE Basic z/OS systems administration skills. REQUIRED ACCESS - Access to OPS/MVS SMP/E Target loadlib CCLXLOAD and any REQUIRED deployed copies - Authority to issue MVS system commands - Authority to stop and start OPS/MVS ***** * STEPS TO PERFORM * ***** 1. This PTF updates load module OPRWFU. APPLY of this PTF updates SMP/E Target loadlib CCLXLOAD. 2. Copy the updated load modules from SMP/E Target loadlib CCLXLOAD to any other deployed copies, such as a STEPLIB	CA OPS/MVS Base	Release 13.5
CA OPS/MVS Base	Release 13.5		

Service	Details
	used by the OPS/MVS main address space, a link listed loadlib, etc. 3. If the system library lookaside (LLA) program is managing any updated loadlib, you must refresh LLA by using MVS system command "F LLA,REFRESH" or some equivalent mechanism. 4. If the system link pack area (LPA) contains any updated load module, you must refresh LPA by using MVS system command "SETPROG LPA" or some equivalent mechanism. 5. Choose one of these two methods to begin using the updated load module: a. STOP OPS/MVS and START OPS/MVS OR b. Issue MVS command: F OPSS,RELOAD(OPRWFU) and restart the OSF address spaces via OPSVIEW option 4.3, line command 'T'.)

Service	Details
SO12658	SO12658 M.C.S. ENTRIES = ++PTF (SO12658) Security or Integrity Problem PROBLEM DESCRIPTION: Security or Integrity Problem. SYMPTOMS. N/A IMPACT. Security or Integrity Problem. CIRCUMVENTION: N/A PRODUCT(S) AFFECTED: CA OPS/MVS Base Release 13.5 Related Problem: OPSMVS 1657 Copyright (C) 2020 CA. All rights reserved. R00257-CLX135-SP1 DESC(Security or Integrity Problem). ++VER (Z038) FMID (CCLXD50) PRE (S000476 S004411 S006502 S008471 S009364 S009794 S010262 S010476 S011445) SUP (AS10476 S005690 S005965 ST05690 ST05965 ST12069 ST12080 ST12658) ++HOLD (SO12658) SYSTEM FMID(CCLXD50) REASON (ACTION) DATE (20100) COMMENT (<pre> +-----+ CA OPS/MVS Base Release 13.5 +-----+ SEQUENCE After Apply PTF +-----+ PURPOSE To activate load modules updated by this PTF +-----+ USERS All OPS/MVS users AFFECTED +-----+ KNOWLEDGE Basic z/OS systems programming skills REQUIRED +-----+ ACCESS - Access to OPS/MVS SMP/E Target loadlib CCLXLOAD and any REQUIRED deployed copies - Authority to issue MVS system commands - Authority to stop and start OPS/MVS +-----+ ***** * STEPS TO PERFORM * ***** 1. This PTF updates load modules identified by the ++MOD statements contained in this PTF. APPLY of this PTF updates SMP/E Target loadlib CCLXLOAD. 2. Copy the updated load modules from SMP/E Target loadlib CCLXLOAD to any other deployed copies, such as a STEPLIB used by the OPS/MVS main address space, a link listed </pre>

Service	Details
	loadlib, etc. 3. If the system library lookaside (LLA) program is managing any updated loadlib, you must refresh LLA by using MVS system command "F LLA,REFRESH" or some equivalent mechanism. 4. TSO users must get out of OPSVIEW. 5. Stop OPS/MVS. 6. If the system link pack area (LPA) contains any updated load modules, you must refresh LPA by using MVS system command "SETPROG LPA" or some equivalent mechanism. 7. Start OPS/MVS. 8. TSO users may access OPSVIEW. Depending on how OPSVIEW is accessed, this may require TSO logoff/logon.).

Service	Details
SO12673	SO12673 M.C.S. ENTRIES = ++PTF (SO12673) PASSWORD MASKING IGNORED FOR SECURITY EVENT PROBLEM DESCRIPTION: Password masking not working for SEC Events SYMPTOMS: Passwords are not masked in OPSLOG for SEC Events IMPACT: Potential password exposure CIRCUMVENTION: None PRODUCT(S) AFFECTED: CA OPS/MVS Base Version 13.0 CA OPS/MVS Base Release 13.5 Related Problem: OPSMVS 1670 Copyright (C) 2020 CA. All rights reserved. R00258-CLX135-SP1 DESC(PASSWORD MASKING IGNORED FOR SECURITY EVENT). ++VER (Z038) FMID (CCLXD50) SUP (ST12673) ++HOLD (SO12673) SYSTEM FMID(CCLXD50) REASON (DYNACT) DATE (20100) COMMENT (<pre> +-----+ CA OPS/MVS Base Release 13.5 +-----+ SEQUENCE After APPLY +-----+ PURPOSE To activate load modules updated by this PTF, including load module OPSAEX +-----+ USERS All OPS/MVS users AFFECTED +-----+ KNOWLEDGE Basic z/OS systems programming skills REQUIRED +-----+ ACCESS - Access to OPS/MVS SMP/E Target loadlib CCLXLOAD and any REQUIRED deployed copies - Authority to issue MVS system commands - Authority to stop and start OPS/MVS +-----+ ***** * STEPS TO PERFORM * ***** 1. This PTF updates load module OPSAEX, as well as the other load modules identified by the ++MOD statements contained in this PTF. APPLY of this PTF updates SMP/E Target loadlib CCLXLOAD. 2. Copy the updated load modules from SMP/E Target loadlib CCLXLOAD to any other deployed copies, such as a STEPLIB used by the OPS/MVS main address space, a link listed </pre>

Service	Details
	loadlib, etc. 3. If the system library lookaside (LLA) program is managing any updated loadlib, you must refresh LLA by using MVS system command "F LLA,REFRESH" or some equivalent mechanism. 4. TSO users must get out of OPSVIEW. 5. Stop OPS/MVS. 6. If the system link pack area (LPA) contains any updated load module, you must refresh LPA by using MVS system command "SETPROG LPA" or some equivalent mechanism. 7. Start OPS/MVS. 8. TSO users may access OPSVIEW. Depending on how OPSVIEW is accessed, this may require TSO logoff/logon.).

Service	Details
SO12676	SO12676 M.C.S. ENTRIES = ++PTF (SO12676) SOC4 ABEND DURING SHUTDOWN WITH INITADMINUI=YES PROBLEM DESCRIPTION: Following ABEND occurs during OPS/MVS shutdown when INITADMINUI=YES. ABEND X'000C4000' in Notify initialization/termination OPMTCAIN+X'000009E0' detected at OPMTCAIN+X'000002C4' SYMPTOMS: OPS9500S ABEND X'000C4000' in Notify initialization/termination OPMTCAIN+X'000009E0' detected at OPMTCAIN+X'000002C4' message is issued. IMPACT: None. Product shuts down normally. CIRCUMVENTION: None. PRODUCT(S) AFFECTED: CA OPS/MVS Base Version 13.0 CA OPS/MVS Base Release 13.5 Related Problem: OPSMVS 1666 Copyright (C) 2020 CA. All rights reserved. R00259-CLX135-SP1 DESC(SOC4 ABEND DURING SHUTDOWN WITH INITADMINUI=YES). ++VER (Z038) FMID (CCLXD50) PRE (SO00476 SO04411 SO05680 SO06939 SO09364 SO10241 SO10450 SO10726 SO11144) SUP (AS00476 SO01297 SO01752 SO05727 SO12101 ST01297 ST01752 ST05727 ST12101 ST12676)

Service	Details		
SO12722	SO12722 M.C.S. ENTRIES = ++PTF (SO12722) OPSJES2 NOT DISPLAYING REMOTE PRINTERS PROBLEM DESCRIPTION: The OPSJES2 function is not returning remote printer information after upgrading to z/OS 2.4. SYMPTOMS: The OPSJES2('I','PRTS','*','*') function returns only local printers. IMPACT: Automation using the OPSJES2 function to gather remote printer information will fail. CIRCUMVENTION: None. PRODUCT(S) AFFECTED: CA OPS/MVS Base Version 13.0 CA OPS/MVS Base Version 13.5 Related Problem: OPSMVS 1675 Copyright (C) 2020 CA. All rights reserved. R00262-CLX135-SP1 DESC(OPSJES2 NOT DISPLAYING REMOTE PRINTERS). ++VER (Z038) FMID (CCLXD50) SUP (S006788 S011878 S012591 S012622 ST06788 ST11878 ST12591 ST12622 ST12722) ++HOLD (SO12722) SYSTEM FMID(CCLXD50) REASON (DYNACT) DATE (20108) COMMENT (<table border="1"> <tr> <td>CA OPS/MVS Base</td><td>Release 13.5</td></tr> </table> SEQUENCE After APPLY PURPOSE To activate load modules updated by this PTF, including load module OPSAEX USERS All OPS/MVS users AFFECTED KNOWLEDGE Basic z/OS systems programming skills REQUIRED ACCESS - Access to OPS/MVS SMP/E Target loadlib CCLXLOAD and any REQUIRED deployed copies - Authority to issue MVS system commands - Authority to stop and start OPS/MVS ***** * STEPS TO PERFORM * ***** 1. This PTF updates load module OPSAEX, as well as the other load modules identified by the ++MOD statements contained in this PTF. APPLY of this PTF updates SMP/E Target loadlib CCLXLOAD.	CA OPS/MVS Base	Release 13.5
CA OPS/MVS Base	Release 13.5		

Service	Details
	2. Copy the updated load modules from SMP/E Target loadlib CCLXLOAD to any other deployed copies, such as a STEPLIB used by the OPS/MVS main address space, a link listed loadlib, etc. 3. If the system library lookaside (LLA) program is managing any updated loadlib, you must refresh LLA by using MVS system command "F LLA,REFRESH" or some equivalent mechanism. 4. TSO users must get out of OPSVIEW. 5. Stop OPS/MVS. 6. If the system link pack area (LPA) contains any updated load module, you must refresh LPA by using MVS system command "SETPROG LPA" or some equivalent mechanism. 7. Start OPS/MVS. 8. TSO users may access OPSVIEW. Depending on how OPSVIEW is accessed, this may require TSO logoff/logon.).

Service	Details		
SO12733	SO12733 M.C.S. ENTRIES = ++PTF (SO12733) POSSIBLE ABEND SOC4 AFTER INSTALLING IBM PTF UJ01558 PROBLEM DESCRIPTION: After UJ01558 is installed, 64-bit storage services (IARV64 and IARST64) may return with unpredictable values in access register 0, 1, 14, and 15. This may cause SOC4 ABENDS in various OPS/MVS modules that operate in AR mode. SYMPTOMS: Potential ABEND SOC4 in OPS/MVS modules OPSMMG, OPIIUASM, and OPMTCAUP. IMPACT: There are no known instances of actual ABENDS in OPS/MVS due to UJ01558. However, it is possible that an SOC4 might occur in a rare codepath, leading to loss of an automation event, or even total product shutdown. CIRCUMVENTION: NONE. PRODUCT(S) AFFECTED: CA OPS/MVS Base Version 13.0 CA OPS/MVS Base Version 13.5 Related Problem: OPSMVS 1673 Copyright (C) 2020 CA. All rights reserved. R00263-CLX135-SP1 DESC(POSSIBLE ABEND SOC4 AFTER INSTALLING IBM PTF UJ01558). ++VER (Z038) FMID (CCLXD50) PRE (S000476 S004411 S005680 S006939 S008471 S010262 S011445 S012658) SUP (ST12694 ST12733) ++HOLD (SO12733) SYSTEM FMID(CCLXD50) REASON (DYNACT) DATE (20100) COMMENT (<table border="1"> <tr> <td>CA OPS/MVS Base</td><td>Release 13.5</td></tr> </table> SEQUENCE After APPLY PURPOSE To activate load modules updated by this PTF, including load module OPSAEX USERS All OPS/MVS users AFFECTED KNOWLEDGE Basic z/OS systems programming skills REQUIRED ACCESS - Access to OPS/MVS SMP/E Target loadlib CCLXLOAD and any REQUIRED deployed copies - Authority to issue MVS system commands - Authority to stop and start OPS/MVS ***** * STEPS TO PERFORM * *****	CA OPS/MVS Base	Release 13.5
CA OPS/MVS Base	Release 13.5		

Service	Details
	1. This PTF updates load module OPSAEX, as well as the other load modules identified by the ++MOD statements contained in this PTF. APPLY of this PTF updates SMP/E Target loadlib CCLXLOAD. 2. Copy the updated load modules from SMP/E Target loadlib CCLXLOAD to any other deployed copies, such as a STEPLIB used by the OPS/MVS main address space, a link listed loadlib, etc. 3. If the system library lookaside (LLA) program is managing any updated loadlib, you must refresh LLA by using MVS system command "F LLA,REFRESH" or some equivalent mechanism. 4. TSO users must get out of OPSVIEW. 5. Stop OPS/MVS. 6. If the system link pack area (LPA) contains any updated load module, you must refresh LPA by using MVS system command "SETPROG LPA" or some equivalent mechanism. 7. Start OPS/MVS. 8. TSO users may access OPSVIEW. Depending on how OPSVIEW is accessed, this may require TSO logoff/logon.).

CA OPS/MVS for JES2 13.5
CA RS 2005 Product/Component Listing

18

Product Family	Product	Release
Systems Management	CA OPS/MVS BASE	13.05.00
The CA RS 2005 Product/Component Count for this release is 1		

CA OPS/MVS for JES2 13.5
All CA RS Levels Service List

CA RS Level	Service	FMID
CAR2005	S012733	CCLXD50
	S012722	CCLXD50
	S012676	CCLXD50
	S012673	CCLXD50
	S012658	CCLXD50
	S012630	CCLXD50
	S012622	CCLXD50
	S012418	CCLXD50
CAR2004	S012591	CCLXD50
	S012414	CCLXD50
	S012403	CCLXD50
	S012373	CCLXD51
CAR2003	S012139	CCLXD50
	S012138	CCLXD50
	S012101	CCLXD50
	S012096	CCLXD50
	S012060	CCLXD50
	S012013	CCLXD50
	S011954	CCLXD50
	S011953	CCLXD50
	S011878	CCLXD50
	S011877	CCLXD51
	S011812	CCLXD50
CAR2002	S011652	CCLXD50
	S011596	CCLXD51
	S011591	CCLXD50
	S011514	CCLXD50
	S011508	CCLXD50
	S011488	CCLXD51
	S011487	CCLXD50
	S011445	CCLXD50
	S011438	CCLXD51
	S011437	CCLXD50
	S011434	CCLXD50
	S011428	CCLXD50
	S011347	CCLXD50
	S011214	CCLXD50
	S006491	CCLXD50
CAR2001	S011260	CCLXD50
	S011241	CCLXD50
	S011213	CCLXD50
	S011203	CCLXD50
	S011188	CCLXD51
	S011144	CCLXD50
	S011125	CCLXD50
	S011100	CCLXD50
	S011092	CCLXD50

CA RS Level	Service	FMID
	S010733	CCLXD51
CAR1912	S010914	CCLXD50
	S010765	CCLXD50
	S010764	CCLXD50
	S010726	CCLXD50
	S010719	CCLXD50
	S010672	CCLXD50
	S010613	CCLXD50
	S010552	CCLXD50
CAR1911	S010490	CCLXD50
	S010476	CCLXD50
	S010453	CCLXD50
	S010450	CCLXD50
	S010413	CCLXD50
	S010402	CCLXD50
	S010384	CCLXD50
	S010262	CCLXD50
CAR1910	S010241	CCLXD50
	S010050	CCLXD50
	S010024	CCLXD50
	S009878	CCLXD50
	S009794	CCLXD50
	S009449	CCLXD50
	S008614	CCLXD51
	S008478	CCLXD50
CAR1909	S009846	CCLXD50
	S009840	CCLXD50
	S009667	CCLXD50
	S009544	CCLXD50
	S009387	CCLXD50
	S009094	CCLXD50
CAR1908	S009364	CCLXD50
	S009193	CCLXD50
	S009160	CCLXD50
	S009115	CCLXD50
CAR1907	S009020	CCLXD50
	S009000	CCLXD50
	S008999	CCLXD50
	S008872	CCLXD50
	S008831	CCLXD50
	S008829	CCLXD50
	S008714	CCLXD50
	S008712	CCLXD50
	S008651	CCLXD50
	S008640	CCLXD50
	S008475	CCLXD51
	S008474	CCLXD50

CA RS Level	Service	FMID
CAR1906	S008647	CCLXD50
	S008645	CCLXD50
	S008583	CCLXD50
	S008572	CCLXD50
	S008535	CCLXD50
	S008471	CCLXD50
	S008386	CCLXD50
	S008367	CCLXD51
	S008357	CCLXD50
	S008339	CCLXD50
	S008299	CCLXD50
	S008241	CCLXD50
	S008166	CCLXD53
	S006836	CCLXD50
CAR1905	S008113	CCLXD50
CAR1904	S007801	CCLXD50
	S007732	CCLXD50
	S007650	CCLXD50
	S007596	CCLXD51
	S007510	CCLXD50
CAR1903	S007406	CCLXD50
	S007289	CCLXD50
	S007231	CCLXD51
	S007197	CCLXD50
CAR1902	S007182	CCLXD51
	S007131	CCLXD50
	S006990	CCLXD50
	S006965	CCLXD50
	S006962	CCLXD50
	S006939	CCLXD50
	S006933	CCLXD50
	S006920	CCLXD51
	S006788	CCLXD50
CAR1901	S006555	CCLXD50
	S006527	CCLXD50
	S006526	CCLXD50
	S006167	CCLXD51
	S006166	CCLXD50
CAR1812	S006502	CCLXD50
	S006380	CCLXD51
	S006379	CCLXD50
	S006345	CCLXD50
	S006257	CCLXD50
	S006212	CCLXD50
	S006109	CCLXD50
	S005996	CCLXD51
CAR1811	S006105	CCLXD50

CA OPS/MVS for JES2 13.5
All CA RS Levels Service List

CA RS Level	Service	FMID
	S006042	CCLXD50
	S005965	CCLXD50
	S005934	CCLXD50
	S005908	CCLXD51
	S005737	CCLXD51
	S005727	CCLXD50
	S005704	CCLXD50
	S005690	CCLXD50
CAR1810	S005680	CCLXD50
	S005674	CCLXD50
	S005661	CCLXD50
	S005638	CCLXD51
	S005619	CCLXD50
	S005593	CCLXD51
	S005592	CCLXD50
	S005541	CCLXD50
	S005320	CCLXD50
	S005285	CCLXD50
	S005275	CCLXD50
CAR1809	S005192	CCLXD51
	S005191	CCLXD50
	S005047	CCLXD50
	S005042	CCLXD50
	S004989	CCLXD50
	S004944	CCLXD50
	S004928	CCLXD50
	S004900	CCLXD50
	S004898	CCLXD50
	S004808	CCLXD50
	S004772	CCLXD50
	S004680	CCLXD50
	S004634	CCLXD50
CAR1808	S004649	CCLXD50
	S004626	CCLXD50
	S004490	CCLXD50
	S004412	CCLXD51
	S004411	CCLXD50
	S004296	CCLXD51
CAR1807	S003933	CCLXD50
	S003910	CCLXD50
	S003905	CCLXD50
	S003594	CCLXD50
	S001859	CCLXD50
CAR1806	S003775	CCLXD51
	S003731	CCLXD50
	S003595	CCLXD51
	S001956	CCLXD50

CA RS Level	Service	FMID
	S001943	CCLXD51
	S001874	CCLXD50
	S001813	CCLXD50
	S001752	CCLXD50
CAR1805	S001580	CCLXD50
	S001320	CCLXD50
	S001297	CCLXD50
	S001270	CCLXD50
	S001221	CCLXD50
CAR1804	S001097	CCLXD50
	S001092	CCLXD50
	S001061	CCLXD50
	S000908	CCLXD50
	S000873	CCLXD51
	S000597	CCLXD50
CAR1803	S000632	CCLXD50
	S000630	CCLXD50
	S000572	CCLXD50
	S000562	CCLXD50
	S000476	CCLXD50
	S000444	CCLXD50
	S000393	CCLXD50
	S000371	CCLXD50
	S000247	CCLXD50
	S000245	CCLXD50
	S000239	CCLXD50
	S000236	CCLXD51
	S000235	CCLXD50