

CA ARCserve® Backup for Windows

Command Line Reference Guide

r15



This documentation and any related computer software help programs (hereinafter referred to as the "Documentation") are for your informational purposes only and are subject to change or withdrawal by CA at any time.

This Documentation may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of CA. This Documentation is confidential and proprietary information of CA and may not be used or disclosed by you except as may be permitted in a separate confidentiality agreement between you and CA.

Notwithstanding the foregoing, if you are a licensed user of the software product(s) addressed in the Documentation, you may print a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all CA copyright notices and legends are affixed to each reproduced copy.

The right to print copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to CA that all copies and partial copies of the Documentation have been returned to CA or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, CA PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL CA BE LIABLE TO THE END USER OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF CA IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is CA.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2010 CA. All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

CA Product References

This document references the following CA products:

- BrightStor® Enterprise Backup
- CA Antivirus
- CA ARCserve® Assured Recovery™
- CA ARCserve® Backup Agent for Advantage™ Ingres®
- CA ARCserve® Backup Agent for Novell Open Enterprise Server for Linux
- CA ARCserve® Backup Agent for Open Files on NetWare
- CA ARCserve® Backup Agent for Open Files on Windows
- CA ARCserve® Backup Client Agent for FreeBSD
- CA ARCserve® Backup Client Agent for Linux
- CA ARCserve® Backup Client Agent for Mainframe Linux
- CA ARCserve® Backup Client Agent for NetWare
- CA ARCserve® Backup Client Agent for UNIX
- CA ARCserve® Backup Client Agent for Windows
- CA ARCserve® Backup Enterprise Option for AS/400
- CA ARCserve® Backup Enterprise Option for Open VMS
- CA ARCserve® Backup for Microsoft Windows Essential Business Server
- CA ARCserve® Backup for Windows
- CA ARCserve® Backup for Windows Agent for IBM Informix
- CA ARCserve® Backup for Windows Agent for Lotus Domino
- CA ARCserve® Backup for Windows Agent for Microsoft Exchange Server
- CA ARCserve® Backup for Windows Agent for Microsoft SharePoint Server
- CA ARCserve® Backup for Windows Agent for Microsoft SQL Server
- CA ARCserve® Backup for Windows Agent for Oracle
- CA ARCserve® Backup for Windows Agent for Sybase
- CA ARCserve® Backup for Windows Agent for Virtual Machines
- CA ARCserve® Backup for Windows Disaster Recovery Option
- CA ARCserve® Backup for Windows Enterprise Module

- CA ARCserve® Backup for Windows Enterprise Option for IBM 3494
- CA ARCserve® Backup for Windows Enterprise Option for SAP R/3 for Oracle
- CA ARCserve® Backup for Windows Enterprise Option for StorageTek ACSLS
- CA ARCserve® Backup for Windows Image Option
- CA ARCserve® Backup for Windows Microsoft Volume Shadow Copy Service
- CA ARCserve® Backup for Windows NDMP NAS Option
- CA ARCserve® Backup for Windows Serverless Backup Option
- CA ARCserve® Backup for Windows Storage Area Network (SAN) Option
- CA ARCserve® Backup for Windows Tape Library Option
- CA ARCserve® Backup Patch Manager
- CA ARCserve® Backup UNIX and Linux Data Mover
- CA ARCserve® D2D
- CA ARCserve® High Availability
- CA ARCserve® Replication
- CA VM:Tape for z/VM
- CA 1® Tape Management
- Common Services™
- eTrust® Firewall
- Unicenter® Network and Systems Management
- Unicenter® Software Delivery
- Unicenter® VM:Operator®

Contact CA

Contact Technical Support

For your convenience, CA provides one site where you can access the information you need for your Home Office, Small Business, and Enterprise CA products. At [CA ARCserve Backup Support](#), you can access the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- CA Support policies and guidelines
- Other helpful resources appropriate for your product

Provide Feedback

If you have comments or questions about CA product documentation, you can send a message to techpubs@ca.com.

If you would like to provide feedback about CA product documentation, complete our short [customer survey](#), which is also available on the CA Support website, found at <http://ca.com/docs>.

Contents

Chapter 1: Introduction	13
Options and Arguments	14
Syntax Characters	14
Chapter 2: authsetup - Authentication Setup Command	17
Syntax	17
Usage	17
Examples	18
Chapter 3: bab - CA ARCserve Backup Services Command	19
Syntax	20
Usage	21
Examples	23
Chapter 4: ca_auth - Authentication Command	25
Syntax	26
Usage	26
Miscellaneous Options	27
User Arguments	28
Role Arguments	30
Equivalence Arguments	32
Examples	33
Chapter 5: ca_backup - Backup Manager Command	35
Syntax	35
Usage	36
Miscellaneous Options	37
Global Job Options	39
Backup Media Options	39
Verification Options	43
File Retry/Sharing Options	44
Operation Options	45
Pre/Post Options	48
Log Options	50
Virus Options	51

Media Exporting Options	52
Advanced Options	53
VSS Options	55
Global Filter Options	56
Source Arguments	59
Node Options	61
Volume Options	63
Database Options	64
Oracle Database Options	65
Oracle RMAN Database Options	67
Exchange DOC Level Database Options	72
Exchange DB Level Database Options	75
SQL Server Database Options	76
Sybase Agent Database Options	79
Informix Agent Database Options	80
VSS Agent Database Options	81
Lotus Agent Database Options	84
Destination Arguments	84
Schedule Arguments	86
Run Job Arguments	94
Staging Options	95
Disk Staging Options	95
Tape Staging Options	101
Return Codes	106
Examples	107

Chapter 6: ca_dbmgr - Database Manager Command **111**

Syntax	111
Usage	112
Miscellaneous Options	113
Display Options	114
Media Pool Management Options	116
Database Management Options	117
Maintenance Options	118
Migration Status Options	119
Examples	120

Chapter 7: ca_devmgr - Device Manager Command **123**

Syntax	123
Usage	124
Miscellaneous Options	124

General Options	125
Tape Drive Options	127
Tape Library Options	129
FSD Options	134
Examples	145

Chapter 8: ca_jobsecmgr - Job Security Manager Command **147**

Syntax	147
Usage	147
Server Arguments	148
Current Security Options	148
New Security Options	149
Examples	149

Chapter 9: ca_log - Log Command **151**

Syntax	151
Usage	151
Miscellaneous Options	152
Log Name Manipulation Options	152
View Options	153
Purge Options	155
Examples	156

Chapter 10: ca_merge - Merge Manager Command **157**

Syntax	157
Usage	158
Miscellaneous Options	158
Source Arguments	159
Run Job Arguments	160
Merge Options	161
Return Codes	166
Examples	166

Chapter 11: ca_mmo - Media Management Administrator Command **169**

Syntax	170
Options	171
Examples	173

Chapter 12: ca_qmgr - Queue Manager Command **175**

Syntax	176
Usage	177
Miscellaneous Options	177
Job Queue Commands	178
Job Specific Commands	180
Job Script Commands	183
Examples	185

Chapter 13: ca_recoverdb - Database Recovery Command **187**

Syntax	188
Options	189
Examples	190

Chapter 14: ca_restore - Restore Manager Command **191**

Syntax	191
Usage	192
Miscellaneous Options	192
Global Job Options	194
Restore Media Options	194
Destination Options	195
Operation Options	197
Pre/Post Options	199
Log Options	200
Virus Options	201
Global Filter Options	202
Source Arguments	204
Destination Arguments	206
Database Options	207
Oracle Database Options	209
Oracle RMAN Database Options	211
Exchange DOC Level Database Options	216
Exchange DB Level Database Options	217
SQL Server Database Options	219
Sybase Agent Database Options	224
Informix Agent Database Options	224
VSS Agent Database Options	225
Lotus Agent Database Options	226
Run Job Arguments	227
Info Arguments	228
Return Codes	230

Examples	231
----------------	-----

Chapter 15: ca_scan - Scan Manager Command **233**

Syntax	233
Usage	233
Miscellaneous Options	234
Source Arguments	235
Run Job Arguments	236
Scan Options	237
Decryption Password List Options	238
Logging Options	238
Pre/Post Options	239
Exit Code Options	240
Media Options	240
Miscellaneous Scan Options	241
Job Status Options	241
Return Codes	242
Examples	242

Chapter 16: ca_vcbspopulatedb - VMware VCB Utility Command **243**

Syntax	244
Usage	244
Create a ca_vcbspopulatedb Configuration File	247
Utility Return Codes	248
Examples	248

Chapter 17: ca_msxmpopulatedb - Hyper-V VM Utility Command **251**

Syntax	251
Usage	252
Utility Return Codes	253
Examples	253

Chapter 18: cabatch - Batch Command **255**

Submit a Job	256
Delete a Job	258
Modify a Job	259
Examples	260

Chapter 19: careports - Report Writer Command	261
Syntax	261
Options	262
Examples	263
Chapter 20: caadvreports - Advanced Report Generator Command	265
Syntax	265
caadvreports - Reports	266
caadvreports - Options	269
Examples	272
Chapter 21: pfc - Preflight Checklist Utility Command	273
Syntax	274
Usage	274
Preflight Checks	274
Examples	278
Chapter 22: tapecomp - Tape Compare Utility	279
Syntax	279
Options	279
Examples	280
Chapter 23: tapecopy - Tape Copy Tool Command	281
Syntax	281
Usage	281
Database Query Options	282
Destination Arguments	285
Source Arguments	289
Examples	292
Chapter 24: Miscellaneous Utility Commands	295
DumpDB Utility	295
IsSafe.bat Utility	299
Mergecat Utility	300
MergeOLF Utility	301
Index	303

Chapter 1: Introduction

A command line interface (CLI) is a method of interacting with a computer by submitting lines of textual commands (a sequence of characters) either from keyboard input or from a script. In its simplest form, the computer displays a prompt, the user enters a command on the keyboard and terminates the command with a keyboard key (usually the Enter key), and the computer then executes the command.

CA ARCserve Backup command line utilities allow direct control (using the command prompt) over all operations that can be performed by a CA ARCserve Backup server. The CA ARCserve Backup command line utilities provide an alternative method of accessing almost all of the operations available from the various CA ARCserve Backup Managers. The command line interface also offers the added benefit of creating batch files that can be automatically executed by other programs.

To use the command line interface feature, the complete CA ARCserve Backup system must be installed on the server and the CA ARCserve Home Directory variable must be set.

As an alternative to using the command line, any command you can enter can also be submitted using the Generic Job Manager. Using the Generic Job Manager provides these benefits:

- The job appears in the Activity Log.
- You can submit repeating jobs.

Important! Make sure that you use the correct syntax when using the Command Line Interface (CLI). Avoid using file names or database names that have the same titles as CLI options. The CLI does not support backup of some special files or databases, such as "- filesystem" or "-database" which have the same titles as CLI options. For example, if you want to back up some files titled "-database", the job will fail because -database is also a CLI global option for CA ARCserve Backup.

Options and Arguments

A command line uses options and arguments to provide specific instructions to tell a computer to do something, such as execute (or run) a program.

- An argument, also called a command line argument, is a file name or other data that is provided to a command in order for the command to use it as an input. Arguments are pieces of information that tell a command what to do and where to send the results.
- An option is a type of argument that modifies the behavior of the command. An option, also referred to as a flag or a switch, is a single-letter or full word that modifies the way a command behaves in some predetermined way. An option is preceded by a hyphen or minus sign (-).

You can combine several command line options into a file called an argument file.

Syntax Characters

Within a command line syntax, certain characters and formatting have special significance and meaning. The command line syntax within this document use the following character format:

Square Brackets []

The square brackets ([]) indicate that the enclosed element (parameter, value, or information) is *optional*. You can choose one or more items or no items. Do not type the square brackets themselves in the command line.

Example: [global options], [source arguments], [destination arguments]

Angle Brackets < >

The angle brackets (< >) indicate that the enclosed element (parameter, value, or information) is *mandatory*. You are required to replace the text within the angle brackets with the appropriate information. Do not type the angle brackets themselves in the command line.

Example: -f [set the File Name variable], -printer <printer name>, -repeat <months> <days> <hours> <minutes>, date access <mm/dd/yyyy>

Ellipsis ...

The ellipsis symbol of three periods (...) means "and so on" and indicates that the preceding element (parameter, value, or information) can be repeated several times in a command line.

Example: -jobid <job id1, job id2, job id3,...>, [-exitcode <exit code 1>, <exit code2>, <exit code3> ...]

Pipe |

The pipe symbol (vertical line) means "or" and indicates a choice within an element. If two arguments are separated by the pipe symbol, you can select the element to the left of the separator or the element to the right of the separator. You cannot select both elements in a single use of the command. Within square brackets, the choices are optional. Within angle brackets, at least one choice is required.

Example: `-ca_backup [-custom|-rotation|-gfsrotation], -excludeday <Sun|Mon|Tue|Wed|Thu|Fri|Sat>, -runjob <start|stop>`

Italics

Italic text indicates information that you must supply with the appropriate value. It is an option or parameter to be replaced with a value.

Example: `-sessionpassword session password, -f [set the File Name variable], -printer <printer name>`

Note: Command line syntax, including user names, passwords, and file names used in UNIX and Linux platforms are case-sensitive. For example, `commandline`, `CommandLine`, and `COMMANDLINE` are not the same.

Chapter 2: authsetup - Authentication Setup Command

The authentication setup command (authsetup) lets you initialize the CA ARCserve Backup authentication database on the primary server. You can also use this to set the password for caroot, create equivalences for the current operating system user on all primary and member servers of a CA ARCserve Backup domain, and to create equivalences for the CA ARCserve Backup System Account user on all primary and member servers of a CA ARCserve Backup domain.

Syntax

The authsetup command line syntax is formatted as follows:

```
authsetup
  -p <new password>
  -s
  -d
```

Usage

The authsetup command contains options that are used to define actions to follow when setting up the CA ARCserve Backup authentication database.

The authsetup command includes the following options:

-p <password>

Specify the password for 'caroot'. This is required. To set an empty password, use authsetup -p "".

-s

This is silent mode for this utility. Use this if you do not want to see message box notifications if some internal operations fail.

-d

Use this to create debug logs for each authsetup usage.

Examples

The following are examples of syntax for the `authsetup` command:

- Use the following command to reset `caroot` password to a new password `"root"` and re-create equivalence for logged in User :

```
authsetup -p "root"
```

- Use the following command to reset `caroot` password to empty password and re-create equivalence for logged in User :

```
authsetup -p ""
```

- Use the following command to reset `caroot` password to a new password `"root"` and re-create equivalence for logged in User. Enable Silent mode and debugging :

```
authsetup -p "root" -s -d
```

Chapter 3: bab - CA ARCserve Backup Services Command

The bab command controls the CA ARCserve Backup services. The bab management utility can be used to load and unload back-end services, display current status and configuration, reconfigure back-end services, and show whether or not the services are running.

The bab command works as a front-end to the CA ARCserve Service Controller service and requires that CA ARCserve Service Controller service be running for loading the back-end services.

The full set of CA ARCserve Backup back-end services includes five services:

- CA ARCserve Service Controller service
- CA ARCserve Domain Server service
- CA ARCserve Database Engine service
- CA ARCserve Tape Engine service
- CA ARCserve Job Engine service

Note: When a CA ARCserve Backup server is configured as cluster-aware, all critical ARCserve base-related services (not agent-related services) will be monitored by the applicable cluster service (MSCS or NEC CLUSTERPRO). If an ARCserve base-related service fails or needs to be shut down, the cluster service will automatically try to restart it or trigger a failover if the restart attempt fails. To run the this task, you must stop ARCserve services. However, in a cluster-aware environment, you must first manually stop the cluster service from continuing to monitor the service and attempting an automatic restart or failover. For procedures to stop HA service monitoring by the Cluster Service, see the Administration Guide.

Syntax

The bab command line syntax is formatted as follows:

```
bab [-cahost <hostname>]
    -load [procid ["all"]]
    -unbad [-force] [-quiet] [procid ["all"]]
    -show [-v] [procid ["all"]]
    -show dfg [-v] [procid ["all"]]
    -reconfig [procid ["all"]]
    -status [procid ["all"]]
    -removehost hostname
    -getprimary
    -getdomainservers
```

Note: The [-cahost <hostname>] switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the -cahost switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the -cahost switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that -cahost be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The bab command contains options that are used to define actions to follow when controlling the CA ARCserve Backup services.

The bab command includes the following options:

-cahost <hostname >

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: If you include -cahost in the command, you must also specify the hostname of the system (local or remote) hosting the operation.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the -cahost switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that -cahost be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

usage

Displays a list of basic bab commands.

-load

Starts CA ARCserve Backup daemons.

Loads a specified service or all services. By default, all services are loaded.

-unload [-force] [-quiet]

Stops CA ARCserve Backup daemons.

Unloads a specified service or the three services (cadbd, camediad, and caqd services) will be unloaded. By default, these three services will be unloaded.

-force

The -force option forces unloading even if a job is queued.

-quiet

The -quiet option suppresses messages.

-show [-v]

Shows the status of CA ARCserve Backup daemons.

Displays the configuration and current status of a specified service or all services. By default, all services are displayed.

-v

Increases the verbosity of the output for status and configuration options. Use the -v option to show the status of the daemons in verbose output.

When used with the -show command, the -v option displays the service name, location of the binary, state, registration status, and "kill" type. The kill type indicates whether a particular service is "immortal" (must be shut down with the -force switch), or "regular" (can be stopped as needed).

-showcfg [-v]

Shows the current status of a specific CA ARCserve Backup service or all CA ARCserve Backup services, as well as how the service is configured.

Displays the status of back-end services and their "kill" type (immortal or regular).

Services that are labeled as "regular", may be stopped as needed. Services labeled as "immortal" can not be stopped unless their termination is forced and all "regular" services have been unloaded.

-v

Increases the verbosity of the output for status and configuration options. Use the -v option to show the status of the daemons in verbose output.

When used with -showcfg, the -v option displays the service name, location of the binary, hostname, RPC program number, RPC program version number, process ID (PID), transport protocol, family, state, registration status, and "kill" type. The kill type indicates whether a particular service is "immortal" (must be shut down with the -force switch), or "regular" (can be stopped as needed).

-reconfig

Brings down a specific CA ARCserve Backup service or services, re-reads the configuration file, and brings the service up again with new configuration file settings.

This command makes a back-end service, when specified, caserved reread its configuration files and activates any changes it finds.

-status

Displays a brief status of services.

-removehost

Removes the host from your CA ARCserve Backup environment.

-getprimary

Returns the name of the Primary Server in the current domain or the domain where the specified host is located. You can provide the name of any Domain member (as the host server) to get the Primary server name.

By default, if the `-cahost` is not specified, it will find out the primary server of the local machine. If `-cahost` is specified, it will find out the primary server of the hostname.

-getdomainservers

Returns a list of all the servers in the current domain or the domain where specified host is located. You can provide the name of any domain member as the host server.

By default, if the `-cahost` is not specified, it will find out all the member servers in the local machine's domain. If `-cahost` is specified, it will find out all the member servers in the hostname's domain.

Examples

The following are examples of syntax for the `bab` command:

- Use the following command to display simplest service status:
`bab -status`
- Use the following command to display the configuration and current status of the job engine in verbose output:
`bab -show -v caqd`
- Use the following command to show the current status of the tape engine and how it is configured:
`bab -show cfg camediad`
- Use the following command to start the database engine:
`bab -load cadbd`
- Use the following command to stop the domains and authentication services if a job is queued:
`bab -unload cadiscovd -force`
- Use the following command to show the name of the Primary Server in the current domain:
`bab -getprimary`

Chapter 4: ca_auth - Authentication Command

The authentication command (`ca_auth`) is used when you are logged in as equivalent to `caroot` to create new users, delete existing users, change any user's password, and establish and delete equivalencies for other users. When you are logged in as equivalent to a user other than `caroot`, you can use `ca_auth` to change and validate your password.

Note: If you are logged in as a user who has no equivalence to any CA ARCserve Backup user, then you must be granted an equivalence before you can use `ca_auth`.

caroot

CA ARCserve Backup is designed with a root-level, super user profile, to which complete control of CA ARCserve Backup is granted. This profile, referred to as the "caroot" user profile, is set up during the first-time installation of CA ARCserve Backup.

The password for the `caroot` profile can be set during installation, or it can be set or changed later using `ca_auth` or `AuthSetup.exe`, located in the CA ARCserve Backup home directory. For security reasons, we recommend that you set a password on this account.

Note: The `caroot` user profile controls access to the CA ARCserve Backup Manager GUI and backup-related functions, and should not be confused with the security required to log in to your operating system.

caroot Equivalence

CA ARCserve Backup allows you to create users that are equivalent to `caroot`. A user that is equivalent to `caroot` has full access to all CA ARCserve Backup features, and can work with the command line utilities, such as `ca_backup` and `ca_restore`. Any Windows user on any host can be granted equivalence to `caroot`. To grant a user equivalence to `caroot`, you must either be logged in as equivalent to `caroot` or know the `caroot` password.

Console utilities such as `ca_backup`, `ca_restore`, and `ca_qmgr` work with remote CA ARCserve Backup servers for submitting and monitoring backup and restore jobs without requiring users to log in to CA ARCserve Backup every time for each command.

Syntax

The `ca_auth` command line syntax is formatted as follows:

```
ca_auth [-cahost <hostname>]
        -user [user arguments]
        -equiv [equivalence arguments]
        -role [role arguments]
        -f [set the File Name variable]
        -help
        -examples
```

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_auth` command allows you to set the following options and arguments:

- miscellaneous options
- user arguments
- role arguments
- equivalence arguments

Miscellaneous Options

The `ca_auth` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during an authentication process.

The `ca_auth` command includes the following miscellaneous options:

-cahost <hostname >

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: If you include `-cahost` in the command, you must also specify the hostname of the system (local or remote) hosting the operation.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-usage

Displays a list of basic `ca_auth` commands.

-help

Opens the `ca_auth` Help topic.

-examples

Opens a Help topic with `ca_auth` usage examples.

User Arguments

Before you can use CA ARCserve Backup, you must have a CA ARCserve Backup account. CA ARCserve Backup is designed with a root-level, super user profile, to which complete control of CA ARCserve Backup is granted. This profile, referred to as the "caroot" user profile, is set up during the first-time installation of CA ARCserve Backup.

The *caroot* user has Administrator privileges, and is created by the program at installation. The password for the *caroot* profile can be set during installation, or it can be set or changed later using *ca_auth* or *AuthSetup.exe*, located in the CA ARCserve Backup home directory. For security reasons, we recommend that you set a password on this account.

Note: The *ca_auth.exe* command only supports only CA ARCserve Backup native users, such as *caroot*, and does not support Windows Users, such as "domain\user" or "hostname\Administrator".

Note: The *caroot* user profile controls access to the CA ARCserve Backup GUI and backup-related functions, and should not be confused with the security required to log in to your operating system.

The *ca_auth* command includes the following user arguments:

ca_auth [-cahost host] -user

```
add username [passwd] [-assignrole [rolelist]]
delete username
chgpasswd username [passwd]
chrole username [rolelist]
validate username [password]
group username
getall
```

add username [passwd] [-assignrole [rolelist]]

Adds a *username* with the specified password as a CA ARCserve Backup user.

Note: The *username* cannot contain the "\" character.

-assignrole [rolelist]

When you add a new user by `ca_auth`, you must also assign a role to the new user to create a User Profile. A User Profile is the combination of linking the user with the assigned role(s) and the associated permissions for the assigned role(s).

The current available role list is as follows:

- 1) Backup Operator
- 2) Restore Operator
- 3) Device Operator
- 4) Tape Operator
- 5) Security Administrator
- 6) Report Operator
- 7) Monitor Operator
- 8) ARCserve Administrator
- 9) Ownership Checking Exemption Privilege

When you include the `-assignrole` switch, you will also be prompted as follows:

Please assign roles for this user:

Each role has a corresponding number assigned to it. To assign a role to a new user, you must enter the role number after the `-assignrole` switch. To add multiple roles, you must insert a comma to separate each role.

For example:

- To assign a Security Administrator role to a new user, enter the following command:

```
ca_auth [-cahost host] -user add username [passwd] -assignrole 5
```

- To assign multiple roles to a new user, enter the following command:

```
ca_auth [-cahost host] -user add username [passwd] -assignrole 1,2,3,4,5
```

Note: For more information about User Profiles and role definitions, see the *Administration Guide*.

delete username

Deletes *username* from the authentication database.

chpasswd username [passwd]

Changes the password for the specified *username*.

chgrole username [rolelist]

Changes the assigned role(s) for an existing CA ARCserve Backup user.

validate *username* [*passwd*]

Checks if the specified username and password combination exists, is valid, and can be used to log in to the CA ARCserve Backup domain.

group *username*

Provides the name of the user group to which the specified user belongs.

getall

Lists all users known to CA ARCserve Backup Authentication Service.

Role Arguments

Each user should be assigned at least one role to create a User Profile. For each role there is a corresponding list of permissions. A User Profile is the combination of linking the user with the assigned role(s) and the associated permissions for the assigned role(s).

- Permission is the right to execute a specified operation in CA ARCserve Backup, for example, the permissions for format media, submit a backup job or a restore job, monitor job status, create reports, etc.
- Role is the combination of permissions.
- A user can be assigned with one or more roles.
- From a Role perspective, a role can be assigned to none or any number of users.
- From a Permission perspective, a permission can be included in one or multiple roles.

Note: For more information about User Profiles, see the *Administration Guide*.

To display the list of current available roles, along with the corresponding role description and role id, you must enter the following command:

```
ca_auth -role getall
```

-role

Displays the role arguments. This provides you with an easy way to find out the role id which could be used while adding a new user or changing the role of an existing user.

getall

Lists all roles known to CA ARCserve Backup Authentication Service.

The current available role list is as follows:

- 1) Backup Operator
- 2) Restore Operator
- 3) Device Operator
- 4) Tape Operator
- 5) Security Administrator
- 6) Report Operator
- 7) Monitor Operator
- 8) ARCserve Administrator
- 9) Ownership Checking Exemption Privilege

Equivalence Arguments

Equivalence allows you to create an equivalent user to *caroot*, if you know the password for *caroot*. Once you've designated a user on a given host as equivalent to *caroot*, you can access the entire authentication database as this user and have full access to all CA ARCserve Backup features.

To be able to use the CA ARCserve Backup command line utilities, you need to create the caroot equivalency for your system account. The caroot equivalency establishes the mapping of a user's login name with the CA ARCserve Backup user database. This allows the user to use the CA ARCserve Backup command line utilities. Any Windows user on any host can be granted equivalence to caroot. To grant a user equivalence to caroot, you must either be logged in as equivalent to caroot or know the caroot password.

Console utilities such as *ca_backup*, *ca_restore*, and *ca_qmgr* work with remote CA ARCserve Backup servers for submitting and monitoring backup and restore jobs without requiring users to log in to CA ARCserve Backup every time for each command.

The *ca_auth* command includes the following equivalency arguments:

```
ca_auth [-cahost host] -equiv
```

```
add ntuser hostName ARCserveUser [caroot_username] [caroot_password]
getequiv [ntuser hostName]
delete ntuser hostName [caroot_username] [caroot_password]
whoami
```

add ntuser hostName ARCserveUser [caroot_username] [caroot_password]

Creates an equivalence of the specified *user* on *host* to caroot.

getequiv [ntuser hostName]

Displays all equivalences for the specified *user* on *host* who runs this command.

delete ntuser hostName [caroot_username password]

Delete equivalence for UNIX *user* on *host*. Unless the current user is equivalent to *caroot*, credentials (i.e., caroot username and password) for the Administrator's account are required.

whoami

Displays the user name you are logged in as on the local machine.

Note: A user with read rights cannot grant somebody else read rights to an object they do not own.

Examples

The following are examples of syntax for the `ca_auth` command:

- Use the following command to change the password for the `caroot` user:

```
ca_auth -user chgpasswd caroot [passwd]
```

- Use the following command to add a user:

```
ca_auth -user add username [passwd]
```

- Use the following command to delete a user:

```
ca_auth -user delete username
```

- Use the following command to validate a user and the associated password:

```
ca_auth -user validate username [password]
```

- Use the following command to add a user (administrator) and a password (`caroot`):

```
ca_auth -user add administrator caroot
```

Note: You are prompted to enter the password for administrator in non-echo mode.

- Use the following command to list all CA ARCserve Backup users:

```
ca_auth -user getall
```

- Use the following command to add a Windows user (administrator) that has a `caroot` equivalency to CA ARCserve Backup Domain Server DOMAIN. The user name is `caroot` and the password is `ccb`:

```
ca_auth -equiv add administrator DOMAIN caroot ccb
```

- Use the following command to show the current CA ARCserve Backup user:

```
ca_auth -equiv whoami
```

`ca_auth` Equivalence Examples

- Use the following command to set up equivalency:

```
ca_auth -equiv add ntuser hostName ARCServeUser [caroot username] [caroot password]
```

For example, to add an equivalency for the Administrator on machine `dev02-vir2`:

```
ca_auth -equiv add Administrator dev02-vir2 'caroot' 'caroot password'
```

- Use the following command to display the equivalence for the user you are logged in as:

```
ca_auth -equiv getequiv
```

- Use the following command to display the equivalence for a user on a particular host machine:

```
ca_auth -equiv getequiv [ntuser hostName]
```

- Use the following command to delete the equivalency for a user:

```
ca_auth -equiv delete ntuser hostName [caroot username] [caroot password]
```

- Use the following command to see the user name you are logged in as on the local machine:

```
ca_auth -equiv whoami
```

- To use command line interface on one machine to manage another, you must add equivalency.

To add equivalency, perform the following steps:

1. Open the command line interface from <Machine A>
2. Enter the following command:

```
ca_auth -cahost <hostnameB> -equiv add <domainnameA\NT user(administrator)> <hostnameA>  
caroot caroot <passwdofcaroot>
```

Chapter 5: ca_backup - Backup Manager Command

The backup manager command (`ca_backup`), is the command line interface to the Backup Manager. All of the features available from the Backup Manager GUI are also available from the command line. Use this command to submit backup jobs to the CA ARCserve Backup queue, including setting all associated options, filtering, GFS Rotation and rotation jobs.

Important! Make sure that you use the correct syntax when using the Command Line Interface (CLI). Avoid using file names or database names that have the same titles as CLI options. The CLI does not support backup of some special files or databases, such as "- filesystem" or "-database" which have the same titles as CLI options. For example, if you want to back up some files titled "-database", the job will fail because `-database` is also a CLI global option for CA ARCserve Backup.

Syntax

The `ca_backup` command line syntax is formatted as follows:

```
ca_backup [-cahost <hostname>]
          [global options]
          [global filters]
          -source [source arguments]
          [destination arguments]
          [schedule arguments]
          [run job arguments]
```

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_backup` command allows you to set the following options and arguments:

- miscellaneous options
- backup options
- filter arguments
- source arguments
- destination arguments
- schedule arguments
- run job arguments
- disk staging options
- return codes

To build a backup operation, you must set one category of options at a time, in the order specified in the `ca_backup` syntax.

Miscellaneous Options

The `ca_backup` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during a backup process.

The `ca_backup` command includes the following miscellaneous options:

`ca_backup`

```
-cahost <hostname>]-list  
[-f [set the File Name variable]]  
[-clearconn]  
[-waitForJobStatus [-polling interval(secs)>]]  
[-help]  
[-examples]  
[-usage]  
[allusage]
```

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-list

Displays a list of all group names and corresponding media that is available for the backup job.

-f [set the File Name variable]

Used to specify a file name that contains the switches and parameters for the command.

This switch overcomes the shell limitation of 1024 character input from command line. You can also use this switch to hide passwords by saving them in a file.

-clearconn

Specifies to clear the user connections before performing the backup. Use this option to log all users off the server that you are backing up. Five minutes before the job is executed, CA ARCserve Backup sends a message asking users to log off the host server. After five minutes, CA ARCserve Backup will automatically log off any users still attached. You must have Supervisor or equivalent rights to use this option.

This option is not valid if you have selected PC Clients as your backup source.

Note: This argument applies to NetWare platforms only

-waitForJobStatus [<polling interval (secs)>]

When specified, the ca_backup command will wait until the job is completed, and exit with a [return code](#) (see page 106) that indicates the success or fail outcome of the job.

The <polling interval> value defines how often (in seconds) the ca_backup utility checks the job status with the Queue services. The default polling interval is 60 seconds.

Note: This is useful for Unicenter NSM Scheduling (formerly known as TNG).

-help

Opens the ca_backup Help topic.

-examples

Opens a Help topic with ca_backup usage examples.

-usage

Displays a list of basic ca_backup commands.

allusage

Displays a list of all ca_backup commands and their switches.

Global Job Options

The `ca_backup` global options allow you to specify various options that are applied to the entire job.

The `ca_backup` command provides the following global options:

- backup media options
- verification options
- file retry/sharing options
- operation options
- pre/post options
- log options
- virus options
- media exporting options
- advanced options
- VSS options

Backup Media Options

The `ca_backup` command includes the following global backup media options:

`ca_backup`

```
[-firsttapeopt <ow rtesameblank|ow rtesameblankany>]
[-firsttape timeout <minutes<1-9999>>]
[-spantapeopt <ow rtesameblank|ow rtesameblankany>]
[-spantape timeout <minutes<1-9999>>]
[-sessionpassword <session password>[-savepassword [-remindafter n]]]
[-encryption <encryption key> [-atagent|-atserverduringbackup|-atserverduringmigration][[-savepassword
[-remindafter n]]]
[-compression [-atagent|-atserver]]
[-medianame]
```

-firsttapeopt <owritesameblank | owritesameblankany>

Specify media options for the first media used in the backup job. By default, set to Overwrite Same media (append to media). Blank media and Any media are not the same. Any indicates a formatted media with a different media name than that provided in the job.

The media selection search order is from left to right. If the `owritesameblankany` option is specified, CA ARCserve Backup will first search for a media with the same name as the job. If one is found and is usable, the media is formatted using the same name, and used for the backup. If not, CA ARCserve Backup will search for a Blank media to use. If no Blank media is available, CA ARCserve Backup will then search for Any usable media to format and use for the backup.

Note: If the `-rotation schedule` argument is included, the specified rotation rules will override these options.

-firsttapetimeout <minutes<1-9999>>

Specify the time, in minutes, to wait for a usable media to be made available for a backup job. By default, this value is 5 minutes. If a usable media is not made available within this time period, the job times out and fails.

-spantapeopt <owritesameblank | owritesameblankany>

Specify media options for any span media used in the backup job. These options apply to jobs that require more than one media to determine the overwrite rules for the additional media. You need to specify which media CA ARCserve Backup can use when the job spans media.

The media selection search order is from left to right. By default, set to Overwrite Same or Blank. During spanning of tape, if the default is specified, CA ARCserve Backup first searches for a media with the same name and a higher sequence than the original tape. If a tape is found and is usable, the media is formatted and used as the next tape. If not, CA ARCserve Backup searches for a Blank media to use.

Note: If the `-rotation schedule` argument is included, the specified rotation rules will override these options.

-spantapetimeout <minutes<1-9999>>

Specify the time, in minutes, to wait for a usable span media to be made available for a backup job. By default, this value is infinite, and the job continues to wait and prompt until a usable media is loaded or the user cancels the job.

-sessionpassword <session password> [-savepassword [-remindafter n]]

Applies a password to each session backed up to media. To restore data from one of these sessions, the password must be provided.

-savepassword

Specifies to save the session password into the CA ARCserve Backup database for this backup job. If you do not include this switch, the session password will not be saved into the CA ARCserve Backup database.

-remindafter n

Specifies the number of days the session password is saved. After the specified number of days has elapsed, a reminder message prompting you to change your password will be logged in the Activity Log. The available range is 0 to 9999 days.

Note: For more information about importing and exporting session password from or to the CA ARCserve Backup database, see the [DumpDB Utility](#) (see page 295).

**-encryption <encryption key>
[-atagent|-atserverduringbackup|-atserverduringmigration]
[-savepassword [-remindafter n]]**

Encrypts files before the backup. To restore encrypted files, the encryption password must be provided.

To restore a session that was backed up using this argument, you must use the `ca_restore -tapesessionpw` argument to execute the restore job.

Note: For a deduplication device, you cannot include the `[-atagent|-atserverduringbackup|-atserverduringmigration]` switch.

- If you select `-atagent`, the encryption will be performed at the agent side. This is the default option.
- If you select `-atserverduringbackup`, the encryption will be performed at the server side during the backup process.
- If you select `-atserverduringmigration`, the encryption will be performed at the server side during the migration process.

-savepassword

Specifies to save the encryption password into the CA ARCserve Backup database for this backup job. By default, this option is selected.

-remindafter n

Specifies the number of days a encryption password is saved. After the specified number of days has elapsed, a reminder message prompting you to change your password will be logged in the Activity Log. The available range is 0 to 9999 days.

Note: For more information about importing and exporting session password from or to the CA ARCserve Backup database, see the [DumpDB Utility](#) (see page 295).

-compression [-atagent|-atserver]

Compresses files before the backup.

Note: For a deduplication device, you cannot include the `[-atagent|-atserver]` switch.

- If you select `-atagent`, the compression will be performed at the agent side. This is the default option.
- If you select `-atserver`, the compression will be performed at the server side.

-mediaby name

CA ARCserve Backup writes to any media that has the specified name, regardless of the media's ID or sequence number. This option is useful if you are running a repeating overwrite job with a specific media and you want to ensure that the same media is used for the job each time.

- When you include this option, CA ARCserve Backup looks for a media that has the specified name and uses it, regardless of the media's other identifying features.
- When you do not include this option, the second time the backup job is run, CA ARCserve Backup cannot always locate the original tape because some of its identifying features will have changed.

Note: If two or more media in the tape library have the same name, CA ARCserve Backup will use the first media in the device group that matches the specified name. Therefore, you should not use this option to perform a single occurrence overwrite.

Verification Options

The `ca_backup` command includes the following global miscellaneous options:

```
ca_backup [-scan |-compare]
```

-scan

Scans the backup media and checks the header of each file to verify the integrity of the backup. If the header is readable, the data is assumed to be reliable.

-compare

Reads blocks of data from the backup media and compares the data, byte for byte, against the source files on the source machine, to verify the integrity of the backup.

Note: The Compare Media to Disk option is not supported with agents for databases and applications.

File Retry/Sharing Options

The `ca_backup` command includes the following global file retry and sharing options:

```
ca_backup
  [-retry <off|now[later]||later[now]>]
  [-retrycount <count<1-9999>>]
  [-retryinterval <seconds<1-9999>>]
  [-accessmethod <denynoneifdenywritefails | lockifdenywritefails | denywrite | denynone>]
```

-retry <off|now[later]||later[now]>

Specifies retrying to back up open files missed during the initial backup.

-retrycount <count<1-9999>>

Specifies the number of retry attempts.

-retryinterval <seconds<1-9999>>

Specifies the interval (in seconds) between retry attempts.

-accessmethod <denynoneifdenywritefails | lockifdenywritefails | denywrite | denynone>

These are file sharing options:

denynoneifdenywritefails

CA ARCserve Backup attempts to place the file in deny write mode. If this is not possible because file is already open, it will be placed into deny none mode. This is the default setting.

lockifdenywritefails

CA ARCserve Backup attempts to place the file in deny write mode. If this is not possible because the file is already open, the file will be locked completely so that no user can open it or write to it. This option ensures that the most recent version of the file is backed up.

denywrite

Prevents another process from writing to the file while CA ARCserve Backup has it open. If another process opens the file before CA ARCserve Backup opens it, CA ARCserve Backup will not back up the file, unless you selected one of the open File Retry options.

denynone

Allows other processes to read or write to the file, regardless of whether CA ARCserve Backup opens it first or opens it after another process already has it open. Although the backed up file may not be the most recent version, this option ensures that the file is up-to-date.

Operation Options

The `ca_backup` command includes the following global operation options:

`ca_backup`

`[-backupasdb]`
`[-backupcatalog]`
`[-backupjobqueue]`
`[-noestimation]`
`[-createcrc]`
`[-deletefiles]`
`[-preserveaccessstime]`
`[-eject|-noeject]`
`[-partialbupdate|-nodbupdate]`
`[-disableResetArchiveBitForDedupe]`

-backupasdb

Appends the CA ARCserve Backup database at the end of the backup data.

-backupcatalog

Appends the catalog files at the end of the backup data.

-backupjobqueue

Appends the job scripts at the end of the backup data.

-noestimation

Disables file estimation. By default, before any file is backed up to media, CA ARCserve Backup performs an estimate of how long the job will take. Select this option if you want CA ARCserve Backup to skip this function, saving time at the beginning of the backup.

-createcrc

Calculates and stores the CRC value on backup media. Select this option if you want CA ARCserve Backup to automatically calculate the CRC values and save them to the backup media during the backup job. The CRC values can then be used by the scan operation immediately following the backup job (if the `-scan` global verification option is included), or as part of a separate scan job.

-deletefiles

Deletes the files from the hard disk after the file backup is completed. Select this option if you want to delete source files from the source machine after they have been backed up to media. This option deletes only the files from the specified unprotected folder. It does not delete the empty folder itself.

You can use this option to perform disk grooming. For example, if you set up a backup job with a filter to back up files that haven't been accessed for a certain period of time, you could then include this option to delete those files from the source disk.

Notes:

- On Windows computers, protected system files and files that are excluded from the backup by other filters are not deleted. For a remote backup job or a 64-bit operating system local backup job or a Windows Server 2008 local backup, the Windows Client Agent backs up the files. After the backup, this option deletes only the files from the specified unprotected folder. It does not delete the empty folder itself. Boot files, however, are not protected and can be deleted.
- On NetWare computers, all files that are backed up are deleted, except for those in protected directories, such as SYSTEM, PUBLIC, LOGIN, ETC, MAIL, and the CA ARCserve Backup home directory.
- On Linux/UNIX and Mac computers, all files that are backed up are deleted, except for those in protected directories, such as /bin, /etc, and /lib. To designate additional directories as protected, add them to the groom.cntl file on the client agent machine.

-preserveaccesstime

Preserves file access time (for windows file system only). This option directs CA ARCserve Backup to preserve the last access time of files when a backup is performed.

The Access Time of a file is automatically updated by the operating system whenever a file is accessed (read or write). However, after a full backup is performed, the Access Times of all the backed up files are also updated. Therefore, if you want to track whether or not a file has actually been accessed (and not just backed up), you need to preserve the original access time.

- If this option is not included, the last file access time of any files that are backed up is updated to the new value that is present when the backup is completed. This is the default setting.
- If this option is included, CA ARCserve Backup preserves the last file access time of any files that are backed as the original value that was present before the backup was performed.

-eject

Ejects the media from the drive after the job finishes. This helps prevent any other job from overwriting information on this media. If you select this, it overrides the setting you selected during library configuration.

-noeject

Does not eject the media from the drive after the job finishes. If you select this, it overrides the setting you selected during library configuration.

-partialdbupdate

Records only Job and Session information into the CA ARCserve Backup database. Select this option to log only job and session information in the database. This is the recommended method.

Note: On Windows, if you select this, no detail information will be merged into the database. If you enabled the catalog database and select this, catalog files are stored in the CATALOG.DB folder. If you did not enable the catalog database, catalog files are deleted afterwards.

-nodbupdate

Disables database recording. Does not log any information about this job in the database. Select this option if you are backing up the CA ARCserve Backup database or if you have limited disk space.

You must submit a Merge Media operation before you can use any of the database views to restore this data.

-disableResetArchiveBitForDedupe

Disables the resetting of the archive bit for all files specified in the command. If you omit this switch, archive bits are reset by default.

Important! Use this switch with caution. The archive bit marks a particular file as changed. When you perform deduplication jobs with Optimization, only the files marked as "changed" since the last backup are actually deduplicated. After the backup job completes, the Archive Bits on those files should be reset. If the Archive Bit is not reset, files are automatically considered "changed" and Optimization includes them in subsequent backup jobs, even if no changes actually took place.

You should disable archive bit resetting in situations where files to be backed up by custom deduplication with optimization jobs are also backed up by some other backup job, such as a GFS job. Clearing the archive bit after the first job could affect the GFS job.

Pre/Post Options

The `ca_backup` command includes the following global pre/post options:

`ca_backup`

```
[-preexec <command>]
[-exitcode <exit code(>=0)>[-skip_delay|-skip_job] [-skip_post]
[-preexec timeout <minutes(0-32767)>]
[-postexec <command>]
[-skippostfail]
[-skippostincmp]
[-skippostcmp]
[-prepostuser <user name>]
[-prepostpassword <user password>]
```

-preexec <command>

Runs the specified command before the job starts.

The entire path of the command should be included.

Note: To use this option, you must also specify the `-prepostpassword` option. If you do not specify the `-prepostpassword` option, the job will fail.

-exitcode <exit code(>=0)>[-skip_delay|-skip_job] [-skip_post]

Specifies the exit code of the pre-execute command. Used with the `-skip_delay`, `-skip_job`, and `-skip_post` switches.

-skip_delay

Runs the backup job immediately, if the specified exit code is received.

-skip_job

Skips the backup job completely, if the specified exit code is received.

-skip_post

Skips the post-execute command, if the specified exit code is received.

-skippostfail

Specifies to not run the post command if the job fails.

-skippostincmp

Specifies to not run the post command if the job is incomplete.

-skippostcmp

Specifies to not run the post command if the job is complete.

-preexectimeout <minutes(0-32767)>

Specifies the time to wait (in minutes) before the backup job starts, to allow time for the pre-execute command to finish. The range of time to specify is from 0 to 32767 minutes.

Default: 0 minutes

-postexec <command>

Runs the specified command after the job finishes.

The entire path of the command should be included.

Note: To use this option, you must also specify the `-prepostpassword` option. If you do not specify the `-prepostpassword` option, the job will fail.

-prepostuser <username>

Specifies the name of the user who is submitting this backup job.

-prepostpassword <user password>

Specifies the password of the user submitting the backup job.

Log Options

The `ca_backup` command includes the following global log options:

`ca_backup`

`[-logfile <allactivity | summary [consolidate] | disabled | errorsonly>]`

-logfile <allactivity | summary [consolidate] | disabled | errorsonly>

Records activities during the running of the backup job in the Job Log. You must specify one of the subordinate options to control the information being recorded.

allactivity

Logs all activities that occur while the job is running.

summary

Logs only summary information such as source, destination, session number, totals, and errors.

consolidate

Consolidates a child job log to the master job. This option can only be used when the summary option is used.

disabled

Log is disabled and does not record any information about the job.

errorsonly

Logs only errors that occur while the job is running.

Default: Summary without consolidate.

Virus Options

The `ca_backup` command includes the following global virus options:

`ca_backup`

`[-virus <skip|delete|rename|cure> [-virus_scanarchive]]`

-virus

Enables automatic scanning for viruses during the backup operation. You must also include one of the virus scanning subordinate options.

Skip

Does not back up the infected file.

Rename

Renames the infected files with the extension AVB. If a file with the same name and the extension AVB exists, then the extension AV0 is used, followed by AV1, AV2, and so on.

Delete

Deletes the infected file.

Cure

Attempts to cure the infected file.

-virus_scanarchive

Checks each file in compressed archives individually. Selecting this option might affect the performance of the backup but provides increased virus protection.

Media Exporting Options

The `ca_backup` command includes the following global media exporting options:

`ca_backup`

`[-export <all|duplicate>]`

-export

Allows you to export media at the end of a backup job. It allows you to move it out of the library or to an off-site location for safe storage. If the job does verification, the export is performed at the end of the verification process. If you do not include this option, no media exporting will take place at the end of a backup job.

all

CA ARCserve Backup exports all of the tapes for the related backup. If the job spanned to multiple tapes, all of the tapes used in this job will be exported. In case of RAID tape sets, all the tapes in the tape sets for this job will be exported. CA ARCserve Backup retries a few times to check if the mail slot is empty to move the next tape to the mail slot. If there are not enough mail slots to export all the tapes, the tapes that could not be exported will be moved back to the original home slot. If the operator does not remove the tape from the mail slots then CA ARCserve Backup will write this information in the activity log.

duplicate

This option is for RAID 1 support. CA ARCserve Backup exports the duplicate media for the related backup. If the job spanned to multiple media, all the duplicate media used in this job will be exported.

Advanced Options

The `ca_backup` command includes the following advanced global options:

`ca_backup`

`[-skipdirandvol | -traversedirandvol]`

`[-bkmountpt]`

`[-preserve_hardlink]`

`[-dr_partiahodeinfo]`

`[-dr_includefiltered]`

`[-sql_norotation]`

`[-sql_nopartialupdate]`

-skipdirandvol

Specifies to skip the directory junctions and volume mount points. Including this option causes the backup job to not back up the directory or volume being referred to by the directory junction or volume mount point, respectively. Therefore, at the time of restore, you cannot restore a file or directory that is contained in the referred to directory or volume.

Note: This option is only supported on Windows 2000, Windows XP, and Windows 2003 operating systems.

-traversedirandvol

Specifies to traverse the directory junctions and volume mount points. Including this option causes the backup job to traverse the specified directory or volume and take a backup of it. At the time of restore of this session, you can restore files and directories contained in the referred to volume or directory. When this option is not included, the backup job does not back up the volume or the directory being referred to by the volume mount point or the directory junction respectively. Therefore, at the time of restore, you cannot restore a file or directory contained in the referred to volume or directory.

-bkmountpt

Backup mount points as part of the volume that they are mounted on. Including this option causes the volumes referred to by the Volume Mount Points to be backed up as part of the same session as the Volume Mount Points. When this option is not included, the volumes referred to by the Volume Mount Points are backed up as separate sessions.

Note: This option is only supported on Windows 2000, Windows XP, and Windows 2003 operating systems.

-preserve_hardlink

Causes the hard link to be backed up, but not the file being referred to. When this option is not included, the file referred to by the hard link is backed up.

Note: This option is only supported on Windows 2000, Windows XP, and Windows 2003 operating systems.

-dr_partialnodeinfo

Generates disaster recovery information for partially selected nodes. Disaster recovery information is normally generated when performing a full machine backup. However, there are special cases where you may need to keep the disaster recovery information updated but cannot perform full machine backups too often (like in a SAN shared disk environment). By including this option, you can generate or update a machine's disaster recovery information without having to back up everything on the machine.

-dr_includefiltered

Includes filtered sessions when generating restore session information. When generating disaster recovery information, the CA ARCserve Backup server keeps track of only the latest non-filtered backup sessions pertaining to the machine. By default, if you back up a machine using filters, the filtered backup sessions will not be used by disaster recovery when recovering the system. By including this option, you can alter the default behavior and have disaster recovery use the filtered backup sessions when recovering the system.

This option is not included by default. When you include this option, it works at the job level. If the job contains multiple machine backups, this option will apply to all machines.

Important! Including this option is very risky, especially for system volumes. Missing system files may lead to incomplete recovery.

-sql_norotation

Does not apply differential or incremental backup methods to Microsoft SQL Server databases. Include this option if you do not want CA ARCserve Backup to apply differential or incremental backup methods to Microsoft SQL Server database backups.

-sql_nopartialupdate

Does not automatically upgrade a Microsoft SQL Server partial backup to a full database backup if a full backup of the database is not found.

VSS Options

The `ca_backup` command includes the following Volume Shadow Copy Service (VSS) options to allow you to specify how open files will be handled during file system backups.

`ca_backup`

```
[-vss_usevss [revertoff]]  
[-vss_exclinclsoff]  
[-vss_exclexclosoff]  
[-vss_onfail]
```

-vss_usevss

Directs CA ARCserve Backup to use VSS to handle the backup of open files.

If this switch is not included, VSS support will not be used and the CA ARCserve Backup Agent for Open Files (if available) will be used to handle open files. If the CA ARCserve Backup Agent for Open Files is not available and the `-vss` switch is not included, a traditional backup is performed. However, the backup will be incomplete if there are any open files that cannot be backed up.

revertoff

Directs CA ARCserve Backup to execute a traditional backup if an attempt to create a VSS backup fails. If the CA ARCserve Backup Agent for Open Files is available, it will be used to handle open files if this switch is included and the VSS backup fails.

If this switch is not included and the VSS backup fails, the backup job will also fail.

The suffix "off" indicates that this option is on by default, but if the user includes it, the option will then be set to off.

-vss_exclinclsoff

Specifies that files included by a writer will be excluded from file system backups. This prevents files that belong to a Component from being backed up by a traditional file system backup.

Including this switch provides the following advantages:

- Avoids backing up files that have already been backed up by VSS.
- By excluding files from traditional backups, fewer files are processed, and traditional backups take less time to complete.
- Helps achieve successful backups by eliminating certain problems associated with files that must be processed as a group.

The suffix "off" indicates that this option is on by default, but if the user includes it, the option will then be set to off.

-vss_exclsexclsoff

Specifies that files excluded by a writer will be excluded from file system backups. This prevents files that have been excluded from being backed up by a Component from being backed up by a traditional file system backup.

The suffix "off" indicates that this option is on by default, but if the user includes it, the option will then be set to off.

-vss_onfail

Specifies that if a component file fails to backup the writer, the backup will terminate. This cancels the backup of a Writer if the backup of any of the Components fail. The backup of a Component will fail if one or more of its files cannot be successfully backed up.

Including this switch ensures that any backup is consistent and that all of the files associated with a Writer are backed up before the backup is considered successful, regardless of how many Components are associated with the Writer.

Global Filter Options

Using filters you can include or exclude specific files and directories from your backup jobs. Use the filters to help focus on the files you want. Filters can be applied globally (to the entire job), at the node level (to a specific node), or at the volume level (to a specific filesystem). The position of the -filter switch in the ca_backup command determines the filter level applied.

Important! Incorrect use of filters can result in data being omitted during the backup. Use care when specifying or applying filters!

The ca_backup command includes the following filter options:

ca_backup [-filter

<include|exclude> <file|dir> <pattern>]]

<include|exclude> [<attribute> [hidden] [readonly] [system] [archive]]]

<include|exclude> [<date> <modify|create|access> <on|before|on|after <mm/dd/yy|yy>>]]

<include|exclude> [<date> <modify|create|access> <between <mm/dd/yy|yy> <mm/dd/yy|yy>>]]

<include|exclude> [<date> <modify|create|access> <within <count> days|months|years>>]]

<include|exclude> [<size> <equalto|greaterthan|lessthan> <size val> <Bytes|KBytes|MBytes|GBytes>]]

<include|exclude> [<size between <<low size val> <Bytes|KBytes|MBytes|GBytes>> <<high size val> <Bytes|KBytes|MBytes|GBytes>>]]

include

Results will contain only those files that satisfy the filter specifications. For example, if you select to back up your entire local hard drive, and then set up a filter to include files in the \SYSTEM directory. The result would be that CA ARCserve Backup would only back up files from your \SYSTEM directory. No other files would be backed up.

exclude

Exclusions always take precedence over inclusions. For example, if you add a filter to include files that have an .exe extension, and add another filter to exclude your \SYSTEM directory, then all the .exe files in the \SYSTEM directory would be excluded.

file|dir <pattern>

Specifies to include or exclude files or directories based on the specified pattern.

Note: If you select the include directory pattern filter and do not specify an absolute path, empty directories for all the directories that do not match the user provided criteria will be backed up. To avoid creating these empty directories during restore, disable the global restore option Create Empty Directories when creating your restore job.

attribute [hidden] [readonly] [system] [archive]

Specify to include or exclude files with the specified file attribute.

date <modify|create|access> <onorbefore |-onorafter <mm/dd/yy[yy]>>

Specifies to include or exclude files that were modified, changed, or accessed on or before the specified date, or on or after the specified date.

date <modify|create|access> <between <mm/dd/yy[yy]> <mm/dd/yy[yy]>>

Specifies to include or exclude files that were modified, changed, or accessed between the specified dates.

date <modify|create|access> <within <count> days|months|years>

Specifies to include or exclude files that were last modified, changed, or accessed within the specified number of days, months, or years.

size <equalto|greaterthan|lessthan> <size val> <Bytes|KBytes|MBytes|GBytes>

Specifies to include or exclude files whose size is equal, greater or less than the specified size.

**size between <<low size val> <Bytes|KBytes|MBytes|GBytes>>
<<high size val> <Bytes|KBytes|MBytes|GBytes>>**

Specify to include or exclude files whose size is within the specified size range.

Note: For the Global Filter options, the following conditions exist:

- For UNIX servers, CA ARCserve Backup will automatically interpret the "-create" command as specifying the File Change date.
- Modified Time is different than Change Time. Modified Time means the content of a file has changed. Change Time means some properties or attributes of the file has changed (permission changes, owner information, etc), but not the content.
- Not all file systems record change or access dates, therefore some of these Global filters may not be available for your job.
- CA ARCserve Backup accepts the wildcard characters asterisk '*' and question mark '?' for include and exclude filtering. The asterisk wildcard specifies to match any number of characters. The question mark wildcard specifies to match any one character.

For example:

- To include/exclude all files with extension 'tmp':
-filter include/exclude file *.tmp
- To include/exclude all directories matching the pattern a01???:
-filter include/exclude dir a01???

Source Arguments

The `ca_backup` source arguments allow you to specify the path or location that you want to back up.

The `ca_backup` command provides the following source arguments:

```
ca_backup -source [<hostname>{<hostIP>}] [node options] -filesystem <filesystem> [<relative directory>] [-inputfile
[set the File Name variable]] [volume options]
```

```
ca_backup -source [<hostname>{<hostIP>}] [node options] [-fsfile [set the File Name variable]]
```

```
host type: unix|ht|nwagent|tagent|w95agent|mac
```

Windows Usage:

```
ca_backup -source [<hostname>{<hostIP>}{<hosttype>} [node options] -filesystem <filesystem> | <folder
path> [-filelist <file list>] [volume options]
```

UNIX Usage:

```
ca_backup -source [<hostname>{<hostIP>}{<hosttype>} [node options] -filesystem <filesystem> [<relative
directory>] [-filelist <file list>] [volume options]
```

RawDevice specific backup (UNIX only):

```
ca_backup -source [<hostname>{<hostIP>}] [node options] -raw <raw device> [volume options]
```

NetWare specific NDS backup:

```
ca_backup -NDS <NDS tree name> -username <NDS login name> -password <NDS password>
-NDSserver <server name> -NDSaddress <server address> [-novellservice [<relative directory>]]
```

VSS specific backup:

```
ca_backup -source [-vss <vss writer path>] [-vsswriter [-transport [retainshadow copy]] [-excludeincludedinthis]
[-erroroncefail]] [-method <full|incr|diff|copy|log>]
```

Database backup (UNIX only):

```
ca_backup -source [<hostname>{<hostIP>}] [node options] -database <dbase type> <dbase name|SQL
server> [<tablespaces>] [dbase options]
```

-source [*<hostname>* [*<hostIP>*]]

Specifies the source machines to back up. The default machine, if *hostname* is not provided, is the local machine. This switch can appear multiple times in a *ca_backup* command, and must appear for each source to be backed up. By default, if used without additional switches, the entire source machine is backed up.

Note: -source accepts only the host name for the machine, and the host name should be resolvable in your network.

-filesystem *<filesystem name>* *<relative directory>* *<folder path>*

Specifies the file system or folder to back up and, optionally, the directory or directories under the file system. This switch can appear multiple times in a *ca_backup* command and must appear for each filesystem to be backed up.

Note: On Windows NT, if you are backing up a folder or a file with a space in the name, you must enclose the name in quotes.

-filelist *<file list>*

Specifies the individual files to back up. Use with the -filesystem switch.

-inputfile [*set the File Name variable*]

Use to pass on the file name containing the list of files to be backed up. You can use this switch as an alternative to -filelist *<file list>*. You can also use this with the -source and -filesystem options.

-fsfile [*set the File Name variable*]

Specifies the input from an external text file that lists the file systems for back up. You can specify the level of granularity of the backup by defining the following information:

- The file systems you want to back up
- The relative directories of the file systems you want to back up
- The -filelist option and file names to specify the files to use within the targeted file system
- The -inputfile option and file name to add files from another external file.

To do this, use the following syntax:

```
[filesystemname] [relative_dir][-filelist <file1><file2>][-inputfile [set the File Name variable]]
```

-raw *<raw device>*

Specifies a raw device to back up.

Note: This argument applies to UNIX and Linux platforms only.

-NDS *<NDS tree name>*

Specifies the NetWare NDS tree name.

-NDSserver <server name>

Specifies the NetWare NDS server name.

-NDSaddress <server address>

Specifies the NetWare NDS server address.

-username <user name>

Specifies the user name of the source machine to back up. This is the user used to log into the source machine.

-password <password>

Specifies the password for the user to be used to log into the source machine.

The `ca_backup` command line utility also supports the following options to assist in further identifying and locating the backup source:

- node options
- volume options
- database options

Node Options

When you select a host (node) object to be backed up, you can set node-level options and filters to be applied and display node-level information.

The `ca_backup` command includes the following node options:

`ca_backup`

```
[-username <username>]
[-password <password>]
[-traversesymlink]
[-traversenfs]
[-resetaccesstime <on|off>]
[-noestimation]
[-acrossfs]
[-filter <node filters>]
```

(for UNIX only)

```
[-priority <priority level>]
[-tapeformat <tar|ppio>]
```

-username <user name>

Specifies the user name of the source machine to back up. This is the user used to log into the source machine.

Note: Regardless of the backup source machine, you must specify a -username if you use ca_backup.

-password <password>

Specifies the password for the user to be used to log into the source machine.

Note: Regardless of the backup source, you must specify a -password if you use ca_backup.

-traversesymlink

Traverses the symbolic links during the backup, and back up the actual file the link points to, not simply the link itself. (UNIX machines only).

-traversenfs

Traverses the mounted NFS file systems during the backup. By default, mounted file systems are skipped during the backup. (UNIX machines only).

-resetaccesstime <on|off>

Specifies whether to reset the file access time, changed when CA ARCserve Backup accesses a file to perform a backup. (UNIX machines only).

-noestimation

Disables file estimation prior to backup.

-acrossfs

Traverses across the file system during backup. (UNIX machines only).

-filter <node filters>

Applies filters at the node level (to a specific node). The position of the -filter switch in the ca_backup command determines the filter level applied.

-priority <priority level>

Assigns a backup priority to the Nodes/Volumes in a job. Priority level ranges from 1 (highest priority) to 255 (lowest priority).

Note: This option applies to UNIX and Linux only.

-tapeformat <tar|cpio>

Specifies the tape format of the backup job. Both tar and cpio tape formats are supported, as well as the tape format of CA ARCserve Backup.

Note: This option applies to UNIX and Linux only.

Volume Options

When you select a volume object to be backed up, you can set volume level options and filters to be applied and display volume-related information.

The `ca_backup` command includes the following volume options:

`ca_backup`

```
[-volscan | -volcompare]
[-volgroomdisable]
[-volsessionpw <session password>]
[-volencryption <encryption key>]
[-volcompression]
[-filter <volume filters>]
```

```
(for UNIX only)
[-priority <priority level>]
```

-volscan

Verifies the integrity of the file-system (volume) backup. Scans the backup media and checks the header of each file. If the header is readable, the data is assumed to be reliable.

-volcompare

Verifies the integrity of the file-system (volume) backup. Reads blocks of data from the backup media and compares the data byte for byte against the source files on the source machine.

-volgroomdisable

Disables the volume groom option.

Note: This option applies to NetWare only.

-volsessionpw <session password>

Applies a session password to the session on tape containing the filesystem (volume) backed up.

To restore a session that was backed up using this option, you must use the `ca_restore -tapesessionpw` option to execute the restore job.

-volencryption <encryption key>

Encrypts files before the backup. To restore the encrypted files in this session, the password must be provided.

-volcompression

Compresses files before the backup, for this file system (volume) only.

-filter <volume filters>

Applies filters at the volume level (to a specific filesystem). The position of the -filter switch in the ca_backup command determines the filter level applied.

-priority <priority level>

Assigns a backup priority to the Nodes/Volumes in a job. Priority level ranges from 1 (highest priority) to 255 (lowest priority).

Note: This option applies to UNIX and Linux only.

Database Options

When you select a database object to be backed up, you can set certain database-specific options to be applied and display database-related information.

Note: For all database agents, CA ARCserve Backup does not support backing up multiple database/application instances from a single command. You must use multiple commands to back up each instance.

The ca_backup command includes the following database options:

ca_backup

```
[-dbusername <database username>]
[-dbpasswd <database passwd>]
-database <database type>[database name]
```

-dbusername <database username>

Specifies the database user name to use to log into the database to be backed up.

-dbpasswd <database password>

Specifies the password for the database user to use to log into the database to be backed up.

`-database <database type> [database name]`

Specifies the database type and name to be backed up.

Supported, valid database types are:

- SQL Server (SQL)
- Exchange DOC Level (EXCHANGEDOC)
- Exchange DB Level (EXCHANGEDB)
- Sybase (SYBASE)
- Informix (INFORMIX)
- Oracle (ORACLE)
- Oracle RMAN (ORACLERMAN)
- Lotus (LOTUS)

Examples:

```
-database SQL
-database EXCHANGEDOC
-database EXCHANGEDB
-database SYBASE
-database INFORMIX
-database ORACLE
-database ORACLERMAN
-database LOTUS
```

Oracle Database Options

The `ca_backup` command includes the following Oracle database options:

```
[-oracle_sid <Oracle SID>]
[-oracle_offline] (for UNIX Oracle agent only)
[-oracle_purgelog] (for UNIX Oracle agent only)
[-oracle_timefinder] (for UNIX Oracle agent only)
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

Note: When using the CA ARCserve Backup CLI (command line interface) to back up or restore an Oracle object with a DBCS (double-byte character set) or a MBCS (multi-byte character set) in the name, you must ensure the CA ARCserve Backup server and the agent box have the same language setting.

-oracle_sid <Oracle SID>

Specifies the Oracle SID (system identifier) of the Oracle database to back up.

-oracle_offline

Specifies to back up the Oracle database in off-line mode (only supports full database backups).

-oracle_purgeolog

Specifies to purge the log after it has been backed up.

-oracle_timefinder

Specifies that you want to use the Symmetrix Timefinder technology option for database backups. This option creates a temporary mirror image of the database, which the agent then backs up.

Examples:

The following are examples of syntax for the `ca_backup` ORACLE database command:

- Use the following command to back up a single tablespace `tbs1`:

```
ca_backup -source [<hostname>[<hostIP>][<hosttype>]] -database ORACLE <instance name> "tbs1"  
[dbase options]
```

- Use the following command to back up multiple tablespaces `tbs1`, `tbs2`, and `tbs3`:

```
ca_backup -source [<hostname>[<hostIP>][<hosttype>]] -database ORACLE <instance name> "tbs1" "tbs2"  
"tbs3" [dbase options]
```

- Use the following command to back up a single file of a tablespace:

```
ca_backup -source [<hostname> [<hostIP>][<hosttype>]]unix -database ORACLE <instance name> -table  
SYS AUX "u01|app|oracle|product|10.1.0|db_1|oracle|dborcl|sysaux01.dbf" -dbusername system  
-dbpassword manager -username root -password caword
```

- Use the following command to back up a control file:

```
ca_backup -source [<hostname>[<hostIP>][<hosttype>]] -database ORACLE <instance name> "CONTROL  
FILE" [dbase options]
```

- Use the following command to back up an archive log:

```
ca_backup -source [<hostname>[<hostIP>][<hosttype>]] -database ORACLE <instance name> "ARCHIVE  
LOG" [dbase options]
```

- Use the following command to back up a control file and an archive log:

```
ca_backup -source [<hostname>[<hostIP>][<hosttype>]] -database ORACLE <instance name> "CONTROL  
FILE" "ARCHIVE LOG" -dbusername system -dbpassword system -username root -password caword
```

- Use the following command to back up full database. Assume the database has 5 tablespaces (tbs1, tbs2, tbs3, tbs4, and tbs5) to back up the full database and you want to back up all tablespaces, the archive log, and the control file:

```
ca_backup -source [<hostname>[<hostIP>][<hosttype>]] -database ORACLE <instance name> "tbs1" "tbs2"
"tbs3" "tbs4" "tbs5" "CONTROL FILE" "ARCHIVE LOG" [dbase options]
```

Oracle RMAN Database Options

The `ca_backup` command includes the following Oracle RMAN database options:

```
-use_rmancat
[-rman_catuser <rman_catuser>]
[-rman_catpassword <rman_catpassword>]
-bkincremental
[-rman_incrementallevel <bkincremental> [-cumulative]
[-bkrecoveryarea]
[-oracle_offline]
[-oracle_purgeolog]
[-rman_numberofchannels <rman_numberofchannels>]
[-rman_archlogsel
al_all | al_pattern -rman_alpattern <rman_alpattern> |
al_time [-rman_alfrontime <rman_alfrontime>] [rman_aluntime <rman_aluntime>] |
al_scn [-rman_alfromscn <rman_alfromscn>] [-rman_aluntilscn <rman_aluntilscn>] |
al_logseq [-rman_alfromlogseq <rman_alfromlogseq>] [rman_aluntillogseq <rman_aluntillogseq>]
[-rman_althread <rman_althread>]]
[-rman_bakpieceprefix <rman_bakpieceprefix>]
[-rman_bakpiecesuffix <rman_bakpiecesuffix>]
[-rman_bakpiecesize <rman_bakpiecesize>]
[-rman_baksetsize <rman_baksetsize>]
[-rman_blocksize <rman_blocksize>]
[-rman_readrate <rman_readrate>]
[-rman_maxopenfile <rman_maxopenfile>]
[-rman_numcopies <rman_numcopies>]
[-rman_numfilesperbakset <rman_numfilesperbakset>]
[-rman_baktag <rman_baktag>]
[-rman_script <rman_script>]
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

Note: When using the CA ARCserve Backup CLI (command line interface) to back up or restore an Oracle object with a DBCS (double-byte character set) or a MBCS (multi-byte character set) in the name, you must ensure the CA ARCserve Backup server and the agent box have the same language setting.

-use_rmancat

Use a catalog (recommended). Indicates if an RMAN catalog is to be used for the operation or not. It is always recommended to use one because RMAN will use the database control file if no catalog is to be used. The loss of this control file will prevent RMAN from restoring the database.

Default: Checked

-rman_catuser <rman_catuser>

Name of the Oracle user who owns the RMAN catalog.

-rman_catpassword <rman_catpassword>

Password for the user that owns the RMAN catalog.

-bkincremental

This is the alternative value of the Full Backup option. It tells RMAN to send only the blocks of data that have not been backed up since the last backup made, depending on the Incremental Level and Cumulative options described below. It is represented by a radio button in the Backup Manager and is not selected by default. Of course, Incremental Backup cannot be selected with Full Backup. It cannot be used if the Oracle object to be backed up is the control file or the archived logs.

-rman_incrementallevel <bkincremental>

Use this option to specify the level of incremental backup to be performed. RMAN will only back up the data blocks that have changed since the last incremental backup of the specified level or less. The valid values for this field vary between 0 and 4, for Oracle 8, 8i and 9i. With Oracle 10g, the levels are limited to 0 and 1 only. The user can enter data in this field only if the Incremental Backup option was selected.

Default: 0 (full backup)

-cumulative

This option indicates that RMAN will send data blocks that have been used since the last incremental backup made at level n-1 or lower. This is represented by a check box in the Backup Manager.

Default: Unchecked

-bkrecoveryarea

This switch is used to include the Oracle Recovery Area in the list of objects to be backed up. Applies only to Oracle 10g or later.

Default: Unchecked

-oracle_offline

Oracle database backup specific. Back up the Oracle database in off-line mode (no tablespace backup).

-oracle_purge_log

Oracle database backup specific. Purge the log after it has been backed up.

-rman_numberofchannels <rman_numberofchannels>

Use this option to specify how many channels to be allocated by RMAN to perform the backup operation. RMAN will submit jobs in parallel, one for each channel.

Default: 1 channel

-rman_archlogsel

The "Archived Logs Selection" section of this panel allows the user to select which archived logs will be backed up, assuming that the "archived logs" object has been included in the Source panel of the Backup Manager GUI. The selection is represented by radio button options. All indicates that all archived logs will be backed up.

Default: All

-rman_alpattern <rman_alpattern>

String pattern used to select the archived logs based on their name.

-rman_alfromtime <rman_alfromtime>

Use this option to indicate that the archived logs to be backed up will be selected based on the time they were created. This field determines the lower time boundary for the archived logs selection. Only the archived logs created after this time will be backed up.

-rman_aluntiltime <rman_aluntiltime>

Use this option to indicate that the archived logs to be backed up will be selected based on the time they were created. This field determines the upper time boundary for the archived logs selection. Only the archived logs created before this time will be backed up.

-rman_alfromscn <rman_alfromscn>

Use this option to indicate that the range of the archived logs to be backed up is not determined by the time, rather by the SCN (System Change Number). This field indicates the lowest SCN boundary for the archived logs selection. It can be left empty, assuming that the Until SCN field is not.

-rman_aluntilscn <rman_aluntilscn>

Use this option to indicate that the range of the archived logs to be backed up is not determined by the time, rather by the SCN (System Change Number). This field is used to determine the upper SCN boundary to the archived logs selection. It is optional, as long as the user has entered a value for the From SCN field.

-rman_alfromlogseq <rman_alfromlogseq>

Use this option to specify that archived logs selection is to be based on the archived log sequence number. This field corresponds to the lowest log sequence number used to determine which archived logs will be backed up. This field can be left empty only if a value is provided for the Until Log Sequence option (-rman_aluntillogseq).

-rman_aluntillogseq <rman_aluntillogseq>

Use this option to indicate that the archived logs selection is to be based on the archived log sequence number. This field is used to enter the upper archived log sequence number boundary for the archived logs selection. Providing a value for this field is optional, as long as the user enters a value in the From Log Sequence field.

-rman_althread <rman_althread>

Use this option to specify the thread number used to identify the Oracle server that generated the archived logs. This parameter is only used with the Time Based, SCN Based or Log Sequence Based options described below. It will be ignored if the All or Pattern Based option is used.

Default: 1

Note: This value is only useful for OPS (Oracle Parallel Server, for Oracle 8 and 8i) or RAC (Real Application Clusters, for Oracle 9i and 10g), otherwise the thread number is always one.

-rman_bakpieceprefix <rman_bakpieceprefix>

Left part (or prefix) of the Backup Piece Format entry.

-rman_bakpiecesuffix <rman_bakpiecesuffix>

Right part (or suffix) of the Backup Piece Format entry.

-rman_bakpiecesize <rman_bakpiecesize>

Use this option to limit the size of a backup piece generated by RMAN. When this option is set, if the data blocks to be backed up do not fit into a single backup piece, then RMAN will generate as many backup pieces as required to contain all the data. By default, the field should be empty. This means that RMAN will typically put the data from one backup command (for one channel) into a single backup piece.

Default: Empty

-rman_baksetsize <rman_baksetsize>

Use this option to limit how much data should go into a backup set. This command determines the maximum size in KBytes that a backup set can have.

Default: Empty

-rman_blocksize <rman_blocksize>

Use this option to specify a value that determines the size of the data blocks that RMAN will send to the Oracle agent when performing a backup. This field should be left empty by default. If the user enters a value for it, then the same block size must also be entered by the user when he wants to restore from this backup. Otherwise, RMAN will produce an error message indicating that there is a mismatch between the backup block size and the restore one. In that case, the value used during the backup will be put in the error message. If no value is provided, then RMAN uses 64 KB for Oracle 8 or 8i and 256 KB for Oracle 9i.

This parameter does not exist anymore with Oracle 10g.

Default: Empty

-rman_readrate <rman_readrate>

This is a performance tuning option. You can use this option to slow down the rate at which RMAN reads data from the hard disk to avoid contention. By default, it is empty, however if you want to set this option, the value represents the maximum number of buffers per second that RMAN can use to read data from the disk. The size of a buffer corresponds to the value `DB_BLOCKSIZE * DB_FILE_DIRECT_IO_COUNT` which are parameters defined in the Oracle database configuration.

Default: Empty

-rman_maxopenfile <rman_maxopenfile>

Use this option to limit the total number of files that RMAN will open at the same time. This command lets you decrease the potential for a "too many open files" error. Leaving the field empty will make RMAN use the default value.

Default: 8 files (for Oracle 10g)

Default: 32 files (for Oracle 8, 8i and 9i)

-rman_numcopies <rman_numcopies>

Use this option to specify how many copies of the backup pieces will be generated by RMAN. The valid values for this parameter are 1 to 4.

Oracle 8.0 does not support this parameter.

Default: 1 copy

-rman_numfilesperbakset <rman_numfilesperbakset>

Use this option to limit the number of files (backup pieces) that RMAN should put per backup set. If not specified, then RMAN will use the lesser values of these two: 64 or the number of input files divided by the number of channels.

Default: Empty

-rman_baktag <rman_baktag>

Use this option to enter a backup identifier called a 'tag'. This tag can then be used to identify which version of the Oracle objects should be used by RMAN during a restore operation.

-rman_script <rman_script>

Use this option to enter the path of an RMAN script. Providing a value for this field will cause the Oracle agent to ignore all other options that might have been entered by the user in the GUI. The script will be passed as is to RMAN and the Oracle agent will perform the backup operation normally.

Exchange DOC Level Database Options

The `ca_backup` command includes the following Exchange DOC Level database options:

`ca_backup`

`[-exsis_glosch | [-exsis_full | -exsis_diff | -exsis_incr | -exsis_timebased [onorafter|onorbefore date <mm/dd/yy> | days <daysprior>] [expurge]]]`

`[-exsisfilter mailbox <Pattern List>]`

`[-exsisfilter folder <Pattern List> [-defaultfolder <{Calendar|[Contacts]|[DeletedItems]|[Drafts]|[Inbox]|[Journal]|[Notes]|[OutBox]|[SentItems]|[Tasks]>}]`

`[-exsisfilter attachment <Pattern List> [-attsizeexclude <size>]]`

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

-exsis_glosch

Specifies to use the globally scheduled backup method.

-exsis_full

Specifies to perform a full backup (back up the entire mail box).

-exsis_diff

Specifies to perform an incremental backup (back up only the changes from the last backup).

-exsis_incr

Specifies to perform a differential backup (back up only the changes from the last full backup).

-exsis_timebased

Specifies to perform a time-based backup.

You can select subordinate options to schedule the time-based backup.

[onorafter |onorbefore date <mm/dd/yyyy>]

Specifies to perform the time-based backup based on a specified date. This option backs up all documents newer than or older than a specified point in time.

[days <daysprior>]

Specifies to perform the time-based backup based on a specified number of days prior to when the job runs. This option backs up all documents based on the number of days prior to when the job runs and is a moving window that stays relative to the time at which the job runs.

expurge

Specifies to purge documents after the backup. Automatically deletes documents after they are backed up. This is useful for pruning an Exchange Server. For example, you can use this option to back up and delete documents older than three years, thus reducing the size of your Exchange Server.

Important! This option should be used with caution because it could delete all documents that were backed up.

-exsisfilter mailbox <Pattern List>

Specifies that the filter applied is based on the name of the mailbox that you want to exclude or the criteria (pattern list) that you want the agent to use to exclude certain mailboxes.

-exsisfilter folder <Pattern List>

Specifies that the filter applied is based on the name of the folder that you want to exclude or the criteria (pattern list) that you want the agent to use to exclude certain folders.

-defaultfolder

Specifies to exclude the default folder from the applied filter. If you want to exclude the default folder, you must specify at least one folder type that you want to exclude, but may specify more than one.

The default folder options include:

- Calendar
- Contacts
- DeletedItems
- Drafts
- Inbox
- Journal
- Notes
- OutBox
- SentItems
- Tasks

-exsisfilter attachment <Pattern List>

Specifies that the filter applied is based on the name of the attachment that you want to exclude or the criteria (pattern list) that you want the agent to use to exclude certain attachments.

-attsizeexclude <size>

Specifies to exclude attachments with a size larger than the specified size.

Exchange DB Level Database Options

The `ca_backup` command includes the following Exchange DB Level database options:

```
ca_backup [-exdb_glosch [-exdb_full | -exdb_copy | -exdb_incr | -exdb_diff]]
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

-exdb_glosch

Specifies to use the globally scheduled backup method.

-exdb_full

Specifies to perform a full backup (back up the entire mail box).

-exdb_copy

Specifies to perform a full backup, except do not purge the log files.

-exdb_incr

Specifies to perform a differential backup (back up only the changes from the last full backup).

-exdb_diff

Specifies to perform an incremental backup (back up only the changes from the last backup).

SQL Server Database Options

The `ca_backup` command includes the following SQL Server specific options:

```
ca_backup -source [-hostname<]>
            [node options]
            <-database SQL <instance name>>
            [[-<dbase name>] [dbase options]]
            [-sql_np]
            [dbaccess options]
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

-sql_np

Specifies "Named Pipes" as the remote protocol. Named pipes allow two unrelated processes to communicate with each other. Named Pipes are the same named pipes mechanism used by the operating system and other programs as a means of inter-process communication and exchanging information within a single machine or across a network.

dbase options

Provides the specific database options available for the type of SQL Server agent detected.

dbaccess options

Provides the specific database access options available for the type of SQL Server agent detected.

SQLServer Agent Options

The `ca_backup` command includes the following SQLServer Agent options:

```
ca_backup
    [-sql_full | -sql_diff | -sql_log <trunc|no_trunc|no_recovery>]
    [-sql_log_afterdata <trunc|no_trunc|no_recovery>][-sql_partial]
    [-sql_filegroup <filegroupname>][-sql_file <filename1>]...[-sql_file<filename>]..
    [-sql_dbcc [sql_before [continue]] [sql_after] [physical_only] [no_indexes]]
    [-sql_checksum]
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

-sql_full

Specifies to perform a Full SQLServer backup.

-sql_diff

Specifies to perform a Differential SQLServer backup.

-sql_log

Specifies to perform a Transaction Log backup.

trunc

Specifies to truncate the Transaction Logs when you back them up. This option removes all inactive entries from the Transaction Log. If the Transaction Log is not truncated, it may eventually grow very large.

no_trunc

Specifies not to truncate the Transaction Logs when you back them up. This option does not remove the inactive entries from the Transaction Log.

no_recovery

Specifies to back up log tail and leave the database in a loading state. The log tail is the oldest end of the log.

-sql_log_afterdata

Specifies to back up the transaction log after the database.

-sql_partial

Specifies to perform a partial backup.

-sql_filegroup <filegroupname>

Specifies the filegroups in the session to be backed up.

-sql_file [set the File Name variable]

Specifies the files in the session to be backed up.

-sql_dbcc

Specifies to perform a database consistency check (DBCC).

sql_before [continue]

Specifies to perform a DBCC before the backup of the database.

You can also specify to continue with the backup even if the DBCC fails.

sql_after

Specifies to perform a DBCC after the backup of the database.

physical_only

Specifies to check only the physical consistency of the database to verify the structural integrity of all the objects in the database.

no_indexes

Specifies to check the database for consistency without checking indexes for user-defined tables.

-sql_checksum

Specifies to include checksums generated by SQL Server in the backup.

Examples:

The following are examples of syntax for the `ca_backup` SQL Server database command:

- Use the following command to perform a full database backup:
`-database SQL <instance name> <dbase name> -sql_full`
- Use the following command to perform a differential database backup:
`-database SQL <instance name> <dbase name> -sql_diff`
- Use the following command to perform a file or file group database backup:
`-database SQL <instance name> <dbase name> -sql_filegroup [-sql_file [set the File Name variable]..]`
- Use the following command to perform a database log backup:
`-database SQL <instance name> <dbase name> -sql_log[trunc|no_trunc|no_recovery]`

Sybase Agent Database Options

The `ca_backup` command includes the following Sybase database options:

```
ca_backup [-sybase_database]-sybase_transactionlog trunc|sybase_transactionlog no_trunc ]
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

-sybase_database

Specifies to back up the Sybase database data.

-sybase_transactionlog trunc

Specifies to truncate the transaction log during backup.

To decrease the size of a transaction log, you can specify to truncate the transaction log when you back it up. When the agent backs up a transaction log without truncating it, the agent backs up the log from the last successfully executed log backup to the current end of the log. The backup includes both the active and inactive portions of the log file. If you specify to truncate the log during backup, the agent removes the inactive portion of the log and truncates the log to the beginning of its active portion, the part that contains the oldest open transaction.

This is the default option.

-sybase_transactionlog no_trunc

Specifies not to truncate the transaction log during backup.

Examples:

The following are examples of syntax for the `ca_backup` SYBASE database command:

- Use the following command to back up database data:
`-database SYBASE <instance> <database> -sybase_database`
- Use the following command to truncate the transaction log during backup:
`-database SYBASE <instance> <database> -sybase_transactionlog trunc`
- Use the following command to not truncate the transaction log during backup:
`-database SYBASE <instance> <database> -sybase_transactionlog no_trunc`

Informix Agent Database Options

The `ca_backup` command includes the following Informix database options:

`ca_backup`

```
[ifmx_level <level(0-2)>]
[ifmx_currentLog | ifmx_salvageLogs]
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

-ifmx_level <level (0-2)>

Specifies the level of the backup to be performed.

- Level 0 - Full backup
- Level 1 - Back up changes made since the last level 0 backup
- Level 2 - Back up changes made since the last level 1 backup

By default, the agent performs a level 0 backup.

-ifmx_currentLog

Specifies to back up the current active logical log, as well as other, full logical logs that were not backed up.

-ifmx_salvageLogs

Specifies to back up all logical logs that reside on the disk.

Examples:

The following are examples of syntax for the `ca_backup` Informix database command:

- Use the following command to back up dbspace:
`-database INFORMIX <instance name> <dbspace name> -ifmx_level <0-2>`
- Use the following command to back up logical logs (including the current log):
`-database INFORMIX <instance name> #LOGFILE# -ifmx_currentLog`
- Use the following command to back up salvage logs:
`-database INFORMIX <instance name> #LOGFILE# -ifmx_salvageLogs`

VSS Agent Database Options

The `ca_backup` command includes the following VSS (Volume Shadow Copy Service) agent database options:

```
ca_backup -vss <vss_path>
    [-vss_writer
    [-transport [retainshadowcopy]]
    [-excludedefincludedinthis]
    [-excludedefexcludedbythis]
    [-erroronceffail]
    [-method <FULL||INCR|DIFF|COPY|LOG>]]
```

-vss <vss_path>

Specifies that the backup options set at the Writer level affect only the selected Writer and overrides any global options set for VSS backups. You must supply the path location for the file system to be backed up.

-vss_writer

Specifies to use Writer options. Directs the VSS backup process to use the options provided by the selected writer and to enable the other Writer backup options.

-transport [retainshadowcopy]

Specifies to use a transportable snap-shot. Creates a transportable VSS backup copy of entire volumes. This shadow copy is a mirror of an entire LUN; however, the data can be restored for specific volumes of the LUN. Transportable shadow copies allow greater flexibility for the backup and restore of your critical applications and files by enabling the shadow copy to be imported onto other servers within the same system. You can then use the transported shadow copy volumes for additional tape backups, or for other uses such as data mining and software development testing.

By default, the shadow copy is deleted after the backup finishes. To retain the shadow copy after the backup, you must also include the "retainshadowcopy" subordinate option.

Note: When this option is included, the only available backup method is Full Backup.

retainshadowcopy

Specifies to retain a shadow copy after backup. Include this option to specify that CA ARCserve Backup should not delete the shadow copy volume after the backup. Because the shadow copy volume is transportable, retaining it after the backup enables the volume to be imported onto another system for other uses.

-excludeincludedinthis

Specifies that files included in this Writer will be excluded from any File System backups. This option prevents files that belong to a Writer component from being backed up by a traditional file system backup. This option offers the following advantages:

- Avoids backing up files that have already been backed up by VSS.
- Ensures that fewer files are processed and that traditional backups take less time to complete by excluding files from traditional backups.
- Helps achieve successful backups by eliminating problems associated with files processed as a group (for example, files associated with a database application). In a traditional backup, there is no mechanism to ensure that the files are processed together.

Note: This option is not available if the Use Transportable snap-shot option is included.

-excludeexcludedbythis

Specifies that files that are specifically excluded by this Writer will be excluded from any File System backups. Include this option to exclude files associated with an application that should never be backed up (the Windows page file, for example) from any file system backups. Each Writer is aware of whether its associated application maintains any such files. This option enables CA ARCserve Backup to use this information when performing traditional backups.

Note: This option is not available if the Use Transportable snap-shot option is included.

-erroroncefail

Specifies that if one or more files of a component of this Writer fail to backup successfully, the entire Writer backup will be terminated. Include this option to cancel the backup of the selected Writer if the backup of any of its components fails. Component backups fail if one or more of the files that are part of the Component cannot be backed up successfully.

Include this option to ensure that all of the files associated with a Writer are backed up before the backup is considered successful, regardless of how many Components are associated with the Writer.

Note: This option is not available if the Use Transportable snap-shot option is included.

-method <FULL|INCR|DIFF|COPY|LOG>

Specifies the backup method to use for the backup of the selected Writer.

FULL

Specifies to perform a Full backup of all the files associated with the selected Writer, regardless of when the data last changed. When the -transport snap-shot option is included, this is the only backup method available.

INCR

Specifies to perform an Incremental backup of only those files that have changed since the last full or incremental backup was performed. After each backup, the backed up files are marked so that they are not backed up during the next incremental backup job unless they have changed. It takes less time to process backup jobs using this method.

DIFF

Specifies to perform a Differential backup of only those files that have changed since the last full backup was performed. Because differential backup jobs do not mark files as having been backed up, the files that were backed up in the last differential job are backed up again. It takes longer to process backup jobs using this method.

COPY

Specifies to back up all the files included by the Writer, but does not mark the files as having been backed up. Select this option to make a full backup of your data without disrupting any existing incremental or differential backups.

LOG

Specifies to back up only the log files associated with the selected Writer.

Lotus Agent Database Options

The `ca_backup` command includes the following Lotus agent database options:

```
ca_backup -source [-hostname <-hostname> [-hostIP <-hostIP>]] [node options]
           -database LOTUS <LotusInstance_HostName> [<Lotus_DBFileName>]
           [-lotusfilter <include|exclude> <file|dir <pattern>>]
           [dbase options]
```

Note: The `ca_backup` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_backup allusage`.

LotusInstance_HostName

Specifies the host name where the Lotus Domino is installed.

Lotus_DBFileName

Specifies the Lotus database file name to be backed up.

-lotusfilter <include|exclude> <file|dir <pattern>>

Specifies the filters to be applied to the backup job. Through the use of these filters, you can include or exclude specific files and directories from your backup jobs.

Destination Arguments

A backup destination is the location where the selected backup files are backed up to. After you have selected the objects you want to back up, you must select the destination and destination options for the backup job.

The `ca_backup` command includes the following destination arguments:

```
ca_backup
           [-group <groupname>]
           [-tape <tape name>]
           [-mediapool <pool name>]
           [-multiplextape [-num of streams (1-32)-] muxChunkSize <size in MB (1-16)>]
           [-multistream [-max streams (1-32)-]
           [-dddpurgedata [-full|diff|incr> <weeks> <days> <hours> <minutes>]]
```

-group <groupname>

Specifies media group to use for the backup job.

-tape <tape name>

Specifies name of media to use for the backup job.

-mediapool <pool name>

Specifies media pool to use for the backup job.

Note: If the target group is deduplication group or if the staging group is deduplication group, you cannot include the `-mediapool` switch.

-multiplextape [<num of steams (1-32)>]

Specifies to submit the backup job with the multiplexing option applied.

Multiplexing is a process in which data from multiple sources is written to the same media simultaneously. When a job that has multiple sources is submitted with the multiplexing option enabled, it is broken into child jobs with one child job for each source. These child jobs write data to the same media simultaneously.

When using multiplexing, you can select the maximum number of streams that can write a tape at the same time. The default number of streams is 4 and the supported range is between 1 and 32.

-muxChunkSize <size in mB (1-16)>

Specifies to set multiplexing chunk size. The chunk size value determines the amount of contiguous data written for one session before data from another session is multiplexed. The higher the value, the faster the restore on some drives, but at the cost of memory size during backup.

The default value is 1 MB and the supported range is between 1 and 16MB.

-multistream [<max streams(1-32)>]

Specifies to submit the backup job with the multistreaming option applied.

Multistreaming allows you to use all the available tape devices on the system by splitting a single backup job into multiple jobs using all the tape devices. As a result, it will increase the overall backup throughput compared with the sequential method.

When using multistreaming, you can select the maximum number of streams that can write to a tape at the same time. The default number of streams is 4 and the supported range is between 1 and 32.

-dddpurgedata [**<full|diff|incr>** **<weeks>** **<days>** **<hours>** **<minutes>**]

Specifies to add deduplication device purge policies for the specified backup method (Full, Differential, or Incremental) to a deduplication device used in a non-staging job.

<weeks> **<days>** **<hours>** **<minutes>**

Specifies how long (in number of weeks, days, hours, and minutes) to wait before purging the device.

Schedule Arguments

The `ca_backup` command provides a means to specify the scheduling methods for your backup job. The method you choose determines when your backups are run, the type of backup to be done on particular days, and the rotation of the backup media. The three schedule methods from which you can choose are Custom schedule, Rotation schedule, and GFS Rotation schedule.

For the following `ca_backup` schedule arguments, "incr" indicates an Incremental Backup and "diff" indicates a Differential Backup.

Note: If a job that is submitted from the `ca_backup` command runs an hour later than the scheduled time, it may be due to change in Daylight Savings Time (DST) start date. To avoid this you need to update your operating system by installing the Microsoft daylight saving time patch. For more information, see the Microsoft Daylight Saving Time Help and Support Center.

The `ca_backup` command includes the following schedule arguments:

Custom Schedule

The `ca_backup` command includes the following filter options:

```
ca_backup [-custom
-repeat <months> <days> <hours> <minutes>]
-excludeday <Sun|Mon|Tue|Wed|Thu|Fri|Sat>*]
-method <incr|diff|full-clear|full-keep>]
-retrymissed_at <hh:mm:ss>|-retrymissed_after <minutes> [-retrymissed_maxtimes <count>]]
-worm]
```

-custom

Specify the schedule type of the backup job as a custom schedule. By default, this is the schedule type used for backup jobs.

-repeat <months> <days> <hours> <minutes>

Use with `-custom`. Specify a repeating interval for a backup job. By default, there is no repeating interval and a job only runs once. Specify a repeating interval so your job runs every X minutes/hours/days/months. The syntax of the command requires a value for each field of months, days, hours, and minutes.

Example: To schedule a repeating job every 1 day and 2 hours enter:
`ca_backup - custom -repeat 0 1 2 0.`

-excludeday <Sun|Mon|Tue|Wed|Thu|Fri|Sat>

Use with `-custom` to exclude specific days from a repeating backup job.

-method <incr|diff|full-clear|full-keep>

Specifies the method for the custom scheduled backup job.

incr

Specifies to perform an incremental backup.

Backs up only those files whose archive bit have been set since the last full or incremental backup was performed. After each backup, archive bits are reset so that they are not backed up during the next incremental backup job.

diff

Specifies to perform a differential backup.

Backs up only those files whose archive bits have been set since the last full backup was performed. Because differential backup jobs do not clear a file's archive bit, the files that were backed up in the last differential job are backed up again. Using this backup method, the backup jobs require more time to process than incremental backup jobs. However, this strategy requires less effort to restore servers and workstations because you will probably require fewer media to restore your machines.

full-clear

Specifies to perform a full backup each time the job is repeated and clear the archive bit.

full-keep

Specifies to perform a full backup each time the job is repeated and keep the archive bit.

-retention <days>

Specifies the media retention period, in days, for the created media pool.

-retrymissed_at <hh:mm:ss>

Backs up or copies any missed targets at the specified time. If the file is still unavailable, CA ARCserve Backup writes information to the Activity Log, and the job is labeled "Incomplete."

-retrymissed_after <minutes>

Backs up or copies any missed targets at the specified number of minutes after all the other source files have been backed up. If the file is still unavailable, CA ARCserve Backup writes information to the Activity Log, and the job is labeled "Incomplete."

-retrymissed_maxtimes <count>

Specifies the number of times you want to try to back up or copy the file.

-worm

Specifies to use the WORM (Write Once Read Many) option to apply media data protection for all custom schedule rules. With this option enabled, CA ARCserve Backup appends the backup sessions to the existing data on the media, because you cannot overwrite or erase WORM media..

Important! CA ARCserve Backup does not support the use of WORM media for multiplexing backup jobs. As a result, if you include the `-multiplextape` switch as a destination option, the `-worm` schedule option will be disabled.

Notes:

- When a backup job spans tapes and the media is WORM media, CA ARCserve Backup needs WORM media to complete the job.
 - If a blank WORM media is not available, and a blank DLT WORM-capable media is available, CA ARCserve Backup automatically converts blank DLT media to DLT WORM media and then completes the backup job.
 - If WORM media is not available for a WORM job to continue, CA ARCserve Backup does not convert non-blank media to WORM media.
- When you are running a backup job that specifies Use WORM Media and there is no WORM media available, CA ARCserve Backup may convert blank WORM-capable media to WORM media for the job.

Rotation Schedule

The `ca_backup` command includes the following Rotation schedule options:

```
ca_backup [-rotation
  -mediapool <mediapool name>]
  -jobunit <full|diff|incr|off> <append|overwrite> <media name>[ds]]
  -saveaset <no. of tapes>]
  -retention <days>]
  -retrymissed_at <hh:mm:ss>|-retrymissed_after <minutes> [-retrymissed_maxtimes <count>]]
  -exception <full|diff|incr|off> <append|overwrite> <mm/dd/yy[yy]>]
  -method <incr|diff|full>]
  -worm]
```

-rotation

Specifies the schedule type of a backup job as a rotation schedule.

-mediapool <mediapool name>

Specifies the media pool to use for the backup job. This switch must be used in conjunction with -rotation or -custom.

- If you use this with -rotation, the media pool name you enter is newly created and associated with this rotation job.
- If you use this with -custom, the media pool name you enter must already exist.

Note: If the target group is deduplication group or if the staging group is deduplication group, you cannot include the -mediapool switch.

-jobunit <full|diff|incr|off> <append|overwrite> <media name> [ds]

Each job unit represents a day in the rotation scheme, from Sunday to Saturday. You can customize each day, although there are certain restrictions, such as not combining differential and incremental backups in the same rotation schedule. The first -jobunit switch is for Sunday, the next for Monday, and so on. The user must account for each day of the week, so seven (7) -jobunit switches are required. By default, any days not represented by a -jobunit switch are set to Off day, and no backup takes place on that day. The user has the option of not specifying the -jobunit switch, to set the rotation schedule to the default 5-day incremental with a full backup on Friday. This is the same schedule seen from the front-end backup manager.

ds

Enables staging in daily backup of a rotation or GFS rotation job.

For a rotation job initiated from the `ca_backup -diskstage` command, every job unit within the rotation job must include "ds" as a parameter to enable the disk staging feature. If you do not include the "ds" parameter, data for the backup sessions will not be sent to the staging device.

For example, to schedule a full disk staging backup job to be executed every Monday for "my_jobs" use the following command:

```
-jobunit off -jobunit full overwrite my_job ds -jobunit off -jobunit off -jobunit off -jobunit off -jobunit off
```

Note: Each job unit represents a day in the rotation scheme, from Sunday to Saturday.

-saveset <number of tapes>

Use with -rotation. Specifies the minimum number of media to keep in the created media pool's save set.

-retention <days>

Specifies the media retention period, in days, for the created media pool.

-retrymissed_at <hh:mm:ss>

Backs up or copies any missed targets at the specified time. If the file is still unavailable, CA ARCserve Backup writes information to the Activity Log, and the job is labeled "Incomplete."

-retrymissed_after <minutes>

Backs up or copies any missed targets at the specified number of minutes after all the other source files have been backed up. If the file is still unavailable, CA ARCserve Backup writes information to the Activity Log, and the job is labeled "Incomplete."

-retrymissed_maxtimes <count>

Specifies the number of times you want to try to back up or copy the file. Available range of count options are from 1 to 12 attempts.

-exception <full|diff|incr|off> <append|overwrite> <mm/dd/yy[yy]>

Specifies an exception condition from the regular rotation schedule. This feature is useful in the case of a holiday or other event, when a different behavior for the backup job is needed on that date.

-method <incr|diff|full>

Specifies the method for the scheduled backup job.

incr

Specifies to perform a scheduled incremental backup.

diff

Specifies to perform a scheduled differential backup.

full

Specifies to perform a scheduled full backup.

-worm

Specifies to use the WORM (Write Once Read Many) option to apply media data protection for all rotation schedule rules. With this option enabled, CA ARCserve Backup appends the backup sessions to the existing data on the media, because you cannot overwrite or erase WORM media.

Important! CA ARCserve Backup does not support the use of WORM media for multiplexing backup jobs. As a result, if you include the `-multiplextape` switch as a destination option, the `-worm` schedule option will be disabled.

Notes:

- When a backup job spans tapes and the media is WORM media, CA ARCserve Backup needs WORM media to complete the job.
 - If a blank WORM media is not available, and a blank DLT WORM-capable media is available, CA ARCserve Backup automatically converts blank DLT media to DLT WORM media and then completes the backup job.
 - If WORM media is not available for a WORM job to continue, CA ARCserve Backup does not convert non-blank media to WORM media.
- When you are running a backup job that specifies Use WORM Media and there is no WORM media available, CA ARCserve Backup may convert blank WORM-capable media to WORM media for the job.

GFS Rotation Schedule

The `ca_backup` command includes the following GFS Rotation schedule options:

```
ca_backup [-gfsrotation
  -mpoolprefix <mediapool prefix>
  -jobunit <full|diff|incr|off>[<ds>]
  -preservedaily <no. of tapes>
  -preserveweekly <no. of tapes>
  -preservemonthly <no. of tapes>
  -retrymissed_at <hh:mm:ss>|-retrymissed_after <minutes> [-retrymissed_maxtimes <count>]
  -exception <full|diff|incr|off> <mm/dd/yy[yy]>
  -method <incr|diff|full>
  -worm [daily] [weekly] [monthly]]
```

-gfsrotation

Specifies the schedule type of the backup job as a GFS (Grandfather, Father, Son) rotation schedule.

-mpoolprefix <mediapool prefix>

Use with -gfsrotation as a prefix for naming three mediapools (Daily, Weekly, and Monthly) to be created and associated with this GFS rotation job.

Example: If the prefix is "GFSJOB1", the 3 pools created are: GFSJOB1_DLY, GFSJOB1_WLY, GFSJOB1_MLY.

Note: If the target group is deduplication group or if the staging group is deduplication group, you cannot include the -mpoolprefix switch.

-jobunit <full|diff|incr|off>

Same as the description for Rotation schedule, except that, for GFS Rotation, the arguments are limited to specifying the type of backup to occur on the selected day.

-preservedaily <no. of tapes>

Use with -gfsrotation to specify the minimum number of media to preserve in the daily media pool save set.

-preserveweekly <no. of tapes>

Use with -gfsrotation to specify the minimum number of media to preserve in the weekly media pool save set.

-preservemonthly <no. of tapes>

Use with -gfsrotation to specify the minimum number of media to preserve in the monthly media pool save set.

-retrymissed_at <hh:mm:ss>

Backs up or copies any missed targets at the specified time. If the file is still unavailable, CA ARCserve Backup writes information to the Activity Log, and the job is labeled "Incomplete."

-retrymissed_after <minutes>

Backs up or copies any missed targets at the specified number of minutes after all the other source files have been backed up. If the file is still unavailable, CA ARCserve Backup writes information to the Activity Log, and the job is labeled "Incomplete."

-retrymissed_maxtimes <count>

Specifies the number of times you want to try to back up or copy the file.

Available range of count options are from 1 to 12 attempts.

-exception <full|diff|incr|off> <mm/dd/yy[yy]>

Same as the description for Rotation schedule, except that, for GFS Rotation, the arguments are limited to specifying the type of backup to occur on the exception date.

-method <incr|diff|full>

Specifies the method for the scheduled GFS rotation backup job.

incr

Specifies to perform a scheduled incremental backup.

diff

Specifies to perform a scheduled differential backup.

full

Specifies to perform a scheduled full backup.

-worm [daily] [weekly] [monthly]

Specifies to use the WORM (Write Once Read Many) option to apply media data protection for all GFS Rotation schedule rules. With this option enabled, CA ARCserve Backup appends the backup sessions to the existing data on the media, because you cannot overwrite or erase WORM media. With this option enabled, you can also specify to apply the WORM media option for daily, weekly, and monthly GFS rotation jobs.

Important! CA ARCserve Backup does not support the use of WORM media for multiplexing backup jobs. As a result, if you include the `-multiplex` switch as a destination option, the `-worm` schedule option will be disabled.

Notes:

- When a backup job spans tapes and the media is WORM media, CA ARCserve Backup needs WORM media to complete the job.
 - If a blank WORM media is not available, and a blank DLT WORM-capable media is available, CA ARCserve Backup automatically converts blank DLT media to DLT WORM media and then completes the backup job.
 - If WORM media is not available for a WORM job to continue, CA ARCserve Backup does not convert non-blank media to WORM media.
- When you are running a backup job that specifies Use WORM Media and there is no WORM media available, CA ARCserve Backup may convert blank WORM-capable media to WORM media for the job.

Run Job Arguments

The `ca_backup` command provides run job arguments to allow you to specify the run job methods for your backup job. The `ca_backup` run job options allow you to submit the job to be run immediately, or to submit the job on Hold, or to schedule the job for a later date and time. The method you choose determines when your backup jobs are run.

Important! To ensure that all jobs start at the scheduled time, you must synchronize the system time of the Member Servers with the system time of the corresponding Primary Server. Use the Windows Time Service to synchronize the time on all ARCserve servers in your domain.

The `ca_backup` command includes the following run job arguments:

```
ca_backup
  [-at <hh:mm>]
  [-on <mm/dd/yy[yy]>]
  [-hold | -runjobnow]
  [-description <descriptionstring>]
```

-at <hh:mm>

Specify the execution time of the backup job.

Note: All scheduled times for CA ARCserve Backup jobs are based upon the time zone where the CA ARCserve Backup server is located. If your agent machine is located in a different time zone than the CA ARCserve Backup server, you will need to calculate the equivalent local time that you want the job to be run.

-on <mm/dd/yy[yy]>

Specify the execution date of the backup job.

-hold

Submit the backup job on hold.

-runjobnow

Submit and execute the backup job immediately.

-description <description string>

Add comments to the job.

Note: You must use double quotes "" to enclose the string and handle blank spaces.

Staging Options

The `ca_backup` staging command allows two methods to backup to a staging area and then migrate (or copy) this data to a final destination (usually a tape).

- The `-diskstage` command utilizes a disk as the staging area and is commonly referred to as Backup to Disk to Tape or B2D2T.
- The `-tapestage` command utilizes a tape library or a virtual tape library as the staging area and is commonly referred to as Backup to Tape to Tape or B2T2T.

Each staging command contains specific options to control the behavior of CA ARCserve Backup during the backup process.

Disk Staging Options

The `ca_backup -diskstage` command allows you to back up data to a disk (staging area), and then based on selected policy options, migrate (copy) the data to the final destination (which could be a tape or disk) or automatically purge the data from the staging area after a specified duration time. When necessary, disk staging also allows you to restore data directly from the staging area.

Note: CA ARCserve Backup will not execute a staging backup job if any of the following error conditions exist:

- If the GROUP NAME is "*", null, or is a valid group name but not a staging group, CA ARCserve Backup will prompt you to provide a valid disk staging GROUP NAME.
- You are not properly licensed and attempt to input more than the maximum two streams.
- Copy policies and `-DONOTCOPY` are specified.
- Multistreaming or Multiplexing is specified for a disk staging job. CA ARCserve Backup supports multiple streaming only for disk staging backup jobs.
- The final destination device group is a disk staging device group.

The `ca_backup -diskstage` command has the following format:

```
ca_backup -diskstage  
  [Miscellaneous Options]  
  [Full Backup Policy]  
  [Incremental/Differential Backup Policy]
```

Disk Staging Miscellaneous Options

The `ca_backup -diskstage` command contains miscellaneous options that are used to define basic policies and parameters for CA ARCserve Backup to use during a disk staging backup job.

The `ca_backup -diskstage` command includes the following miscellaneous options:

```
ca_backup -diskstage <groupname>
    [-maxstreams <Max # Streams(1-32)>]
    [-chunksize <size in MB(1-16)>]
    [-purgefailedsessions]
    [-purgecancelledsessions]
    [-makeupjobtotape]
    [-createDMJMakeupJobOnHold]
    [-leaveCatalogsOnDisk]
    [-consolidate
        [-consolidate_mediaprefix <media prefix>]
        [-consolidate_mediapoolprefix <mediapool prefix>]
        [-consolidate_copymethod <append|overwrite>]]
```

-diskstage <groupname>

Specifies that the backup job will use staging functionality and the name of the disk staging device group.

-maxStreams <Max # Streams(1-32)>

Specifies how many streams CA ARCserve Backup will use as it runs the backup job to the staging device.

The default number of streams is 4 and the supported range is between 1 and 32.

-chunksize <size in MB(1-16)>

During a staging backup, directs CA ARCserve Backup to divide the data into smaller chunks (or sub jobs) to be written to the disk. You must specify the maximum size or amount of data (in MB) contained in each chunk.

The default chunk size is 1MB and the supported range is between 1 and 16MB.

-purgefailedsessions

If a session fails during the backup to disk (staging) process, directs CA ARCserve Backup to mark this session for deletion (purged from disk) immediately. This helps to reclaim disk space as soon as possible.

-purgecancelledsessions

If a session is cancelled during the backup to disk (staging) process, directs CA ARCserve Backup to mark this session for deletion (purged from disk) immediately. This helps to reclaim disk space as soon as possible.

-makeupjobtape

During the backup to disk (staging) process, if an error occurs because the disk is full, directs a makeup job to be created, which when run will directly back up to the final destination media (tape). This increases the chances of a successful backup even though the disk is full.

-createdmjmakeupjobonhold

During a data migration job (DMJ), if a media or a tape drive error occurs, a makeup job would automatically be created on Hold. As a result, you do not have to create a tapecopy job. After fixing the drive or media error, you would then just need to change the status of the makeup job from Hold to Ready to execute the migration process (disk to tape).

-leaveCatalogsOnDisk

Directs CA ARCserve Backup to leave the catalog files on the disk. Use this option to store the catalog files on the staging device in the CATALOG.DB directory.

-migrationpassword <password>

Sets the migration password and directs CA ARCserve Backup to encrypt the data during the migration (copy) process. To enable secure migration, you must specify a password.

Note: If the data was encrypted during the backup process for the job, CA ARCserve Backup will not attempt to encrypt the data again during the migration process for the job.

-consolidate

Enables consolidation of data from different backup jobs to one tape during the migration (copy) process. This allows you to optimize the use of space on the tape as the data is copied.

You can specify subordinate parameter switches to control the data consolidation. For data to be consolidated, you must select at least one of these parameters, but you can specify more than one to further control the data consolidation. However, if you do include multiple parameters, then all of the specified parameters must be satisfied for the jobs to be consolidated. If you do not include any subordinate parameters, the data will not be consolidated at all.

In addition, if you want to consolidate data across multiple jobs to the same tape, the backup jobs should be run on the same machine.

Note: This option cannot be used if the -DO NOT COPY is included.

[-consolidate_mediaprefix <media prefix>]

Consolidates data based on the specified prefix of the media that you want to use for migration. This allows you to specify a group of media (based on prefix) that CA ARCserve Backup can choose from to consolidate during the migration process. If any of the media prefixes are different than the specified media prefix, the data from those jobs will not be consolidated.

[-consolidate_mediapoolprefix <mediapool prefix>]

Consolidates data based on the specified media pool that you want to use for migration. This allows you to specify a group of media (based on media pool prefix) that CA ARCserve Backup can choose from to consolidate during the migration process. If any of the media pool prefix are different than the specified media pool prefix, the data from those jobs will not be consolidated.

[-consolidate_copymethod <append|overwrite>]

Specifies whether CA ARCserve Backup will append the consolidated data to the destination tape or overwrite the destination tape.

If you specify append, the consolidated data will be added to the existing tape that was formatted on the first day of the backup cycle.

If you specify overwrite, a new tape would be formatted daily and the consolidated data would then be added to that tape. This method is recommended when you are backing up large data on a daily basis.

The advantage of specifying the overwrite method is that a new tape would be used each day and you could ship the previous tape offsite.

If you do not specify a method for consolidation, the append method will be selected by default.

Disk Staging Full Backup Options

The `ca_backup -diskstage` command contains policies that are used to define the options and parameters for CA ARCserve Backup to use during a full backup disk staging job.

The `ca_backup -diskstage` command includes the following full backup policies:

```
ca_backup -diskstage [-fullbackup
  [-DONOTCOPY]
  [-enablesnaplock]
  [-copyDataToDestination
    [afterjobstarts <weeks> <days> <hours> <minutes>] |
    [afterjobends <weeks> <days> <hours> <minutes>] |
    [aftersessionends <weeks> <days> <hours> <minutes>] |
    [at <hh:mm:ss> [afterjobends ]]]]
  [-purgeData
    [afterjobstarts <weeks> <days> <hours> <minutes>] |
    [afterjobends <weeks> <days> <hours> <minutes>] |
    [at <hh:mm:ss>]]]
```

-fullbackup

Specifies that the staging backup job consists of full backups.

-DONOTCOPY

Directs disk staging to back up data to a staging device, but do not copy the media to a final destination after the retention period elapses.

-enablesnaplock

Directs CA ARCserve Backup to use SnapLock protection on the backup job.

-copyDataToDestination

[afterjobstarts <weeks> <days> <hours> <minutes>] |

[afterjobends <weeks> <days> <hours> <minutes>] |

[aftersessionends <weeks> <days> <hours> <minutes>] |

[at <hh:mm:ss> afterjobends]]

Specifies when the copy to final destination operation should begin.

For `-afterjobstarts`, `-afterjobends`, and `-aftersessionends`, you need to input the desired retention period.

-purgeData

[afterjobstarts <weeks> <days> <hours> <minutes>] |

[afterjobends <weeks> <days> <hours> <minutes>] |

[at <hh:mm:ss>]]

Specifies when the purge data from disk process should begin.

For -afterjobstarts and -afterjobends, you need to input the desired length of time that must elapse before the purge process begins.

Disk Staging Incremental/Differential Backup Options

The ca_backup -diskstage command contains policies that are used to define the options and parameters for CA ARCserve Backup to use during an incremental or differential backup disk staging job.

The ca_backup -diskstage command includes the following incremental/differential backup policies:

```
ca_backup -diskstage [-incdiffbackup  
  [-DONOTCOPY]  
  [-enablesnaplock]  
  [-copyDataToDestination  
    [afterjobstarts <weeks> <days> <hours> <minutes>] |  
    [afterjobends <weeks> <days> <hours> <minutes>] |  
    [aftersessionends <weeks> <days> <hours> <minutes>] |  
    [at <hh:mm:ss> [afterjobends ]]]]  
  [-purgeData  
    [afterjobstarts <weeks> <days> <hours> <minutes>] |  
    [afterjobends <weeks> <days> <hours> <minutes>] |  
    [at <hh:mm:ss>]]]
```

-incdiffbackup

Specifies that the staging backup job consists of either incremental or differential backups.

-DONOTCOPY

Directs disk staging to back up data to a staging device, but do not copy the media to a final destination after the retention period elapses.

-enablesnaplock

Directs CA ARCserve Backup to use SnapLock protection on the backup job.

-copyDataToDestination

[afterjobstarts <weeks> <days> <hours> <minutes>] |

[afterjobends <weeks> <days> <hours> <minutes>] |

[aftersessionends <weeks> <days> <hours> <minutes>] |

[at <hh:mm:ss> afterjobends]]

Specifies when the copy to final destination operation should begin.

For -afterjobstarts, -afterjobends, and -aftersessionends, you need to input the desired retention period.

-purgeData

[afterjobstarts <weeks> <days> <hours> <minutes>] |

[afterjobends <weeks> <days> <hours> <minutes>] |

[at <hh:mm:ss>]]

Specifies when the purge data from disk process should begin.

For -afterjobstarts and -afterjobends, you need to input the desired length of time that must elapse before the purge process begins.

Tape Staging Options

The `ca_backup -tapestage` command allows you to back up data to a staging area (tape library or a virtual tape library), and then based on selected policy options, migrate (copy) the data to the final destination (a different tape library). The backup to tape to tape (B2T2T) allows you to submit policy-based jobs that let you copy data to a different tape after a specified length of time has elapsed after the backup operation is complete.

The `ca_backup -tapestage` command has the following format:

```
ca_backup -tapestage <tapestage_group <groupname>>
    [-tapestage_media <medianame>]
    [-tapestage_mediapool <poolname>]
    [-tapestage_enablemus -tapestage_maxstreams <maximum# of streams(1-32)>]
    [-tapestage_enablemux -tapestage_chunksize <size in MB(1-16)>]
    [-fullbackup [Full Backup Policy]]-incdiffbackup [hc Diff Backup Policy]] [Miscellaneous Options]
```

-tapestage <-tapestage_group <groupname>>

Specifies that the backup job will use tape staging functionality and the name of the tape staging group.

-tapestage_media <media name>

Specifies the media name to be used for the backup stage for the job.

-tapestage_media pool <poolname>

Specifies the media pool to be used for the backup stage for the job.

-tapestage_enable mus

Specifies to enable multistreaming and allow simultaneous backup operations to a file system device in a staging group. When multistreaming is enabled, a single backup job is split into multiple jobs using all the tape devices.

-tapestage_maxstreams <maximum # of streams(1-32)>

Specifies the maximum number of simultaneous data streams that this job would be allowed to use while writing to the FSD in the staging group. The available maximum number is 1 to 32 streams.

For example, if the maximum number of streams is specified at 4, this means that at any point of time this staging job will have no more than 4 child jobs writing to the FSD simultaneously.

-tapestage_enable mux

Specifies to enable multiplexing and allow data from multiple sources to be written to the same media simultaneously. When a job that has multiple sources is submitted with the multiplexing option enabled, it is broken into child jobs, with one for each source. These child jobs write data to the same media simultaneously.

-tapestage_chunksize <size in MB(1-16)>

Specifies the maximum amount data (in MB) to be written to the staging device per write operation. The chunk size value determines the amount of contiguous data written for one session before data from another session is multiplexed.

The higher the value, the faster the restore on some drives, but at the cost of memory size during backup. The available chunk size range is 1 to 16 MB. For most drives, the default value of 1 MB is recommended.

-fullbackup [Full Backup Policy] | -incdiffbackup [IncDiff Backup Policy]

Specifies either a Full Backup or an Incremental/Differential Backup to set policies for the backup job. You can then specify the corresponding backup policies.

Tape Staging Full Backup Policies

The `ca_backup -tapestage` command contains backup policies that are used to control how CA ARCserve Backup processes data for full backup jobs.

The `ca_backup -tapestage` command includes the following full backup policies:

```
ca_backup -tapestage <tapestage_group <groupname>>
    [-donotmigrate]]
    [-afterjobends <weeks|-days|-hours|-minutes <count> ...-migthdataonly]]
```

-donotmigrate

Specifies that you do not want to copy the backup data from the staging location to final destination media.

-afterjobends <-weeks|-days|-hours|-minutes <count> ...>

Specifies the number of Weeks, Days, Hours, and Minutes that must elapse after the backup process ends before the migration process starts.

-migmonthdataonly

Specifies to migrate only the monthly GFS backup data. When you include this switch, CA ARCserve Backup migrates monthly full backups to the final destination media. CA ARCserve Backup does not migrate the weekly full backups and the first full backup in the GFS rotation.

Note: If you specify a GFS rotation, CA ARCserve Backup considers the last weekly full backup in a GFS rotation job a monthly backup.

Tape Staging Incremental/Differential Backup Policies

The `ca_backup -tapestage` command contains backup policies that are used to control how CA ARCserve Backup processes data for incremental/differential backup jobs.

The `ca_backup -tapestage` command includes the following incremental/differential backup policies:

```
ca_backup -tapestage <tapestage_group <groupname>>
    [-donotmigrate]]
    [-afterjobends <weeks|-days|-hours|-minutes <count> ...>]
```

-donotmigrate

Specifies that you do not want to copy the backup data from the staging location to final destination media.

-afterjobends <-weeks|-days|-hours|-minutes <count> ...>

Specifies the number of Weeks, Days, Hours, and Minutes that must elapse after the backup process ends before the migration process starts.

Tape Staging Miscellaneous Options

The `ca_backup -tapestage` command contains miscellaneous options that are used to define basic policies and parameters for CA ARCserve Backup to use during a tape staging backup job.

The `ca_backup -tapestage` command includes the following miscellaneous options:

`ca_backup -tapestage <-tapestage_group <groupname>>`

```
[createdmjmakeupjobonhold]
[-rescheduleiffail <on <minutes>|off>]
[-consolidate
  [-consolidate_mediaprefix <prefix>]
  [-consolidate_mediapool <poolname>]
  [-consolidate_mediagroup <groupname>]
  [-consolidate_copymethod <append|overwrite>]
```

-createdmjmakeupjobonhold

Specifies to create a makeup job on hold if a data migration job fails. Include this option to direct CA ARCserve Backup to create makeup jobs on HOLD if the data migration (copy to tape) job fails.

A data migration job can fail if a media or tape drive error occurs during the copy to tape operation. Include this option to create a makeup job with a HOLD status that you can change to a READY status after correcting the tape drive or media errors. If an error condition exists, this option minimizes the needs to create tapecopy jobs.

-rescheduleiffail <on <minutes>| off>

Specifies to schedule a makeup job for a data migration job if it cannot proceed because the source group or tape is not available. Include this option to direct CA ARCserve Backup to schedule a makeup job when the source group or tape is not available.

The source may not be available do to a variety of reasons. For example, the backup phase for the job is not complete, or a hardware problem exists in the tape library or virtual tape library.

You can specify how many minutes must elapse before the makeup will be rescheduled.

By default, this option is set to on.

-consolidate

Specifies to consolidate the backup data during the migration process.

If you want to consolidate data across multiple jobs to the same tape, the backup jobs should be run on the same machine.

-consolidate_mediaprefix <prefix>

Specifies the media prefix for all jobs that you want to consolidate.

-consolidate_mediapool <poolname>

Specifies the name of the media pool that you want to consolidate.

-consolidate_mediagroup <groupname>

Specifies the name of the media group that you want to consolidate.

-consolidate_copymethod <append|overwrite>

Specifies a copy method (Append or Overwrite) that you want to use for the consolidation operation. The method that you specify must be the same for all jobs that you want to consolidate.

Note: When you specify the Append option for weekday schedules, CA ARCserve Backup appends daily backup data to the tape that was formatted on the first day of the GFS backup cycle. When you specify the Overwrite option for weekday schedules, CA ARCserve Backup formats a new tape daily and then consolidates the data from different jobs to that tape.

Return Codes

The following codes are returned by the `ca_backup` command:

If the `-waitForJobStatus` option is not specified:

Return Codes:

- **0** – Command executed successfully.
(For commands which will not submit a job, like `allusage`, `-usage`, or `-list`)
- **N** (positive integer) – Command submitted the job successfully.
(For commands which will submit a job. The actual return value will be the job number)
- **-1** – An error occurred while executing a command.

If the `-waitForJobStatus` option is specified:

Return Codes:

- **0** – Job completed successfully
- **1** – Job failed
- **2** – Job is incomplete
- **3** – Job was cancelled
- **4** – Job status is unknown

Note: If you combine `-waitForjobstatus` with switches like `allusage`, `-usage`, or `-list`, the `-waitForjobstatus` switch will be ignored, and the rule for return codes without `-waitForjobstatus` take effect.

Examples

Example: ca_backup

The following are examples of syntax for the `ca_backup` command:

```
ca_backup -source machine1 -filesystem C:\DIR1 -filesystem D:\DIR2 -username Administrator -password abc
ca_backup -source machine1 -filesystem C:\DIR1 -filelist File1.TXT -filelist File2.TXT -filelist FILE3.TXT -Group
GROUP1 -tape TAPE1 -username Administrator -password abc
```

- Use the following syntax to submit a backup job to a remote CA ARCserve Backup server:

```
ca_backup -cahost machine1 -source machine1 -filesystem D:\DIR1 -username Administrator -password abc
```

- Use the following syntax to submit a backup job through the CA ARCserve Backup Client Agent for Windows to back up data from a remote client machine:

```
ca_backup -source machine1 -filesystem C:\Folder1 -filesystem D:\Folder2 -filelist file.TXT -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem "C:\Program Files\Back me up dir" (path with spaces need to enclose "") -tape TAPE1 -runjobnow -username Administrator -password abc
```

Example: ca_backup -filter

The following are examples of syntax when using `ca_backup -filter`:

```
ca_backup [-filter include|exclude file|dir <pattern>] -username Administrator -password abc
ca_backup -source machine1 -filesystem c:\DIR -filter include file "*.doc" -username Administrator -password abc
ca_backup [-filter include|exclude date modify|create|access on|before|prior|after <mm/dd/yyyy>] -username Administrator -password abc
ca_backup -source machine1 -filesystem c:\DELL -filter exclude dir khan -username Administrator -password abc
ca_backup -source machine1 -filesystem c:\DELL -filter exclude file lrhd.doc -username Administrator -password abc
```

Example: ca_backup -on -at

The following is an example of syntax when using `ca_backup -on -at`:

```
ca_backup -source machine1 -filesystem c:\DIR -filter include file "*.doc" -at 12:50 -on 08/08/2002 -username Administrator -password abc
```

Example: ca_backup Session Password Keys

The following are examples of syntax when using `ca_backup -sessionpassword`:

```
ca_backup -source machine1 -filesystem c:\DIR -username Administrator -password abc
ca_restore -tape TAPE1 -session 2 -dest C:\DIR -sessionpassword xyz -username Administrator -password abc
```

Example: ca_backup Rotation Job

The following are examples of syntax when using the `ca_backup` rotation job option:

```
ca_backup [-filter include|exclude date modify|create|access within <count> days|months|years] -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem c:\DIR1 -filesystem "C:\Program Files\Back me up dir" -rotation -mediapool testingpool -jobunit full append test -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem c:\DIR1 -rotation -mediapool testingpool -jobunit full overwrite test1 -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem c:\DIR1 -mediapool testingpool -exception full append 12/12/2001 -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem c:\DIR1 -gfsrotation -mpoolprefix khan -jobunit full -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem C:\DIR1 -username Administrator -password abc -rotation -mediapool Pool1 -jobunit full overwrite -jobunit full overwrite -jobunit full overwrite -jobunit full overwrite -jobunit full overwrite -retention 5 -tape "*"
```

```
ca_backup -source machine1 -filesystem D:\DIR2 -username Administrator -password abc -gfsrotation -mpoolprefix GFSpool -jobunit full -jobunit incr -jobunit incr -jobunit incr -jobunit incr -jobunit incr -jobunit incr -description GFSpoolJob
```

```
ca_backup -source machine1 -filesystem c:\dell -gfsrotation -mpoolprefix machine1 -jobunit full -jobunit full -jobunit full -jobunit full -jobunit incr -jobunit incr -jobunit full -description pool -username Administrator -password abc
```

```
ca_backup -source 141.202.243.173 unix -filesystem /ca_lic -username root -password abc
```

```
ca_backup -source apoc unix -filesystem /ca_lic -username root -password abc
```

```
ca_backup -source machine1 -filesystem C:\ca_lic -rotation -mediapool khan -jobunit off append * -jobunit incr append * -jobunit incr append * -jobunit incr append * -jobunit incr append * -jobunit full overwrite * -jobunit off append * -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem c:\temp -rotation -mediapool hello -jobunit off overwrite -jobunit full overwrite -jobunit incr append -jobunit incr append -jobunit incr append -jobunit full overwrite -jobunit off overwrite -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem C:\ca_lic -rotation -mediapool khan -username Administrator -password abc
```

```
ca_backup -source dellwin2k -filesystem c:\temp -rotation -mediapool hello -jobunit off overwrite -jobunit full overwrite -jobunit incr append -jobunit incr append -jobunit incr append -jobunit full overwrite -jobunit off overwrite -username Administrator -password abc
```

```
ca_backup -source machine1 -filesystem c:\Temp -rotation -mediapool test -jobunit off overwrite -jobunit full overwrite -jobunit incr append -jobunit incr append -jobunit incr append -jobunit full overwrite -jobunit off overwrite -username Administrator -password abc
```

Example: ca_backup to a Deduplication Device

The following example shows the ca_backup command syntax for a deduplication device that sets the purge policy for a full backup after 4 weeks, 3 days, 2 hours and 1 minute of the job completion time:

```
ca_backup -cahost hostname -source -filesystem c:\temp -group Dedupegroup -dddpurgedata full 4 3 2 1 -username administrator -password caword
```


Chapter 6: ca_dbmgr - Database Manager Command

The database manager command (`ca_dbmgr`) is the command line interface to the Database Manager and the Media Pool Manager. It allows you to maintain the database, including configuring media pools. Using this command you can query database information and set database options. This powerful utility allows other programs to interact easily with backup events. All of the features available from the Database Manager and Media Pool Manager are available from the command line.

Syntax

The `ca_dbmgr` command line syntax is formatted as follows:

```
ca_dbmgr [-cahost <hostname>]
  -show [display options]
  -tape delete <tapeID[:seqNb]>
  -mediapool [media pool management options]
  [database management options]
  -prune on|off|set <count> day(s) <hh:mm>
  -maintenance
  -migrationstatus <job description> [migration status options]
  -help
  -examples
```

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Note: To properly display all Unicode characters in the output of a command, you must first set the environmental variable "ARCSERVE_UNICODE_DISPLAY_CMDL" to a value of 1 prior to running the command as follows:

```
C:\Documents and Settings\cb>set ARCSERVE_UNICODE_DISPLAY_CMDL=1
```

To view these Unicode characters correctly, you will also we need to redirect the output of ca_log after setting the environmental variable as follows:

```
C:\>ca_log -view activity.log >UNICODE_log.txt
```

Usage

The ca_dbmgr commands allow you to set the following options and arguments:

- miscellaneous options
- display options
- media pool management options
- database management options
- maintenance options
- migration status options

Miscellaneous Options

The `ca_dbmgr` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during database management process.

The `ca_dbmgr` command includes the following miscellaneous options:

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: If you include `-cahost` in the command, you must also specify the hostname of the system (local or remote) hosting the operation.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-usage

Displays a list of basic `ca_dbmgr` commands.

-help

Opens the `ca_dbmgr` Help topic.

-examples

Opens a Help topic with `ca_dbmgr` usage examples.

Display Options

The `ca_dbmgr` display options allow you to view information about the jobs processed by CA ARCserve Backup, the media used, data backed up, session information, disk usage, and client information.

The `ca_dbmgr` command includes the following display options:

```
ca_dbmgr [-cahost <host>]-show
  prune
  summary
  jobs | jobsessions <jobID>
    [-completed]
    [-cancelled]
    [-failed]
    [-incomplete]
    [-last <no_of> days | weeks | months]
  tapes | tapesessions <tapeID [seqNb]>
  pools | poolmedia <poolName>
  scratchmedia | savemedia
```

Note: To properly display all Unicode characters in the output of a command, you must first set the environmental variable "ARCSERVE_UNICODE_DISPLAY_CMDL" to a value of 1 prior to running the command as follows:

```
C:\Documents and Settings\cb>set ARCSERVE_UNICODE_DISPLAY_CMDL=1
```

To view these Unicode characters correctly, you will also we need to redirect the output of `ca_log` after setting the environmental variable as follows:

```
C:\>ca_log-view activity.log >UNICODE_log.txt
```

prune

Displays pruning status and settings.

summary

Displays database size and limits, and status of pruning and purging, space information and database information.

jobs -completed | -cancelled | -failed | -incomplete

Displays status and other information for a specified job

jobs | jobsessions <jobID>**[-completed]****[-cancelled]****[-failed]****[-incomplete]****[-last <no_of> days | weeks | months]**

Display information for all jobs of a particular type or all sessions contained in the specified job ID.

For example, enter [-completed] to view all completed jobs. You can also enter a time limit, for example: [-last 2 weeks].

If you enter the command without any parameters, information on all jobs in the database will be displayed.

tapes | tapesessions <tapeID[:seqNo]>

Displays information about the specified tape or tapesessions.

pools | poolmedia <poolName>

Displays information about the specified pools or poolmedia.

scratchmedia

Displays information about all medias current in the scratch set of a media pool. The information includes the tape name, serial number, tape ID, sequence number, format date, expiration date, and the media pool it belongs to.

savemedia

Displays information about all medias current in the save set of a media pool. The information includes the tape name, serial number, tape ID, sequence number, format date, expiration date, and the media pool it belongs to.

Media Pool Management Options

The `ca_dbmgr` media pool management options allow you to manage, create, and maintain logical groupings of media (media pools) for easy identification of backups.

The `ca_dbmgr` command includes the following media pool management options:

```
ca_dbmgr [-cahost <host>]-mediapool
  add <poolName> <saveTapes>
    [-b <baseSerial>]
    [-i <serialIncr>]
    [-m <maxSerial>]
    [-retention <retentionDays>]
  modify <poolName>
    [-save <saveTapes>]
    [-retention <retentionDays>]
  delete [-f] <poolName> [tapeID[:seqNo]]
  move <tapeID[:seqNo]> <fromPoolName> <toPoolName> SCRATCH | SAVE
```

add <poolName> <saveTapes>

[-b <baseSerial>]

[-i <serialIncr>]

[-m <maxSerial>]

[-retention <retentionDays>]

Creates a new media pool. You must specify the name of the media pool and the minimum number of media to keep in the Save Set.

Optionally, you can specify serial number information and the retention period.

modify <poolName>

[-save <saveTapes>]

[-retention <retentionDays>]

Allows you to change the minimum number of media to keep in the Save Set and the retention time for the specified media pool.

delete [-f] <poolName> [tapeID [:seqNo]]

Deletes the specified tape from the specified media pool.

If you enter the name of a media pool without specifying a tape, the entire media pool is deleted.

Use the `-f` switch to perform the deletion in non-interactive mode.

**move <tapeID [:seqNo]> <fromPoolName> <toPoolName>
SCRATCH|SAVE**

Moves tapes from media pool to media pool. You can also move tapes from the Scratch Set to the Save Set, or back. You can use the default value for either the *fromPoolName* value or the *toPoolName* value to specify a non-pool setting.

For example, to move a tape that is unassigned a pool value, use the default value setting for the *fromPoolName* value. This command also has the same function as Move Media in the Media Pool Manager user interface.

Database Management Options

The `ca_dbmgr` database management options allow you to query database information and set database options.

The `ca_dbmgr` command includes the following database management options:

```
ca_dbmgr [-cahost <host>]
-tape delete <tapeID[:seqNo]>
-prune on | off | set <count> days | months | year(s) <hh:mm>
```

-tape delete <tapeID[:seqNo]>

Deletes a specified tape from the database.

-prune on | off | set <count> day(s) <hh:mm>

Sets database pruning on or off.

Specifies the elapsed number of days and the starting time for the pruning period. During the pruning process, all detail records older than the specified number of days will be removed from the database at the specified time every day.

For example, to specify that the pruning operation should remove all records older than seven days, and that the pruning should start at 5 PM every day, enter the following command:

```
ca_dbmgr -prune set 7 days 17:00
```

Note: Pruning removes detail records older than the specified number of days, but retains job and session records.

Maintenance Options

The `ca_dbmgr` maintenance options allow you to tune and maintain the database in an efficient state and a manageable size. By periodically performing these maintenance tasks you can improve the overall performance of the CA ARCserve Backup database.

The results of the maintenance tasks will be saved to a special maintenance log called `SQLMaint.log`, which is located in the CA ARCserve Backup LOG directory.

The `ca_dbmgr` command includes the following maintenance options:

```
ca_dbmgr [-cahost <host>]
          -maintenance
            [UpdateStatistics]
            [ReBuildIndex]
            [CheckIntegrity]
            [ReduceDBSize]
```

UpdateStatistics

Updates the statistics on all the tables and indexes in your database.

SQL Server collects statistics about the distribution of data in tables and indexes and uses these statistics to determine which indexes to use during a query process. If the statistics are outdated, SQL Server might not be able to properly evaluate which indexes to use when executing a query and as a result, might choose to perform a time-consuming scan of a complete table instead of just scanning an index. Having up-to-date statistics is important to ensure effective use of indexes.

Recommended: daily

ReBuildIndex

Rebuilds all indexes in your database to ensure that the data is not fragmented.

When you perform any data modification operations (insert, update, delete) table fragmentation can occur. When this data modification affects the index, index fragmentation can also occur and information in the index can get scattered in the database. Fragmented data can cause SQL Server to perform unnecessary data reads during a query process and result in slow and inefficient performance. The greater the fragmentation, the less effective the index will be. Periodically rebuilding the index will remove fragmentation, reclaim disk space, and improve overall performance during a database query.

Recommended: weekly

CheckIntegrity

Checks the integrity of all objects in the CA ARCserve Backup database.

Databases can be corrupted by unusual events such as hardware failures, sudden loss of power, operating system failure, or improper operator action. It is important to periodically check the allocation, structural, and logical integrity of all objects in the CA ARCserve Backup database. Performing a database integrity check on a regular basis will detect and report any changes in the database that occurred since the last integrity check. Depending upon the size of your database, this can be a time-consuming task.

Recommended: weekly

ReduceDBSize

Reduces the size of the data and log files in the CA ARCserve Backup database and releases them back to the operating system.

Over time, your log files and data files can grow rapidly to a very large size and reduce the effectiveness of your database. When you control database size, performance will often improve and more users can access the database.

When you run ReduceDBSize you will need to enter the name of the database you want to shrink, along with the percentage of free space to leave in each file of the database. For example, if you've used 60 MB of a 100-MB database file, you can specify a shrink percentage of 25 percent. SQL Server will then shrink the file to a size of 80 MB, and you'll have 20 MB of free space.

Recommended: as needed

Migration Status Options

The `ca_dbmgr` migration status options allow you to check a specified job to determine if the migration process has been successfully completed or not.

The `ca_dbmgr` command includes the following migration status options:

```
ca_dbmgr [-cahost <host>]
        -migrationstatus <job description>
            [-lastjobbeforestarttime <mm/dd/yyyy hh:mm:ss>] |
            [-lastjobbeforeendtime <mm/dd/yyyy hh:mm:ss>]
```

-migrationstatus <job description>

Allows you to check the migration status for the specified job. This command will return status properly only if you assign unique job descriptions while submitting jobs.

The available return codes for this check are as follows:

- **1** - migration failed
- **2** - migration completed
- **3** - migration in progress
- **4** - migration not required
- **5** - failed to get migration status

-lastjobbeforestarttime <mm/dd/yyyy hh:mm:ss>

Allows you to check the migration status for the last job started on the specified date and time. This is helpful for jobs that have been started multiple times on the same day.

-lastjobbeforeendtime <mm/dd/yyyy hh:mm:ss>

Allows you to check the migration status for the last job that ended on the specified date and time. This is helpful for jobs that have been run and finished multiple times on the same day.

Examples

The following are examples of syntax for the `ca_dbmgr` command:

- Use the following command to display the CA ARCserve Backup database pruning configuration settings (DB Pruning time, # of days after which sessions are removed):

```
ca_dbmgr -cahost machine1 -show prune
```

- Use the following command to display the CA ARCserve Backup database summary (Total Space occupied, Free Space, DB Size, DB Job/Tape/Media record count, etc..)

```
ca_dbmgr -cahost machine1 -show summary
```

- Use the following command to display details of a specified job ID:

```
ca_dbmgr -cahost machine1 -show jobs 8
```

- Use the following command to display details of all jobs in the last 8 days with status as 'complete':

```
ca_dbmgr -cahost machine1 -show jobs -completed -last 8 days
```

- Use the following command to display details of all the sessions for a specified ID:

```
ca_dbmgr -cahost machine1 -show jobsessions 8
```

- Use the following command to display details of all the tapes recorded in the database:

```
ca_dbmgr -cahost machine1 -show tapes
```

- Use the following command to display details of all the sessions on a specified tape

```
ca_dbmgr -cahost machine1 -show tapesessions AB3C
```

- Use the following command to display details of all the media pools:

```
ca_dbmgr -cahost machine1 -show pools
```

- Use the following command to display details of a specified media pool:

```
ca_dbmgr -cahost machine1 -show poolmedia POOL1
```

Example: ca_dbmgr Media Pool Management Options

- Use the following command to add a new media pool with specified parameters:

```
ca_dbmgr -cahost machine1 -mediapool add POOL1 0-b 1200000 -i 1000 -m 1299999 -retention 100
```

- Use the following command to modify a media pool with specified settings of the number of media in the save set and the retention time period (99 days):

```
ca_dbmgr -cahost machine1 -mediapool modify POOL1 -save 0 -retention 99
```

- Use the following command to remove the specified media (AB3C) from media pool TMPPOOL:

```
ca_dbmgr -cahost machine1 -mediapool delete -f TMPPOOLAB3C
```

- Use the following command to move the specified media (AB3C) from media pool "POOL1" to the save set of media pool "POOL2":

```
ca_dbmgr -cahost machine1 -mediapool move AB3C POOL1 POOL2 SAVE
```

Example: ca_dbmgr Database Management Options

- Use the following command to delete the media record with ID AB3C:1:

```
ca_dbmgr -cahost machine1 -tape delete AB3C:1
```

- Use the following command to modify the database pruning settings to a job execution time of 23:59 and prune all records exceeding 20 days:

```
ca_dbmgr -cahost machine1 -prune set 20 days 23:59
```

Example: ca_dbmgr Database Maintenance Options

- Use the following command to rebuild the index:

```
ca_dbmgr -cahost machine1 -maintenance RebuildIndex
```

Chapter 7: ca_devmgr - Device Manager Command

The device manager command (`ca_devmgr`) allows you to perform various device management commands in CA ARCserve Backup without interfacing with the Device Manager. You can use this tool to obtain information or to manipulate the tape or library devices. This command allows you to control storage devices, and to format and erase media in drives or changers. All of the features available from the Device Manager are available from the command line.

To use `ca_devmgr`, CA ARCserve Backup must be running, and you need authorization by an authentication service. If you are not authorized, then run the `ca_auth` utility to authorize yourself.

Syntax

The `ca_devmgr` command line syntax is formatted as follows:

```
ca_devmgr [-cahost <hostname>]
          [miscellaneous options]
          [general command options]
          [tape drive command options]
          [tape library command options]
          [FSD command options]
```

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_devmgr` command includes the following options:

- miscellaneous options
- general options
- tape drive options
- tape library options
- FSD options

Miscellaneous Options

The `ca_devmgr` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during a device management process. Miscellaneous commands do not interact with a tape drive or a tape library, but do interact with CA ARCserve Backup.

The `ca_devmgr` command includes the following miscellaneous options:

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: If you include `-cahost` in the command, you must also specify the hostname of the system (local or remote) hosting the operation.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-usage

Displays a list of basic `ca_devmgr` commands.

allusage

Displays a list of all `ca_devmgr` commands and their switches.

-help

Opens the ca_devmgr Help topic.

-examples

Opens a Help topic with ca_devmgr usage examples.

General Options

Common commands can be used whether you have a tape drive or a tape library attached to the system.

ca_devmgr [-cahost <host>]

-v <adapterinfo...>|<deviceinfo...>|<groupinfo...>|<mediainfo...>

-adapterinfo

-groupinfo [-alldomain]

-deviceinfo <adapter #> <scsi ID> <lun>|<groupname>|<-all>|<-alldomain>

-mediainfo <adapter #> <scsi ID> <lun>

-setdebug <none|summary|detail|detail+>

-v

Used only with the adapterinfo, deviceinfo, groupinfo, and mediainfo commands. The major difference in using the -v switch is to print additional information about these four commands. The -v switch is more of a verbose command.

- adapterinfo

Cycles through all the SCSI adapters attached to the system and prints out the adapter name, adapter number, SCSI ID, vendor ID, product ID, and firmware of any tape drive or tape library connected to the system.

-groupinfo

Prints the adapter number, SCSI ID, vendor ID, product ID, firmware, and status (tape libraries only) information on all groups configured in CA ARCserve Backup.

-deviceinfo <adapter #> <scsi ID> <lun>

Prints the type of device, SCSI ID, vendor ID, product ID, firmware, status, and device sharing (tape libraries only) information for any tape drive or tape library.

The adapter number, SCSI ID, and lun are required.

-mediainfo <adapter #> <scsi ID> <lun>

Prints the tape name, tape ID, sequence number, serial number, and expiration date for any tape device. For tape libraries, the same information is displayed, including slot number, and if the tape is loaded and write protected. For tape libraries, each slot is displayed.

The adapter number, SCSI ID, and lun are required.

-setdebug <none|summary|detail|detail+>

Controls the level of debugging information that appears in the TAPE.LOG file which is generated and stored in the CA ARCserve Backup\Log folder.

none

No information is logged.

summary

Logs critical messages and reduces the size of the tape log by excluding unnecessary information.

This is the default setting.

detail

Logs all commands sent to the attached backup devices by CA ARCserve Backup, but does not include Read/Write commands and Test Unit Ready commands. Tape Engine specific information, which may be used by Customer Support to troubleshoot backup and restore issues, is also logged.

detail+

Logs all commands sent to the attached backup devices by CA ARCserve Backup, including Read/Write commands and Test Unit Ready commands. Tape Engine specific information, which may be used by Customer Support to troubleshoot backup and restore issues, is also logged.

Tape Drive Options

The following tape drive options can be used only for a tape drive.

`ca_devmgr [-cahost <host>]`

```
-format [<adapter #> <scsi ID> <lun> <tape name>] [<mm/dd/yyyy> <serial no.>] [MEDIAPOOL <mediapool name>]
-erase [<adapter #> <scsi ID> <lun>] [q|qz|qw|I]
-online [<adapter #> <scsi ID> <lun>]
-offline [<adapter #> <scsi ID> <lun>]
-compression [<adapter #> <scsi ID> <lun>] <on|off>
-eject [<adapter #> <scsi ID> <lun>]
-retension [<adapter #> <scsi ID> <lun>]
```

-format [<adapter #> <scsi ID> <lun> <tape name>] [<mm/dd/yyyy> <serial no.>] [MEDIAPOOL <mediapool name>]

Formats a tape in a tape drive.

When used with the **-force** option, formats the specified media, regardless of whether it is in a Save Set or Scratch Set.

The adapter number, SCSI ID, lun, and the new name of the tape are required. The date and serial number are optional.

-erase [<adapter #> <scsi ID> <lun>] [q|qz|qw|I]

Erases a tape in a tape drive.

When used with the **-force** option, erases all data on specified media, regardless of whether it is in a Save Set or Scratch Set.

The adapter number, SCSI ID, and lun options are required.

Options include:

- **q** - quick erase (destroy media label). This is the default option.
- **qz** - quick erase plus (destroy media label and serial number).
- **qw** - quick erase and convert it to WORM, if media and tape drive support WORM technology. If hardware does not support WORM technology, the erase operation will fail.
- **I** - long erase (destroy all data on the media).

Important! Long erase removes the entire media from the beginning of the tape to the end of the tape, and may take a long time to complete.

-online [*<adapter #>* *<scsi ID>* *<lun>*]

Sets the specified device (FSD or tape device) to an online status. When set to online, the device can be shared among multiple servers.

You must verify that you do not have more than one server set to write backup data to the same device at the same time. If multiple servers access the device at the same time, the backup could fail and data could get lost.

Example: If you have a FSD/tape device whose adapter #, scsi ID, and lun is 0, 0, and 1 and you want to set it to an online status, enter the following command:

```
-ca_devmgr-online 001
```

-offline [*<adapter #>* *<scsi ID>* *<lun>*]

Sets the specified device (FSD or tape device) to an offline status. When set to offline, no other backup job can be submitted to the device.

If a backup job to the device is already in progress, you will not be allowed to change the device status to offline until the job is completed. For an FSD, this prevents multiple servers from inadvertently accessing the device at the same time. If a backup job attempts to access the device when set to offline, the job will fail.

Example: If you have a FSD/tape device whose adapter #, scsi ID, and lun is 0, 0, and 1 and you want to set it to an offline status, enter the following command:

```
-ca_devmgr-offline 001
```

-compression [*<adapter #>* *<scsi ID>* *<lun>*] *<on|off>*

Enables or disables compression on a tape drive.

For this command to work, the tape device must support compression and there must be a blank tape in the drive.

The adapter number, SCSI ID, lun and the on or off flags are required.

-eject [*<adapter #>* *<scsi ID>* *<lun>*]

Ejects a tape from the tape drive.

To use this command, the tape drive must support the eject command. The adapter number, SCSI ID, and lun options are required.

-retension [*<adapter #>* *<scsi ID>* *<lun>*]

Retensions a tape in a tape drive.

The adapter number, SCSI ID, and lun are required.

Tape Library Options

The following tape library options can be used only for a tape library.

`ca_devmgr [-cahost <host>]`

`-cherase <adapter #> <changer scsi ID> <changer lun> [<slot #> [q|qz|pw]] ...]`

or

`-cherase <adapter #> <changer scsi ID> <changer lun> SLOT_RANGE <slot range> [q|qz|pw]]`

`-chformat <changer adapter #> <changer scsi ID> <changer lun>`

`SLOT <slot #> <tape name> [<mm/dd/yy[yy]>|def [<serial no.>]] MEDIA POOL [<mediapool name>] SLOT
<slot #> <tape name> [<mm/dd/yy[yy]>|def [<serial no.>]] MEDIA POOL [<mediapool name>] ...]`

`-load <changer adapter #> <changer scsi ID> <changer lun> <drive adapter #> <drive scsi ID> <drive lun>
<slot #>`

`-unload <changer adapter #> <changer scsi ID> <changer lun> <drive adapter #> <drive scsi ID> <drive lun>`

`-mount <changer adapter #> <changer scsi ID> <changer lun> <beg. slot> <end slot> [q]]`

`-dismount <changer adapter #> <changer scsi ID> <changer lun> <beg. slot> <end slot>`

`-ieinfo <changer adapter #> <changer scsi ID> <changer lun>`

`-import <changer adapter #> <changer scsi ID> <changer lun> <slot #> [<slot #> ...]`

`-export <changer adapter #> <changer scsi ID> <changer lun> <slot #> [<slot #> ...]`

`-clean <changer adapter #> <changer scsi ID> <changer lun> <drive adapter #> <drive scsi ID> <drive lun>`

`-importall <changer adapter #> <changer scsi ID> <changer lun>`

-cherase <adapter #> <changer scsi ID> <changer lun> [<slot #> [q|qz|qw|l] ...]

-cherase <adapter #> <changer scsi ID> <changer lun> SLOT_RANGE <slot range> [q|qz|qw|l]

Erases a single tape or multiple tapes in a tape library.

When used with the **-force** option, erases all data on specified media, regardless of whether it is in a Save Set or Scratch Set.

The adapter number, changer SCSI ID, changer lun, and slot are required.

Options include:

- **q** - quick erase (destroy media label). This is the default option.
- **qz** - quick erase plus (destroy media label and serial number)
- **qw** - quick erase and convert it to WORM, if media and tape drive support WORM technology. If hardware does not support WORM technology, the erase operation will fail.
- **l** - long erase (destroy all data on the media).

Alternatively, enter `ca_devmgr -cherase [groupname] slot # [q|qz|qw|l] [,slot # [q|qz|qw|l] ,...]` to erase the tape using just the group name and the slot number.

Note: The "," in the examples is not a switch. It is there only to show you how to specify multiple slots to be erased.

**-chformat <changer adapter #> <changer scsi ID> <changer lun>
SLOT <slot#> <tape name> [<mm/dd/yy[yy]>|def [<serial no.>]]
MEDIAPool [<mediapool name>] SLOT <slot#> <tape name>
[<mm/dd/yy[yy]>|def [<serial no.>]] MEDIAPool [<mediapool
name>] ...]**

Formats a single tape or multiple tapes in a tape library.

When used with the **-force** option, formats the specified media, regardless of whether it is in a Save Set or Scratch Set.

The changer adapter number, changer SCSI ID, changer SCSI LUN, and group name are required, as are the word SLOT, the slot number where the tape to be formatted is located, and the tape name. The mm/dd/yyyy (the expiration date) is optional.

The def switch (default expiration date) cannot be used with the expiration date. (The "|" between the expiration date and the default expiration date indicates you must choose one or the other.) The serial number is optional. The 3 "." at the end means that you can specify more slot numbers.

Alternatively, you can enter `ca_devmgr -chformat [SLOT <slot#> <tape name> [<mm/dd/yy[yy]>|def [<serial no.>]]`.

The changer format can use the the slot number and the tape name. The expiration date and the serial number are optional, the rest is required. The word SLOT must be used before each slot number you specify.

-load <changer adapter #> <changer scsi ID> <changer lun> <drive adapter #> <drive scsi ID> <drive lun> <slot #>

Loads a tape from a specified slot into a tape drive.

The changer adapter number, changer SCSI ID, changer lun, drive adapter number, drive SCSI ID, drive lun, and slot number are required.

-unload <changer adapter #> <changer scsi ID> <changer lun> <drive adapter #> <drive scsi ID> <drive lun>

Unloads a tape from a tape drive and returns it in the specified slot.

The changer adapter number, changer SCSI ID, changer lun, and the slot number are required.

-mount <changer adapter #> <changer scsi ID> <changer lun> <beg. slot> <end slot> [q|l]

Performs an inventory of your entire tape library.

If your tape library does not have a bar code reader, CA ARCserve Backup puts all the tapes into the tape drive and reads them. If your tape library does have a bar code reader, you can specify whether to obtain the information from the database or have CA ARCserve Backup read in all the tapes. The changer adapter number, changer SCSI ID, changer lun, beginning slot, and end slot are required.

The beginning and end slots can be any slot number, as long as the slots conform to the group you are mounting. The end slot cannot be smaller than the beginning slot. The q (quick mount) or l (long mount) options are optional. Quick mount is the default for tape libraries with bar code readers.

If your tape library has a bar code reader, it obtains the information from the CA ARCserve Backup database. Long mount forces CA ARCserve Backup to put each tape into the tape drive and read the information on it. If your tape library has no bar code reader, the q switch is disabled, and each tape must be read in by the tape drive.

-dismount <changer adapter #> <changer scsi ID> <changer lun> <beg. slot> <end slot>

Dismounts the slots in the specified group within the range provided in the options, and renames all slots to "Dismounted Slot".

Unless CA ARCserve Backup is restarted or a mount command is issued to the dismounted group, no other command can be issued to the dismounted slots. The changer adapter number, changer SCSI ID, changer lun, beginning slot, and end slot are required.

-ieinfo <changer adapter #> <changer scsi ID> <changer lun>

Displays information on the import/export slot of the library, including whether or not it is full and, if full, the barcode number of the tape in the slot.

The changer adapter number, changer SCSI ID, and the changer lun are all required.

-import <changer adapter #> <changer scsi ID> <changer lun> <slot #> [<slot #> ...]

Takes a tape from the import/export slot of the tape library and places it into its destination slot.

If your tape library has a bar code reader enabled, the information is taken from the database, and the tape is not read in by the drive.

If your tape library does not have a bar code reader, it places the tape into the drive to be read.

The changer adapter number, changer SCSI ID, changer lun, and slot number are required. The only optional switch is the extra *slot # ...* for tape libraries with more than one import/export slot. You can import multiple tapes at the same time. If your tape library has only one import/export slot, you can only import one tape at a time.

-export <changer adapter #> <changer scsi ID> <changer lun> <slot #> [<slot #> ...]

Takes a tape from a slot in the tape library and puts it in the import/export slot.

The changer adapter number, changer SCSI ID, changer lun, and the slot number are required. The *slot #...* is to export multiple tapes. This can only be done if your tape library has more than one import/export slot.

-clean <changer adapter #> <changer scsi ID> <changer lun> <drive adapter #> <drive scsi ID> <drive lun>

Takes a cleaning tape (if one is installed in the tape library), puts it into the specified drive, and cleans the tape drive.

The changer adapter number, changer SCSI ID, changer lun, tape drive adapter number, tape drive SCSI ID, and tape drive lun are required.

-importall <changer adapter #> <changer scsi ID> <changer lun>

Imports each tape found in the library's mail slots into the first available storage slot(s) in the library specified.

You can use this when you just want to import tapes from the mail slot, but do not need the tapes to go to any specific storage slots.

If there is not enough library slots for all the tapes in the mail slots, a message "Not enough empty slots to import all the tapes!" will be displayed after all the empty library slots have been filled.

The changer adapter number, changer SCSI ID, and changer lun are required.

FSD Options

The following File System Device (FSD) options can be used only for an FSD.

ca_devmgr [-cahost <host>]

-format [<adapter #> <scsi ID> <lun> <tape name>] [<mm/dd/yyyy> <serial no.>]

-erase [<adapter #> <scsi ID> <lun>] [q|qz|pw |]

-online [<adapter #> <scsi ID> <lun>]

-offline [<adapter #> <scsi ID> <lun>]

-purge <adapter #> <scsi ID> <lun> -sessions <session no.> [<session no.>]

or

-purge <adapter #> <scsi ID> <lun> -sessions <session range>

<session range> can be either <start session no.><end session no.> or "all" which means all sessions

-query <adapter #> <scsi ID> <lun> <all|copied|uncopied|purgable|snaplocked|failed> -sessions <session no.> [<session no.>]

or

-query <adapter #> <scsi ID> <lun> <all|copied|uncopied|purgable|snaplocked|failed> -sessions all

-regenerate [<adapter #> <scsi ID> <lun> <tape name>] [<tape ID> <mm/dd/yyyy>]

-createfsd <FSD Description> <FSD Name> <FSD Path> [<Domain Name> <User> <Password>]

-removefsd <FSD Path>

-setstaging <Group Name> [-mstreams <Max Stream>] [-mthreshold <Max Threshold/Purge to Threshold <"xx/xx%"|"xx/xx">>] [-snaplock <Enable Snaplock <0|1>>] [-pausemig <Pause Migration <0|1>>] [-chunksize <Chunk Size>]

-cleanstaging <Group Name>

-getstaging <Group Name>

-queryfsd <FSD Path> [-group]

-creatededupfsd <FSD Description><FSD Name><Data Path><Index Path> [<Domain Name> <User><Password>] [-GrpName <Group Name>]

-removededupfsd <Group Name>

-configdedupfsd <Group Name> [-FSDsp<FSD Description>] [-FSDName <FSD Name>] [-DataPath <Data Path>] [-IndexPath <IndexPath>]

-setdedupegrproperties <Group Name> [-mstreams <Max Stream>] [-mthreshold <Max Threshold <"xx%"|"xx">>] [-pausemig <Pause Migration <0|1>>] [-optimization <Allow Optimization <0|1>]

-getdedupegrproperties <Group Name>

**-format [<adapter #> <scsi ID> <lun> <tape name>]
[<mm/dd/yyyy> <serial no.>]**

Formats a tape in a tape drive.

When used with the **-force** option, formats the specified media, regardless of whether it is in a Save Set or Scratch Set.

The adapter number, SCSI ID, lun, and the new name of the tape are required. The date and serial number are optional.

-erase [<adapter #> <scsi ID> <lun>] [q|qz|qw|l]

Erases a tape in a tape drive.

When used with the **-force** option, erases all data on specified media, regardless of whether it is in a Save Set or Scratch Set.

The adapter number, SCSI ID, and lun options are required.

Options include:

- **q** - quick erase (destroy media label). This is the default option.
- **qz** - quick erase plus (destroy media label and serial number).
- **qw** - quick erase and convert it to WORM, if media and tape drive support WORM technology. If hardware does not support WORM technology, the erase operation will fail.
- **l** - long erase (destroy all data on the media).

Important! Long erase removes the entire media from the beginning of the tape to end of the tape, and may take a long time to complete.

-online [<adapter #> <scsi ID> <lun>]

Sets the specified device (FSD or tape device) to an online status. When set to online, the device can be shared among multiple servers.

You must verify that you do not have more than one server set to write backup data to the same device at the same time. If multiple servers access the device at the same time, the backup could fail and data could get lost.

Example: If you have a FSD/tape device whose adapter #, scsi ID, and lun is 0, 0, and 1 and you want to set it to an online status, enter the following command:

```
-ca_devmgr-online 00 1
```

-offline [<adapter #> <scsi ID> <lun>]

Sets the specified device (FSD or tape device) to an offline status. When set to offline, no other backup job can be submitted to the device.

If a backup job to the device is already in progress, you will not be allowed to change the device status to offline until the job is completed. For an FSD, this prevents multiple servers from inadvertently accessing the device at the same time. If a backup job attempts to access the device when set to offline, the job will fail.

Example: If you have a FSD/tape device whose adapter #, scsi ID, and lun is 0, 0, and 1 and you want to set it to an offline status, enter the following command:

```
-ca_devmgr-offline 0 0 1
```

-purge <adapter #> <scsi ID> <lun> -sessions <session no.> [*<session no.>*]

-purge <adapter #> <scsi ID> <lun> -sessions <session range>

Purges the specified session or group of sessions. Use this command to delete the data from the FSD.

- If one of the sessions is SnapLock protected, a warning will be logged for that session and the purge process will continue for the rest of the specified sessions.
- If a session was supposed to be migrated and has not been migrated yet, a warning will be logged, the session will not be purged, and the purge process will continue for the rest of the specified sessions.

You can specify the **-force** option to purge sessions, regardless of whether it has been migrated or not.

- If a session is active, a warning will be logged, the session will not be purged and purge process will continue for the rest of the specified sessions.

You can specify to purge a single session or multiple sessions in one of three methods; by session numbers (single or group), by range, or by all.

-sessions <session no.> [*<session no.>*]

-sessions <session range>

Note: <session range> can be either <start session no.>-<end session no.> or "all" which means all sessions

Specifies the session number (or group of session numbers), the range of session numbers, or all session numbers to be purged.

- To specify a single session to be purged, you must use the following syntax format
-sessions 1
- To specify a group of sessions to be purged, you must provide a list of space-separated session numbers using the following syntax format:
-sessions 1 2 5 7 8
- To specify a range of sessions to be purged, you must provide the start session number and end session numbers connected by a dash using the following syntax format:
-sessions 3-5
- To specify all sessions to be purged, you must use the following syntax format:
-sessions all

**-query <adapter #> <scsi ID> <lun>
<-all|-copied|-uncopied|-purgable|-snaplocked|-failed> -sessions**

Queries the specified sessions. Use this command to query the server about the currently active user sessions. You can request information about all of the active sessions or just those sessions that match the type you specify.

The -query command provides you with a description of the following information:

- All copied and uncopied sessions
- All sessions with SnapLock security
- Retention period for each session
- All sessions that can be purged

The adapter number, SCSI ID, and lun are required.

-copied

Displays a list of all copied sessions.

-uncopied

Displays a list of all sessions that were not copied.

-purgable

Displays a list of all sessions that can be purged.

-snaplocked

Displays a list of all sessions with SnapLock protection enabled and the retention period for each session.

-failed

Displays a list of all sessions that failed.

-sessions <list of space separated sessions | all>

Specifies the session number, the group of session numbers, or all session numbers that you want to query.

- To specify a single session to be queried, you must use the following syntax format
-sessions 1
- To specify a group of sessions to be queried, you must provide a list of space-separated session numbers using the following syntax format
-sessions 1 2 3
- To specify all sessions to be queried, you must use the following syntax format:
-sessions all

-regenerate [*<adapter #>* *<scsi ID>* *<lun>* *<tape name>*] [*<tape ID>* *<mm/dd/yy[yy]>*]

Used with file system devices if you accidentally delete the tape header. It lets you regenerate or rebuild a tape header with a specified tape name (*<tape name>*) for a file system device. After you generate a new tape header, you can then merge all of the sessions on the file system device into the CA ARCserve Backup database, which enables the capability for point-and-select restores.

If you know the original tape name (*<tapename>*) and its tape ID (*<tapeID>*), you can reuse them so that the session records in the CA ARCserve Backup database can reconnect to the volume without having to merge the session records again. (You can check the original tape record in the CA ARCserve Backup database for the tape name and tape ID).

You can use the *<mm/dd/yyyy>* parameter to specify a different tape expiration date from the default date.

-createfsd

Specifies to create an FSD dynamically during run time, without stopping the tape engine. CA ARCserve Backup will check if the device to create is already in the device list system, and if not will add it to the device list.

Note: For *ca_devmgr*, the *-createfsd* command will fail if the CA ARCserve Backup Configure Groups GUI is open.

FSD Description

Specifies the description for the FSD being created.

FSD Name

Specifies the identity name for the FSD being created.

FSD Path

Specifies the physical path for the FSD being created.

Domain Name

Specifies the domain to access the remote FSD being created.

User

Specifies the user name to access the remote FSD being created.

Password

Specifies the user password to access the remote FSD being created.

-removefsd *<FSD Path>*

Specifies to remove an FSD dynamically from CA ARCserve Backup during run time, without stopping the tape engine.

-setstaging <Group Name>

Specifies to configure the FSD group as a staging group.

-mstreams <Max Stream>

Specifies the maximum number of simultaneous data streams to be sent to the FSD in a staging group.

The available options are 1 or 2 streams, and the default value is 1 stream.

-mthreshold <Max Threshold/Purge to Threshold**<"xx/xx%"|"xx/xx">**

Specifies the maximum capacity threshold and purge to threshold of the FSD.

When the amount of used space on the FSD is greater than the specified maximum threshold, the data (from the oldest migrated sessions) will begin to be purged from the FSD. The "purge to" threshold is the minimum threshold and allows you to specify the amount of used space on an FSD when CA ARCserve Backup stops purging.

The maximum and purge to thresholds can be represented as either an absolute value (in MB) or as a percentage of the capacity of the volume.

By default, the maximum threshold value is 80%.

By default, the purge to threshold value is 60%.

The following example sets the maximum threshold value at 80% and the purge to threshold value at 60%:

```
ca_devmgr -setstaging group0 -mthreshold "80/60"
```

If you only specify one threshold value, it will automatically represent the maximum threshold and the purge to threshold will be disabled. (The purge to threshold cannot be set independent of the maximum threshold.)

The following example sets the maximum threshold value at 80% and disables the purge to threshold:

```
ca_devmgr -setstaging group0 -mthreshold "80"
```

Notes:

- The specified maximum threshold must always be greater than the purge to threshold.
- If the threshold value is set as a percent, the maximum threshold must be less than 100% and the purge to threshold must be greater than 0%. (If the purge to value is 0%, the auto purge will be disabled).
- If the threshold value is set as an absolute value, the maximum threshold must be greater than 1 MB. The purge to value must be greater than 0. (If the value is 0, the auto purge will be disabled).

-snaplock <Enable Snaplock <0|1>>

Specifies to enable or disable SnapLock protection. When you back up data with SnapLock protection enabled, you cannot purge or over-write the backed up data until the specified retention time elapses. This ensures that the data on the FSD can not be deleted by any user.

0 = Disabled

1 = Enabled

By default SnapLock is disabled.

-pausemig <Pause Migration <0|1>>

Specifies to pause the migration of data from the FSD to the final destination media. This option allows you to continue backing up to the FSD, but pauses the migration from the FSD to the final destination media in case the final destination media is scheduled for maintenance or has hardware problems.

0 = Disabled

1 = Enabled

By default, the pause data migration option is disabled.

-chunksize <Chunk Size>

Specifies the maximum amount of data (in KB) to be written to the staging device per write operation.

By default, the staging chunk size is 512KB.

-cleanstaging <Group Name>

Specifies to clean (or remove) the FSD staging group attributes from the local/remote server.

-getstaging <Group Name>

Specifies to get (or obtain) the staging group attributes from the local/remote server.

-queryfsd <FSD Path> [-group]

Specifies to query the FSD adapter number, scsi id, and lun by default; or query FSD group by switch "-group", this is mainly used for the automation script.

-creatededupefsd <FSD Description><FSD Name><Data Path><Index Path> [<Domain Name> <User><Password>] [-GrpName <Group Name>]

Directs CA ARCserve Backup to create a new deduplication device. You must provide the FSD Description, FSD Name, Data Path and Index Path. The Group Name is optional; you may specify a valid group name, if desired. If not, the new device is added to a default deduplication group.

FSD Description

Specifies a description for the deduplication device being created.

FSD Name

Specifies the identity name for the deduplication device being created.

Data Path

Specifies the physical path where deduplicated data is stored.

Index Path

Specifies the physical path where the index and reference file data is stored. This path should be on a different volume than the Data Path. If you mistakenly provide the same path as the Data Path, you will not be prompted to specify another path.

Domain Name

Specifies the domain to access the remote deduplication device being created.

User

Specifies the user name to access the remote deduplication being created.

Password

Specifies the user password to access the remote deduplication being created.

-GrpName

Creates a new deduplication device group.

Group Name

Specifies the name of the new deduplication device group created by -GrpName. This is optional. If you do not specify a Group Name, CA ARCserve Backup assigns the deduplication device to new default group.

-removededupefsd <Group Name>

Directs CA ARCserve Backup to remove the deduplication device identified by Group Name.

<Group Name>

Specifies the name of the group containing the deduplication device to be removed.

-configdedupefsd <Group Name> [-FSDDsp<FSD Description>][-FSDName <FSD Name>] [-DataPath <Data Path>] [-IndexPath <IndexPath>]

Directs CA ARCserve Backup to modify an existing deduplication device. You may specify new values for FSD Description, FSD Name, Data Path and Index Path.

-FSDDsp <FSD Description>

Specifies a new description for the deduplication device identified in Group Name.

-FSDname <FSD Name>

Specifies a new identity name for the deduplication device identified in Group Name.

-DataPath <Data Path>

Specifies a new data path that the deduplication device identified in Group Name uses to store deduplicated data.

-IndexPath <Index Path>

Specifies a new index path that the deduplication device identified in Group name uses to store the index and reference files associated with the deduplication process.

Note: The data path and index path only can be changed when the media of the deduplication device is a blank media

-setdedupegrpproperties <Group Name> [[-mstreams <Max Stream>][-mthreshold <Max Threshold <"xx%"|"xx">][-pausemig <Pause Migration <0|1>>][-optimization <Allow Optimization <0|1>>]]

Instructs CA ARCserve Backup to set deduplication group properties for the device identified in <Group Name>.

-mstreams <Max Stream>

Specifies the maximum number of simultaneous data streams sent to the deduplication device.

The default value is 1.

-mthreshold <Max Threshold <"xx%"|"xx">>

Specifies the maximum capacity threshold of the deduplication device. The threshold value can be specified as a percentage of the device's capacity or as an absolute value (in MB only).

The default value is 80%.

-pausemig <Pause Migration <0|1>>

Specifies to pause migration of data from the deduplication device to the final destination media.

0 = Disabled

1 = Enabled

By default, the pause data migration option is disabled.

-optimization <Allow Optimization <0|1>>

Enables or disables optimization in deduplication processes. When you deduplicate data with optimization enabled, only file header data is examined for changes instead of the entire file.

0 = Disabled

1 = Enabled

By default, optimization is disabled.

-getdedupegrpproperties <Group Name>

Directs CA ARCserve Backup to obtain the properties set for the group specified in <Group Name>.

Examples

The following are examples of syntax for the `ca_devmgr` command:

- Use the following command to view adapter information with SCSI IDs and adapter numbers:

```
ca_devmgr -adapterinfo
```

- Use the following command to view tape information (name and serial number) for the specified adapter and SCSI number:

```
ca_devmgr -mediainfo 34
```

- Use the following command to specify an FSD group as a staging group and configured as follows:

- maximum number of streams set to 2
- threshold values set at 80% (maximum) and 60% (minimum)
- chunk size set at 512MB

```
ca_devmgr -setstaging group0 -mstreams 2 -mthreshold "80/60%" -chunksize 512
```

- Use the following command to create a new deduplication device called DDD1 and assign it to a group called DDDGrp1:

```
ca_devmgr -creatededupefsd DedupeDeviceSalesData DDD1 c:\data d:\index -GrpName DDDGrp1
```

- Use the following command to change the data and index paths for an existing deduplication device called DDD0 assigned to a group called DDGrp0:

```
ca_devmgr -configdedupefsd DDGrp0 -FSDName DDD0 -DataPath c:\dataFiles -Index d:\refFiles\
```

- Use the following command to set the deduplication group properties for a group called DDDGrp9 as follows:

- Maximum data streams set to 2
- Maximum Threshold set to 90%
- Pause migration enabled
- Optimization enabled

```
ca_devmgr -setdedupegrpproperties DDDGrp9 -mstreams 2 -mthreshold "90%" -pausemig 1 -optimization 1
```


Chapter 8: ca_jobsecmgr - Job Security Manager Command

If a username or password changes, you must modify every job in the Job Queue to reflect the change. The job security manager command (`ca_jobsecmgr`) allows you to make a global username or password change for all the jobs in the Job Queue. You can make these changes for a specific CA ARCserve Backup server or for all CA ARCserve Backup servers in the current CA ARCserve Backup domain.

Note: To run `ca_jobsecmgr`, you must have equivalency to a CA ARCserve Backup user. In most cases, you can use the user defined password for the CA ARCserve Backup system account. To assign equivalencies, use [ca_auth](#) (see page 25).

Syntax

The `ca_devmgr` command line syntax is formatted as follows:

```
ca_jobsecmgr
    [server arguments]
    <current security>
    <new security>
```

Usage

The `ca_jobsecmgr` command includes the following options and arguments:

- server arguments
- current security
- new security

Server Arguments

The `ca_jobsecmgr` command provides a means to specify whether you want your changes (username and password) to be applied to a specific CA ARCserve Backup server or to all CA ARCserve Backup servers in the current CA ARCserve Backup domain.

The `ca_jobsecmgr` command includes the following server arguments:

Note: You can only use one of the following arguments in a given `ca_jobsecmgr` command.

-s

Use this to change the username or password on a specific CA ARCserve Backup server.

-d

Use this to change the username or password on all servers in the CA ARCserve Backup domain.

Current Security Options

After specifying one of the server arguments, you must provide the current security credentials for the jobs.

The `ca_jobsecmgr` command includes the following current security options:

`ca_jobsecmgr`

`-u`

`-p`

-u

Use this to specify the current source node username used for the jobs in the Job Queue.

To specify a domain user, use the following format:

`Domain\Username`

-p

Use this to specify the current password that was used by the source node user for the jobs in the Job Queue.

New Security Options

After specifying the current username and password, you can then provide new security credentials that you want to apply for the jobs. You can use the new security options to specify a new password and, optionally, a new username.

The `ca_jobsecmgr` command includes the following new security options:

`ca_jobsecmgr`

`-np`

`-nu`

-np

Use this to specify a new password to be used by the source node user for the jobs in the Job Queue.

-nu

Optional. Use this to specify a new source node username to be used for the jobs in the Job Queue.

To specify a domain user, use the following format:

`Domain\user`

Examples

The following are examples of syntax for the `ca_jobsecmgr` command:

- Use the following command to change the username and password on a specific CA ARCserve Backup server:

```
ca_jobsecmgr -s machine1 -u administrator -p xyz -nu administrator2 -np xyz2
```

- Use the following command to change the username and password on all servers in the CA ARCserve Backup domain:

```
ca_jobsecmgr -d -u administrator -p xyz -nu administrator2 -np xyz2
```


Chapter 9: ca_log - Log Command

The log command (`ca_log`) is a utility that allows you to view, purge, clear, and maintain CA ARCserve Backup logs. With `ca_log` you can view the Activity log and the Job logs, both of which are also available from the Job Status Manager.

Syntax

The `ca_log` command line syntax is formatted as follows:

```
ca_log [-cahost <hostname>] [-entiredomain]
```

```
-browse  
-view <logname> [view options]  
-purge <logname> [purge options][-yes]  
-clear <logname>[-yes]  
-help  
-examples
```

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_log` commands include the following options:

- miscellaneous options
- log name manipulation options
- view options
- purge options

Miscellaneous Options

The `ca_log` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during a log generation process.

The `ca_log` command includes the following miscellaneous options:

-cahost <hostname>

Identifies the name of the system hosting the operation.

The switch is a filter. If you want to execute the operation on a specified machine in a domain, this switch must be included in the command. Without this switch, all operations are for the entire domain.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-entiredomain

Limits the searching range to include only logs in the domain, rather than default to the local host for search limits. If `-entiredomain` is not specified, the `ca_log` commands will expand the search to all logs for the specified host.

-usage

Displays a list of basic `ca_log` commands.

-help

Opens the `ca_log` Help topic.

-examples

Opens a Help topic with `ca_log` usage examples.

Log Name Manipulation Options

There are several options you can use for manipulating and viewing log files.

The `ca_log` command includes the following log name manipulation options:

```
ca_log [-cahost <hostname>] [-entiredomain]
      -clear <logname>[-yes]
      -browse
```

-clear <logname> [-yes]

Deletes all logs with the specified log name from the database.

Note: All the information in the database will be lost with this option.

-browse

Lists all the log files on the specified host that can be displayed.

Lists all the log names on the entire domain. If this switch is included with -cahost, it will list all the log names of the specified host.

View Options

There are several options you can use for viewing logs.

The ca_log command includes the following log viewing options:

```
ca_log [-cahost <hostname>][-entiredomain]
```

```
-view <logname>[-<view options>]
```

```
-jobID <ID>
```

```
-groupbyjob
```

```
-before <mm/dd/yyyy>
```

```
-after <mm/dd/yyyy>
```

```
-monitor
```

```
-sev
```

Note: To properly display all Unicode characters in the output of a command, you must first set the environmental variable "ARCSERVE_UNICODE_DISPLAY_CMDL" to a value of 1 prior to running the command as follows:

```
C:\Documents and Settings\cb>set ARCSERVE_UNICODE_DISPLAY_CMDL=1
```

To view these Unicode characters correctly, you will also we need to redirect the output of ca_log after setting the environmental variable as follows:

```
C:\>ca_log-view activity.log >UNICODE_log.txt
```

logname

Displays the logs specified by the log name according to one or several view options.

-jobID <ID>

Displays the specified logs by job ID or job list ID for the activity log.

For example:

- `ca_log -view activity.log -jobID 5`
- `ca_log -view activity.log -jobID 1,2,3` (split by comma)

-groupbyjob

Available only when the filename to be viewed is an activity log. Specifies that the `ca_log -view` command will display logs grouped by job ID first, and then logs for jobs without a job ID. The job logs will also group master jobs and its child jobs logs together before other logs.

Without this switch included, the activity log will be displayed in time order.

With this switch included, the activity log will be displayed and grouped by job.

For example, the output would be as follows:

- Logs of job1 in activity log
- Logs of job2 in activity log ...
- Logs of jobn in activity log
- Logs in activity log without job id.

-before <mm/dd/yyyy>

Displays all entries with the specified log name before date mm/dd/yyyy.

Note: You can use the `-before` and `-after` options together to display logs across a period of time.

-after <mm/dd/yyyy>

Displays all entries with the specified log name after date mm/dd/yyyy.

Note: You can use the `-before` and `-after` options together to display logs across a period of time.

-monitor

Displays logs with the specified log name and keeps it open indefinitely. The log name is updated in real time as additional entries to the log are recorded.

Keeps the `ca_log` command from terminating after displaying the last specified log, and continues to read and display additional logs from the log file as they become available.

-sev

Displays the severity level of each entry with the specified log name. The severity levels are displayed after the date column. The severity levels are:

I - Information

W - Warning

E - Error

Note: The `-sev` option can be used in conjunction with the `-jobID`, `-before`, and `-after` options.

Purge Options

The `ca_log` purge options are used to delete the oldest part of logs based upon age criteria. The `-purge` is a single-time, on-demand command that is initiated at the time the command is issued.

The `ca_log` command includes the following log file purge options:

```
ca_log [-cahost <hostname>][-entiredomain]
```

```
-purge <logname>
```

```
-olderthan num<day[s] | week[s] | months[s] | year[s]>
```

logname

Purges the logs with the specified log name according to the age criteria specified in the `-olderthan` purge option.

-olderthan num <day[s] | week[s] | months[s] | year[s]>

Purges logs older than the specified number of days, weeks, months or years. Based on age criteria, the information with the specified log name will be purged from the database.

Note: The number of days specified should be between 1 and 365.

You need to add the word "day", "week", "month", or "year" as applicable when specifying the purge time period. For example:

```
ca_log -purge <log name> -olderthan 3 day
ca_log -purge <log name> -olderthan 3 week
ca_log -purge <log name> -olderthan 3 month
ca_log -purge <log name> -olderthan 3 year
```

Examples

The following are examples of syntax for the `ca_log` command:

- Use the following command to view the Activity Logs for the entire domain:
`ca_log -entiredomain -view Activity.log`
- Use the following command to view the Activity Log from the specified host:
`ca_log -cahost hostname -view Activity.log`
- Use the following command to view the Activity Logs for the member server:
`ca_log -cahost <member server> -view Activity.log`
- Use the following command to view the Activity Logs for the entire domain, grouped first by the logs of master jobs and their corresponding child jobs, then by other activity logs:
`ca_log -entiredomain -view Activity.log -groupbyjob`
- Use the following command to view the Activity Log for a specified job. If the job is a master job, the output logs will contain not only the master job logs, but also the corresponding child jobs logs.
`ca_log -view jobXXX.log`
- Use the following command to clear the Activity Log from the entire domain:
`ca_log -entiredomain -clear Activity.log`
- Use the following command to clear the Activity Log from the specified host:
`ca_log -cahost hostname -clear Activity.log`
- Use the following command to purge the Activity Log of all entries created between August 2, 2006 and September 2, 2006:
`ca_log filename -purge Activity.log -after 08/02/2006 -before 09/02/2006`
- Use the following command to purge the Activity Log on a specified host of all entries more than four days old:
`ca_log -cahost hostname -purge Activity.log -olderthan 4 days`
- Use the following command to purge logs for Job 8 of all entries more than a day old:
`ca_log -purge Job8.log -olderthan 1 day`

Chapter 10: ca_merge - Merge Manager Command

The merge manager command (`ca_merge`) is the command line interface to the CA ARCserve Backup Merge Manager. Use this command to create and submit merge jobs to the Job Queue. You can merge database information from backup media into your CA ARCserve Backup database. Many of the features available from the Merge Manager are available from the command line.

Syntax

The `ca_merge` command line syntax is formatted as follows:

```
ca_merge
  [-cahost <hostname>]
  <source args>
  <run job args>
  <options>
```

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_merge` commands allow you to set the following options and arguments:

- miscellaneous options
- source arguments
- run job arguments
- merge options
- job status return codes

Miscellaneous Options

The `ca_merge` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during a merge process.

The `ca_merge` command includes the following miscellaneous options:

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: If you include `-cahost` in the command, you must also specify the hostname of the system (local or remote) hosting the operation.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-f [*set the File Name variable*]

Used to specify a file name that contains the switches and parameters for the command.

This switch overcomes the shell limitation of 1024 character input from command line. You can also use this switch to hide passwords by saving them in a file.

usage

Displays a list of basic `ca_merge` commands.

-help

Opens the ca_merge Help topic.

-examples

Opens a Help topic with ca_merge usage examples.

Source Arguments

The ca_merge command source arguments allow you to specify the data to be merged. You can use these arguments to identify the group, tape, and sessions to be used in your merge operation.

The ca_merge command includes the following source arguments:

ca_merge

[-group <group name> -tape <tape name> [<tape ID>]]

[-tape <tape name> [<tape ID>]]

WINDOWS Usage:

[-currenttapeseq][allsessions|-session [<session #>|<session range>]]

UNIX Usage:

[-currenttapeseq][allsessions|-session <session range>]

-group <group name> -tape <tape name> [<tape ID>]

Specify the tape group name to use for the merge job.

If you include -group, then you must also include -tape information.

-tape <tape name> [<tape ID>]

Specify the tape to use for the merge job. The tape ID is optional and is used if there are multiple tapes with the same name.

-currenttapeseq

Specify to use the current tape sequence for the merge job.

-allsessions

Specify to merge all the sessions of the tape for the merge job.

Note: If you select to merge all sessions and the tape set spans to multiple sequences, the sequence number 1 tape has to be present for this operation to complete successfully.

-session [*<session #>* | *<session range>*]

Specify to merge a single session or multiple sessions of the tape. Specify a session range to merge multiple sessions.

Example:

To merge session 27 of a tape named "MYTAPE" use the following command:

```
ca_merge -tape MYTAPE\ -session 27
```

To merge sessions 9 through 24 of a tape named "MYTAPE" use the following command:

```
ca_merge -tape MYTAPE\ -session 9-24
```

Run Job Arguments

The `ca_merge` command provides run job arguments to allow you to specify the run job methods for your merge job. The `ca_merge` run job options allow you to submit the job to be run immediately, or to submit the job on Hold, or to schedule the job for a later date and time. The method you choose determines when your merge jobs are run.

Important! To ensure that all jobs start at the scheduled time, you must synchronize the system time of the Member Servers with the system time of the corresponding Primary Server. Use the Windows Time Service to synchronize the time on all ARCserve servers in your domain.

The `ca_merge` command includes the following run job arguments:

```
ca_merge  
  [-at <hh:mm>]  
  [-on <mm/dd/yy[yy]>]  
  [-hold | -runjobnow]  
  [-description <descriptionstring>]
```

-at <hh:mm >

Specify the execution time of the merge job.

Note: All scheduled times for CA ARCserve Backup jobs are based upon the time zone where the CA ARCserve Backup server is located. If your agent machine is located in a different time zone than the CA ARCserve Backup server, you will need to calculate the equivalent local time that you want the job to be run.

-on <mm/dd/yy[yy]>

Specify the execution date of the merge job.

-hold

Submit the merge job on hold.

Cannot be used with -runjobnow.

-runjobnow

Submit and execute the merge job immediately.

Cannot be used with -hold.

-description <description string>

Add comments to the merge job.

Note: You must use double quotes " " to enclose the string and handle blank spaces.

Merge Options

The `ca_merge` command allows you to specify various merge options that are applied to the job.

The `ca_merge` command includes the following merge options:

```
ca_merge
  [Database Options] (for UNIX host)
  [Decryption Password List Options]
  [Logging Options] (for UNIX use only)
  [Pre/Post Options]
  [Exit Code Options]
  [Media Options]
  [Miscellaneous Merge Options]
  [Job Status Options]
```

Database Options

Note: This option is for UNIX use only.

The `ca_merge` command includes the following database options:

```
ca_merge
  [-partialdbupdate]
```

-partialdbupdate

Record only Job and Session information into the CA ARCserve Backup database.

Decryption Password List Options

The `ca_merge` command includes the following decryption password list options:

`ca_merge`

`[decryptionpwdlist <password 1> [<password 2>] [<password 3>] ... [password 8>]`

[decryptionpwdlist <password 1> [<password 2>] [<password 3>] ... [<password 8>]

Provides a list of decryption passwords to be used if the sessions are encrypted. If a merge job contains multiple sessions with different passwords, CA ARCserve Backup will not stop for each session and ask for a password. Instead, the specified decryption passwords will be packaged as a combined list and the list will automatically be checked as each encrypted session is merged.

If the required password is supplied as part of the decryption password list, the job will continue without any further user input. If the required session password is not supplied as part of the decryption password list, you will be prompted to provide one prior to allowing that encrypted session to continue.

A maximum of eight passwords can be included in the decryption password list, with each password separated by a space. Each password can have a maximum of 23 characters and cannot contain any spaces or commas.

Logging Options

Note: This option is for UNIX use only.

The `ca_merge` command includes the following logging options:

`ca_merge`

`[-logfile [set the File Name variable] [summary | allactivity]]
[-snmp] [-tng] [-email <email address>] [-printer <printer name>]`

-logfile [set the File Name variable] [summary | allactivity]

Records activities during the running of the merge job to the specified filename. You can specify to record all activity or just a summary of the activity.

-snmp

Enables SNMP (Simple Network Management Protocol) alert.

-tng

Enables Unicenter Network and Systems Management (NSM) alert (formerly known as TNG).

-email <email address>

Sends a copy of the Activity log to the specified email address.

-printer <printer name>

Sends a copy of the Activity log to the specified printer.

The printer must be set up in the configuration file
ARCServe_HOME/config/calloggerd.cfg

Pre/Post Options

The ca_merge command includes the following pre/post options:

ca_merge

[-preexec <command>]

[-preexectimeout <minutes>]

[-postexec <command>]

[-prepostuser <user name>]

[-prepostpassword <user password>]

-preexec <command>

Runs the specified command before the job starts.

The entire path of the command should be included.

Note: To use this option you must also specify the -prepostuser option.

-preexectimeout <minutes>

The time to wait, in minutes, before the merge job starts, to allow time for the pre-execute command to finish.

-postexec <command>

Runs the specified command after the job finishes.

The entire path of the command should be included.

Note: To use this option you must also specify the -prepostuser option.

-prepostuser <user name>

The user name of the user submitting this merge job.

-prepostpassword <user password>

The password of the user submitting this merge job.

Exit Code Options

The `ca_merge` command includes the following exit code options:

```
ca_merge  
    [-exitcode <exit code1>]  
    [-skip_delay|-skip_job]  
    [-skip_post]
```

-exitcode <exit code1>

Specifies the exit code of the pre-execute command.

Used with the `-skip_delay`, `-skip_job`, and `-skip_post` switches.

Note: The skip delay, skip job, and skip post options will only be activated if CA ARCserve Backup detects that the returned exit codes meet the selected condition (Equal To, Greater Than, Less Than, or Not Equal to).

-skip_delay

Runs the merge job immediately if the specified exit code is received.

-skip_job

Skips the merge job completely if the specified exit code is received.

-skip_post

Skips the post-execute command if the specified exit code is received.

Media Options

The `ca_merge` command includes the following media options:

```
ca_merge  
    [-firsttapetimeout <minutes>]  
    [-spantapetimeout <minutes>]
```

-firsttapetimeout <minutes>

Specifies the time (in minutes) to wait for a usable media to be made available for the merge job. If a usable media is not made available within this specified time period, the job will time out and fail.

Default: 5 minutes

-spantapetimeout <minutes>

Specifies the time (in minutes) to wait for a usable span media to be made available for the merge job. If a usable media is not loaded within this specified time period, the job will time out and fail.

If the infinite value is specified, the job continues to wait and prompt until a usable media is loaded or the user cancels the job.

Default: Infinite

Miscellaneous Merge Options

The `ca_merge` command includes the following miscellaneous merge options:

`ca_merge`

`[-list]`

(for UNIX use only)

`[-savescript <scriptname>]`

-list

Used to display a list of tapes available for the merge job.

-savescript <script name>

Instead of submitting this job to the job queue, the merge job is saved as a script that can be loaded into the job queue later.

Note: This option is for UNIX use only.

Job Status Options

The `ca_merge` command includes the following job status options:

`ca_merge`

`[-waitForJobStatus [<polling interval (secs)>]]`

-waitForJobStatus [<polling interval (secs)>]

The `ca_merge` command will wait until the job is completed, and then exit with a [return code](#) (see page 166) that indicates the success or fail outcome of the job.

The `<polling interval>` value defines how often (in seconds) the `ca_merge` utility checks the job status with the Queue services. The default polling interval is 60 seconds.

Return Codes

The following codes are returned by the `ca_merge` command:

Return Codes:

- **0** – Command executed successfully.
- **-1** – An error occurred while executing a command.

Examples

The following are examples of syntax for the `ca_merge` command:

Specify the machine on which the source being merged is located

- Use the following command to specify that the source machine for the merge is by default the localhost:

```
ca_merge -tape TAPE01
```

- Use the following command to specify that the source machine for the merge is hostA:

```
ca_merge -cahost hostA -tape TAPE01
```

Confine the range of the source

- Use the following command to merge all sessions of tapes belonging to a group of localhost:

```
ca_merge -group <group name> -tape <tape name> [<tape ID>]
```

- Use the following command to merge all sessions of tape TAPE01 on hostA:

```
ca_merge -cahost hostA -tape TAPE01
```

- Use the following command to merge all sessions of tape TAPE01 with tapeid B5E3 on hostA:

```
ca_merge -tape TAPE01 B5E3
```

- Use the following commands to merge a specified session range:

```
ca_merge -cahost hostA -tape TAPE01 -allsessions
```

```
ca_merge -cahost hostA -tape TAPE01 -session 6
```

```
ca_merge -tape TAPE02 -session 2-8
```

Confine the time at which the merge job will run

- Use the following command to specify the time of the current day that the merge will be performed:

```
ca_merge -cahost hostB -tape TAPE03 -session 6-9 at 11:20
```

- Use the following command to specify the time and date that the merge will be performed:

```
ca_merge -cahost hostB -tape TAPE03 -session 6-9 -at 11:20 -on 03/25/2007
```

- Use the following command to submit the merge job on hold:

```
ca_merge -cahost hostB -tape TAPE03 -session 6-9 -hold
```

- Use the following command to specify run job now

```
ca_merge -cahost hostB -tape TAPE03 -session 6-9 -runjobnow
```

Wait for Job Status

- Use the following command to query the job status at a specified polling interval (secs) until the job is finished.

```
ca_merge -cahost hostB -tape TAPE03 -session 6-9 -runjobnow -waitforjobstatus 60
```


Chapter 11: ca_mmo - Media Management Administrator Command

The media management administrator command (ca_mmo) is the command line interface to the CA ARCserve Backup Media Management Administrator (MMO Admin) from the command prompt. This command is used to control and monitor vaulting operations and reports. Many of the features available from the Media Management Administrator are available from the command line.

Note: To enable this feature, the CA ARCserve Backup Enterprise Module must be installed.

Syntax

The `ca_mmo` command line syntax is formatted as follows:

`ca_mmo`

[vault cycle options]

-start [-alert] [-export] [-jid]
-startall [-alert] [-export] [-jid]

[vault status reset options]

-reset

[mmo database options]

-init

[vaulted media options]

-checkin -tapename <Tape name>
-tapeid <Tape id #>
-seqnum <Tape seq #>
-type <Check in type>

-checkin -serialnum <Tape serial #>
-type <Check in type>
Check in types: temp | manual | manualretire

[vault assignment options]

-assign -tapename <Tape name>
-tape id <Tape id #>
-seqnum <Tape seq #>
-vaultname <Vault Name>

-assign -serialnum <Tape serial #>
-vaultname <Vault Name>

[print report options]

-printreport <Print type>
Print types: VaultSelection | Shipping | ShippingContent | Receiving | ReceivingContent |
InventoryByMedia | InventoryByVault

[vault export options]

-export
-exportall

Options

The `ca_mmo` command provides options to establish vaulting policy and manage your media resources. Using the Media Management Administrator (MM Admin), you can organize tape movement to off-site storage locations, define retention policies to ensure that your tapes are protected from being prematurely overwritten, secure access to tape-resident files, and maintain a comprehensive inventory of tape library resources.

The `ca_mmo` command includes the following options:

-start [-alert] [-export]

Starts a vault cycle on a member server or a primary server.

If you use only the `-start` command and the output has vaulted tapes that need to be sent to an offsite vault, you must export these tapes out of the changer manually. If you do not want to export tapes manually, use the `-export` command.

When you use the `-export` command, MM Admin automatically exports all of the local vaulted tapes to the mailslots of the changer so that you do not have to export them manually. If there are more vaulted tapes to export than mailslots, MM Admin waits for the Administrator to empty the mailslots so it can continue exporting the remaining tapes.

If you want to receive a notification when mailslots need to be emptied, use the `-alert` option. After the notification occurs, MM Admin waits a maximum of 24 hours for the mailslots to be emptied.

-startAll [-alert] [-exportAll]

Starts a vault cycle in a SAN or on the primary or member servers.

Use the `-exportAll` switch with `-startAll` if you want to start a vault cycle in a SAN and export all of the local tapes and tapes in the SAN.

-export

Exports all tapes locally.

This option is usually used independently if it is not used with the `-start` or `-startAll` options. This is useful if you do not want to export every time you run a vault cycle.

-exportAll

Exports all of the local tapes and all of the tapes in the SAN or on the primary or member servers.

This option is usually used independently if it is not used with the `-start` or `-startAll` options. This is useful if you do not want to export every time you run a vault cycle.

-jid

Specifies the Job ID.

-reset

Resets the vault status.

-init

Initializes the MM Admin database.

-checkin -tapename <Tape name> -tapeid <Tape id #> -seqnum <Tape seq #> -type <Check in type>

Checks media back into Tape Service using the tape name, ID, and sequence number.

Check in type can be temporary <temp>, manually <manual>, or permanently (manual and retire) <manualretire>.

-checkin -serialnum <Tape serial #> -type <Check in type>

Checks media back into Tape Service using its serial number.

Check in type can be temporary <temp>, manually <manual>, or permanently (manual and retire) <manualretire>.

-assign -tapename <Tape name> -tapeid <Tape id #> -seqnum <Tape seq #> - vaultname <Vault Name>

Assigns media into a vault using the tape name, ID, and sequence number.

When selecting a Vault Criteria Descriptor (VCD), if you selected the Assign by User option as the controlling data set, you must use either this command or the - assign -serialnum command to assign a specific tape.

-assign -serialnum <Tape serial #> - vaultname <Vault Name>

Assigns media into a vault using its serial number.

When selecting a Vault Criteria Descriptor (VCD), if you selected the Assign by User option as the controlling data set, you must use either this command or the -assign -tapename command to assign a specific tape.

-printreport <Print type>

Prints a report.

Depending on which type of report you want to print, enter VaultSelection, Shipping, ShippingContent, Receiving, ReceivingContent, InventoryByMedia, InventoryByVault for <Print type>.

-usage

Displays a list of basic ca_mmo commands.

Examples

The following are examples of syntax for the `ca_mmo` command:

- Use the following syntax to export all tapes locally:

```
ca_mmo-export
```

- Use the following syntax to export all of the local tapes and all of the tapes in the SAN:

```
ca_mmo-exportAll
```

- Use the following syntax to start the vault cycle and then export all of the local tapes:

```
ca_mmo-start [-startall[-alert] [-export] [-jid]
```

- Use the following syntax to start the vault cycle in the SAN and then export all of the local tapes and tapes in the SAN:

```
ca_mmo-startAll-exportAll
```


Chapter 12: ca_qmgr - Queue Manager Command

The queue manager command (`ca_qmgr`) is the command line interface with the Job Status Manager and allows you to monitor and control jobs submitted to the CA ARCserve Backup Job Queue. These job management commands are used for obtaining information or manipulating jobs in the job queue. All of the features available from the Job Status and Activity Log Manager are available from the command line.

Syntax

The `ca_qmgr` command line syntax is formatted as follows:

```
ca_qmgr [-cahost <hostname>] [-entiredomain]
  -list [<job #> [jobid][jobtype][jobstatus][exechost][execdate][exec time][asresult][owner][description]]
  -listscripts
  -load <job script> [<script owner>]
  -addscript <job script>
  -removescript <job script> [<script owner>]
  -changestatus <job #> <ready|hold>
  -changedate <job #> <mm/dd/yy|yy>
  -changetime <job #> <hh:mm>
  -stop <job #>
  -view <job #>
  -delete <job #>
  -waitForJobStatus <job #> [-polling interval <secs>]
  -move <s_server <source primary server>> <d_server <dest primary server>> [-m_server <member
server>] [-jobnum <<job #>>] [-hold]
  -changeSessionPassw d <job number> [<old passw ord> <new password>]
  -usage
  -help
  -examples
```

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_qmgr` commands allow you to set the following options and commands:

- miscellaneous options
- job queue commands
- job script commands
- job specific commands

Miscellaneous Options

The `ca_qmgr` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use for jobs submitted to the job queue.

The `ca_qmgr` command includes the following miscellaneous options:

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: The [-cahost <hostname>] switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the -cahost switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the -cahost switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that -cahost be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-entiredomain

Limits the searching range to include only jobs in the domain, rather than default to the local host for search limits. If -entiredomain is not specified, the `ca_qmgr` commands will expand the search to all jobs in the job queue for the specified host.

-usage

Displays a list of basic ca_qmgr commands.

-help

Opens the ca_qmgr Help topic.

-examples

Opens a Help topic with ca_qmgr usage examples.

Job Queue Commands

The ca_qmgr command contains job queue commands that allow you to view and control the Job Queue.

The ca_qmgr command includes the following job queue commands:

```
ca_qmgr [-cahost <hostname> [-entiredomain]] -list
    [<job #>
        [jobid]
        [jobtype]
        [jobstatus]
        [exechost]
        [execdate]
        [exectime]
        [lastresult]
        [owner]
        [description]]
```

-list

Shows current job queue and the member server of where the job is scheduled to run.

job #

Lists all jobs in the job queue for the specified job number. If the job number is not specified, the -list command will list all jobs on the specified host. You can also add subordinate options to specify various job-related information to be displayed for the specified job.

jobid

Includes the job id for the specified jobs.

jobtype

Includes the job type for the specified jobs.

jobstatus

Includes the job status for the specified jobs.

exechost

Includes the execute host for the specified jobs.

execdate

Includes the execute date for the specified jobs.

exectime

Includes the execute time for the specified jobs.

lastresult

Includes the last result for the specified jobs.

owner

Includes the owner for the specified jobs.

description

Includes the description for the specified jobs.

Job Specific Commands

The `ca_qmgr` command contains job specific commands that allow you to monitor and control individual jobs.

The `ca_qmgr` command includes the following job specific commands:

```
ca_qmgr [-cahost <hostname>] [-entiredomain]
  -changestatus <job #> <ready|hold>
  -changedate <job #> <mm/dd/yy[yy]>
  -changetime <job #> <hh:mm>
  -stop <job #>
  -view <job #>
  -delete <job #>
  -waitForJobStatus <job #> [-polling interval <secs>]
  -move <s_server <source primary server>> <d_server <dest primary server>> [-m_server <member
server>] [-jobnum <job #>] [-hold]
  -changeSessionPassword <job number> [-old password <new password>]
```

-changestatus <job #> <ready|hold>

Changes the job status to ready, or puts a job on hold.

Example:

```
ca_qmgr -changestatus 12 hold
```

-changedate <job # mm / dd / yy[yy]>

Changes the date a job will run.

Example:

```
ca_qmgr -changedate 12 04/01/2006
```

-changetime <job # hh:mm >

Changes the time a job will run.

Example:

```
ca_qmgr -changetime 12 12:08
```

Note: All scheduled times for CA ARCserve Backup jobs are based upon the time zone where the CA ARCserve Backup server is located. If your agent machine is located in a different time zone than the CA ARCserve Backup server, you will need to calculate the equivalent local time that you want the job to be run.

-changeSessionPasswd <job number> [<old password> <new password>]

Changes the session password for the specified backup job with the status of ready, hold, or done. You can execute this command using either of two formats:

- You can include this switch and specify the old and new session passwords all in one line:

```
ca_qmgr-changeSessionPasswd5AAA BBB
```

- You include this switch but do not include an old or new password and you will be prompted for each password.

```
ca_qmgr-changeSessionPasswd5
```

```
Please enter old passw ord:
```

```
Please enter new passw ord:
```

```
Please reconfirm new passw ord:
```

job number

Specifies the job number of the backup job that you want to change the session password.

old password

Specifies the old session password that will be replaced for the backup job. This parameter is optional; however, if it is included you must also include the new password.

new password

Specifies the new session password that will be applied to the backup job. This parameter is optional; however, it cannot remain empty if you include the old password.

Notes:

- If the backup job has no previous session password, you cannot add a new session password.
- If the old password provided and the original session password for the specified job do not match, this command will fail.
- If you include the old session password, but do not include a new session password, this command will fail (the new session password cannot be empty).
- The maximum length of the session password is 23 characters.

-stop <job ID>

Stops a currently running job. If it is a repeating job, the next job in the sequence is queued. If it is a run-once job, the job is stopped and deleted. If it is a job on hold, no action is taken.

Example:

```
ca_qmgr-stop 12
```

Important! No confirmation is asked prior to stopping the job. The job is stopped without asking if you are sure.

-view <job ID>

Views details of job ID (Job Summary)

Example:

```
ca_qmgr-view 12
```

-delete <job ID>

Deletes an inactive job. Deleting an inactive job completely removes it from the job queue.

Example:

```
ca_qmgr-delete 12
```

Note: To delete an active job, you must first stop the job before you can delete it.

-waitForJobStatus <job #> [<polling interval <secs>>]

The ca_qmgr command will wait until the job is completed, and then returns to prompt. The optional polling interval indicates the time to poll for the job status internally.

The <polling interval> value defines how often (in seconds) the ca_qmgr utility checks the job status with the Queue services. The default polling interval is 60 seconds.

-move <-s_server <source primary server>> <-d_server <dest primary server>> [-m_server <member server>] [-jobnum <job #>] [-hold]

Moves the job from one server to another. If you include this command, you must specify a source server and a destination server. In addition, you can also include subordinate options to further define the job to be moved. If you do not include any subordinate options, all jobs on the source primary servers will be moved to the destination primary server by default.

-s_server <source primary server>

Specifies the source primary server where the job will be moved from. You must include the name of the source primary server.

-d_server <dest primary server>

Specifies the destination primary server where the job will be moved to. You must include the name of the destination primary server.

-m_server <member server>

Specifies the host where the moving job will be executed from. If you include this option, you must specify the member server.

-jobnum <job #>

Specifies the job number that will be moved. If you include this option, you must specify a job number on the source primary server.

-hold

If the option is included, specifies that the jobs being moved on the source primary server will be modified to a Hold status after they have been successfully moved, instead of the default action of Deleted.

Job Script Commands

The `ca_qmgr` command contains job script commands that allow you to control and use the job scripts.

The `ca_qmgr` command includes the following job script commands:

```
ca_qmgr [-cahost <hostname>] [-entiredomain]
        -listscripts
        -load <job script> [<script owner>]
        -addscript <job script>
        -removescript <job script> [<script owner>]
```

-listscripts

Shows available job scripts (in ARCServe_HOME/jobscripts).

A job script is a saved job file that has a .asx extension. Any job can be saved as a job script from the CA ARCserve Backup Manager GUI.

Example:

```
ca_qmgr -listscripts
```

-load <job script> [<script owner>]

Loads and runs a previously saved job script.

To load a script, the script must be present in the CA ARCserve Backup home directory.

Example:

```
ca_qmgr -load myscript caroot
```

Note: X.asx can only be loaded on the Primary Server. If you run ca_qmgr -load X.asx on a Member Server, you will receive an error.

-addscript <job script>

Imports and registers a job script.

Specify a path along with the job script file name. The job script file is copied to the CA ARCserve Backup home directory from the given path.

Example:

```
ca_qmgr -addscript C:\myscript.asx
```

-removescript <job script> [<script owner>]

Removes and de-registers a job script.

The job script file is deleted from the CA ARCserve Backup home directory.

Example:

```
ca_qmgr -removescript myscriptcaroot
```

Examples

The following are examples of syntax for the `ca_qmgr` command:

- Use the following syntax to display the current job queue:

```
ca_qmgr-list
```

- Use the following syntax to display all jobs on the domain:

```
ca_qmgr-list-entiredomain
```

- Use the following syntax to stop a currently running job (in this example, Job 5):

```
ca_qmgr-stop 5
```

- Use the following syntax to delete a job (in this example, Job 5):

```
ca_qmgr-delete 5
```

- Use the following syntax to display available job scripts:

```
ca_qmgr-listscripts
```

- Use the following syntax to import and register a job script from a given path:

```
ca_qmgr-addscript C:\bkpjob1.asx
```

- Use the following syntax to load a run a saved job script:

```
ca_qmgr-load bkpjob1
```


Chapter 13: ca_recoverdb - Database Recovery Command

Each time you run a backup job, CA ARCserve Backup records information in its databases about the machines, directories, and files that have been backed up, and the media that was used. This allows you to locate files whenever you need to restore them. The database recovery command (`ca_recoverdb`) is a self-protection feature that allows you to recover a CA ARCserve Backup database if it is lost and was backed up by the CA ARCserve Backup domain that is using the database.

Note: The `ca_recoverdb` utility invokes the `ca_restore` commands to implement the database recovery function. The `ca_recoverdb` utility will automatically determine if the CA ARCserve Backup database is a SQL Server database or SQL Server 2005 Express Edition instance and provide the appropriate parameters for the `ca_restore` command.

Note: When a CA ARCserve Backup server is configured as cluster-aware, all critical ARCserve base-related services (not agent-related services) will be monitored by the applicable cluster service (MSCS or NEC CLUSTERPRO). If an ARCserve base-related service fails or needs to be shut down, the cluster service will automatically try to restart it or trigger a failover if the restart attempt fails. To run this task, you must stop ARCserve services. However, in a cluster-aware environment, you must first manually stop the cluster service from continuing to monitor the service and attempting an automatic restart or failover. For procedures to stop HA service monitoring by the Cluster Service, see the Administration Guide.

Note: The `ca_recoverdb` utility is only used to recover an ARCserve Database (ASDB) on the same machine or ARCserve domain on which that ASDB backup was taken. If you want to backup an ASDB on one machine and then recover it on another machine (the two machines are not in the same ARCserve domain), this command can not be used. In this situation, you have two solutions:

Solution 1:

1. Take a DR backup from machine A and then recover it on machine B.
This solution needs DR option installed.

Solution 2:

1. Install CA ARCserve Backup on both machine A and machine B.
2. Perform an ASDB backup on machine A.
3. Move the tape to machine B, and submit a merge job to merge the information of the tape into the CA ARCserve Backup on machine B.
4. On machine B, open Restore Manager (Restore by Tree option) and locate the "CA ARCserve Backup Database".
5. Right click the "CA ARCserve Backup Database" and on the popup menu, choose "Agent Options".
6. From the Agents Restore Options dialog, select the following options:
 - Force restore over existing files or database
 - Use current ARCserve Database as original location
 - Preserve current ARCserve Domain Memberships
7. Submit the restore job.

Syntax

The `ca_recoverdb` command line syntax is formatted as follows:

```
ca_recoverdb [-cahost <hostname> ]  
  
[-i [n]]  
-username <username> [-passwd <password>]  
[-dbusername <database username> [-dbpasswd <database passwd> ] ] [-sessionpasswd [session  
passwd] -session passwd [session passwd]...]  
[-waitforjobstatus <polling interval>]
```

Options

The `ca_recoverdb` provides various options for recovering a lost CA ARCserve Backup database.

The `ca_recoverdb` command includes the following options:

cahost <hostname>

Redirects default host from the backup log to the host specified by `cahost`.

For example:

HostA - The default host that existed in backup log, which will be used in `ca_restore`.

HostB - The host that you specify.

In these examples, if you do not specify the `cahost` switch, then the `ca_restore` command invoked by the `ca_recoverdb` utility will look as follows:

```
ca_restore -cahost HostA
```

If you do specify the `cahost` switch with the parameter HostB, then the `ca_restore` command invoked by the `ca_recoverdb` utility will look as follows:

```
ca_restore -cahost HostB
```

-i [n]

Specifies to use the interactive mode. If you include this switch, it allows you to specify a point in time from which to perform the CA ARCserve Backup database recovery by selecting which backup to use as a baseline. When the interactive mode is invoked, the `ca_recoverdb` displays the list of CA ARCserve Backup sequences for which it has log files. Each of the log files start with a Full database backup, and contains all of the other backups which are dependent on that Full backup to be restored (the Full backup is root of the "dependency chain" for those sessions).

The parameter *n* is used to specify the number of latest backup log sets (dependency chains) that you want to select from. The range of values for *n* is 1 to 99, and the default value is 10.

When you select a Full backup sequence, you will then be prompted to select which session to use as the restore point. After you select a session, the `ca_recoverdb` utility will determine the dependency chain for that sequence, and use `ca_restore` to submit a restore job for each session.

If you do not include the `-i` switch, the `ca_recoverdb` utility automatically uses the most recent backup as the specified selection, and builds the dependency chain for that session. This is helpful if you just want to recover to the latest point in time backup. However, if the most recent backup is lost or damaged, you can use the interactive mode to restore from an older session, and then merge tapes to re-integrate the latest information.

-username <username> [-password <password>]

Specifies the authenticating information for the database agent that will perform the actual recovery job. If you do not include the password option, it will default to no password required.

-dbusername <database username> [-dbpassword <database password>]

Specifies the authenticating information for the database. If you do not include the database username and corresponding database password, it will default to "dbusername" and "dbpassword" for authenticating purposes.

[-sessionpassword [session password] -sessionpassword [session password] ...]

Specifies the authenticating information for the sessions being set authenticating password.

[-waitForJobStatus <polling interval>]

Specifies the time interval (in seconds) that `ca_recoverdb` will wait until the job is completed and then exit with a return code that indicates the success or fail outcome of the job.

The <polling interval> value defines how often (in seconds) that the `ca_recoverdb` utility checks the job status with the Queue services. The default polling interval is 60 seconds.

Examples

The following are examples of syntax for the `ca-recoverdb` command:

- Use the following syntax to recover an ASDB if the ASDB is hosted on a primary server:

```
ca_recoverdb.exe -username Administrator -passwordwin_pwd
```

- Use the following syntax to recover an ASDB if an ASDB session is encrypted or password protected:

```
ca_recoverdb.exe -username Administrator -passwordwin_pwd -sessionpasswordses_pwd
```

- Use the following syntax to recover an ASDB if an external ASDB server and SQL Authentication is used:

```
ca_recoverydb.exe -cahost machinename -username Administrator -passwordwin_pwd -dbusername db_username -dbpassword db_password
```

Chapter 14: ca_restore - Restore Manager Command

The restore manager command (`ca_restore`), the command line interface to the Restore Manager, allows you to create and submit restore jobs to the CA ARCserve Backup Job Queue, and to set all associated options. All of the features available from the Restore Manager are available from the command line. The options and switches for the `ca_restore` command allow you to set global options and filters, select your source and destination for the restore job, and submit the restore job to run immediately or at a scheduled time.

Syntax

The `ca_restore` command line syntax is formatted as follows:

```
ca_restore [-cahost <hostname>]
           [global options]
           [global filters]
           -source [source arguments]
           -dest [destination arguments]
           [run job arguments]
           [info arguments]
```

Note: The `[-cahost <hostname>]` switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the `-cahost` switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_restore` commands allow you to set the following options and arguments:

- miscellaneous options
- restore options
- filter arguments
- source arguments
- destination arguments
- run job arguments
- info arguments
- return codes

To build a restore operation, you must set one category of options at a time, in the order specified in the `ca_restore` syntax.

Miscellaneous Options

The `ca_restore` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during a restore process.

The `ca_restore` command includes the following miscellaneous options:

`ca_restore`

```
[-cahost <hostname>][info args]
[-f [set the File Name variable]]
[-sessionpassword <session password/encryption key>]
[-waitForJobStatus [-polling interval (secs)>]]
[-help]
[-examples]
[-usage]
[allusage]
```

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: The [-cahost <hostname>] switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the -cahost switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the -cahost switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that -cahost be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-f [set the File Name variable]

Used to specify a file name that contains the switches and parameters for the command.

This switch overcomes the shell limitation of 1024 character input from command line. You can also use this switch to hide passwords by saving them in a file.

-sessionpassword <session password/encryption key>

Specifies that a session/encryption password will be required in order to restore this data from media. To restore data from one of these sessions, the password must have been provided during backup.

-waitForJobStatus [<polling interval (secs)>]

When specified, the ca_restore command will wait until the job is completed, and exit with a return code that indicates the success or fail outcome of the job.

The <polling interval> value defines how often (in seconds) that the ca_restore utility checks the job status with the Queue services. The default polling interval is 60 seconds.

-help

Opens the ca_restore Help topic.

-examples

Opens a Help topic with ca_restore usage examples.

-usage

Displays a list of basic ca_restore commands.

allusage

Displays a list of all ca_restore commands and their switches.

Global Job Options

The ca_restore global options allow you to specify various options that are applied to the entire job.

The ca_restore command provides the following global options:

- media options
- destination options
- operation options
- pre/post options
- log options
- virus options

Restore Media Options

The ca_restore command includes the following global media options:

ca_restore

```
[-firsttapetimeout <minutes<1-9999>>]  
[-spantapetimeout <minutes<1-9999>>]  
[-optimizerestoreoff]
```

-firsttapetimeout <minutes>

Specify the time (in minutes) to wait for a usable media to be made available for the restore job. If a usable media is not made available within this specified time period, the job will time out and fail.

Default: 5 minutes

-spantapetimeout <minutes>

Specify the time (in minutes) to wait for a usable span media to be made available for the restore job. If a usable media is not loaded within this specified time period, the job will time out and fail.

If the infinite value is specified, the job continues to wait and prompt until a usable media is loaded or the user cancels the job.

Default: Infinite

-optimizerestoreoff

Disables the optimize restore option.

If, during a restore operation, CA ARCserve Backup discovers duplicate backup sessions, where one session resides on tape media and another session resides on a file system device, CA ARCserve Backup will by default restore the data from the session that resides on the file system device.

Under most circumstances, restoring data from a file system device is faster than restoring from tape media. However, you may want to disable the optimize restore option if you are using tape media or a library with high-speed reading capabilities, or if there is a known problem with your file system device. If you want to disable the optimize restore option, you would need to include this switch in the `ca_restore` command.

Destination Options

The `ca_restore` command includes the following global destination options:

`ca_restore`

```
[-nobase|-base|-entirepath]
[-onconflict <overwrite|rename|skip|overwriteold>]
[-createversion|-replaceversion|-restoreversion]
```

-nobase

Specifies not to create the base directory on the destination path, but instead create all subdirectories below the source base directory during restore. This is the default option.

-base

Creates the destination path from the base directory during restore.

-entirepath

Creates the entire source path on the destination. No files from any parent directories are restored. Only the directory path to the base directory is created on the destination.

-onconflict <overwrite|rename|skip|overwriteold|confirm>

Specifies the method that CA ARCserve Backup will use when there are files on the destination disk that have the same name as files being copied from the source.

overwrite

Specifies to overwrite and restore all source files to the destination regardless of conflicting file names. The files from the source will overwrite the existing files on the destination.

This is the default option.

rename

Specifies to rename and copy the source file to the destination with the same file name but a different extension. The format of the renamed extension will vary depending upon the file system that is present on the target partition.

skip

Specifies to skip and not restore a source file if a file with the same name already exists on the destination.

overwriteold

Specifies to overwrite with newer files and only restore source files whose modification date is later than the modification date of the file with the same name on the destination. Source files whose modification date is earlier are not copied to the destination.

-createversion

Specifies to create a new file version. CA ARCserve Backup will restore all files as new versions of the original. The files in the target directory will not be affected.

-replaceversion

Specifies to replace (overwrite) a file version if a file in the target directory has the same name and version number as a file in the restore data.

-restoreversion

Specifies to restore (not overwrite) a file version if a file in the target directory has the same name and version number as a file in the restore data, CA ARCserve Backup will not restore the file. All other files will be restored with their original names and version numbers.

Operation Options

The `ca_restore` command includes the following global operation options:

`ca_restore`

```
[createemptydiroff]
[restorereregistry]
[preservefileattroff]
[-nodbupdate [-stopdb [-restartdb]] [-partialdbupdate]
[-preserveuserspaceoff]
[-preservedirspaceoff]
```

-createemptydiroff

Turns off (disables) the Restore and Preserve Directory Attributes and Security Information option.

Specifies to not create an empty directory, but instead restore the existing directory attributes (such as Read Only, Archive and Hidden) and security data to the machine.

If the client agent is a Windows client agent, CA ARCserve Backup will restore and preserve the directory attributes and security information. If the client agent is a UNIX client agent, CA ARCserve Backup will create empty directories.

-restorereregistry

Turns on (enables) the Restore Registry Files and Event Logs option.

Specifies to restore the registry files and event logs to the restore target machine if the sessions selected for restore have the registry files and event log files.

-preservefileattroff

Turns off (disables) the Restore and Preserve File Attributes and Security Information option.

Specifies to restore the existing file attributes (such as Read Only, Archive and Hidden) and security data to the machine.

-nodbupdate [-stopdb [-restartdb]]

Turns off (disables) the Database Recording option.

Specifies not to keep a record of this job in the CA ARCserve Backup database.

-stopdb

Stops the database engine before a restore.

-restartdb

Restarts the database engine after a restore.

-partialdbupdate

Turns on (enables) the Record Job Information Only option.

Specifies to keep a record of this job in the CA ARCserve Backup database.

-preserveuserspaceoff

Disables the Preserve User Space Restrictions option. Does not restore the user space restrictions along with the files.

By default, the preserve user space option is applied and the same user space restrictions assigned during the backup will also be applied during the restore.

Note: This option is only applicable when files or sessions will be restored to a machines running the Client Agent for NetWare.

-preservedirspaceoff

Disables the Preserve Directory Space Restrictions option. Does not restore the directory space restrictions along with the files.

By default, the preserve directory space option is applied and the same directory space restrictions assigned during the backup will also be applied during the restore.

Note: This option is only applicable when files or sessions will be restored to machines running the Client Agent for NetWare.

Pre/Post Options

The `ca_restore` command includes the following global pre/post options:

`ca_restore`

```
[preexec <command>]
[exitcode <exit code(>=0)>[-skip_delay|-skip_job][-skip_post]]
[preexec timeout <minutes(0-32767)>]
[postexec <command>]
[skippostfail]
[skippostincmp]
[skippostcmp]
[prepostuser <user name>]
[prepostpassword <user password>]
```

-preexec <command>

Runs the specified command before the job starts. The entire path of the command should be included.

Note: To use this option, you must also specify the `-prepostpassword` option. If you do not specify the `-prepostpassword` option, the job will fail.

-exitcode <exit code(>=0)> [-skip_delay|-skip_job] [-skip_post]

Specifies the exit code of the pre-execute command. Used with the `-skip_delay`, `-skip_job`, and `-skip_post` switches.

-skip_delay

Runs the restore job immediately if the specified exit code is received.

-skip_job

Skips the restore job completely if the specified exit code is received.

-skip_post

Skips the post-execute command if the specified exit code is received.

-skippostfail

Specifies to not run the post command if the job fails.

-skippostincmp

Specifies to not run the post command if the job is incomplete.

-skippostcmp

Specifies to not run the post command if the job is complete.

-preexectimeout <minutes(0-32767)>

Specifies the time to wait (in minutes), before the restore job starts, to allow time for the pre-execute command to finish. The range of time to specify is from 0 to 32767 minutes.

Default: 0 minutes

-postexec <command>

Runs the specified command after the job finishes. The entire path of the command should be included.

Note: To use this option, you must also specify the `-prepostpassword` option. If you do not specify the `-prepostpassword` option, the job will fail.

-prepostuser <username>

Specifies the name of the user who is submitting this restore job.

-prepostpassword <user password>

Specifies the password of the user who is submitting this restore job.

Log Options

The `ca_restore` command includes the following global log options:

`ca_restore`

`[-logfile <allactivity|summary|disabled|errorsonly>]`

-logfile <allactivity | summary | disabled | errorsonly>

Records activities during the running of the restore job in the Job Log. You must specify one of the subordinate options to control the information being recorded.

allactivity

Logs all activities that occur while the job is running.

summary

Logs only summary information such as source, destination, session number, totals, and errors.

disabled

Log is disabled and does not record any information about the job.

errorsonly

Logs only errors that occur while the job is running.

Default: Summary without consolidate.

Virus Options

The `ca_restore` command includes the following global virus options:

`ca_restore`

`[-virus <skip|delete|rename|cure> [-virus_scanarchive]]`

-virus

Enables automatic scanning for viruses during the restore operation. You must also include one of the virus scanning subordinate options.

Skip

Does not restore the infected file.

Rename

Renames the infected files with the extension AVB. If a file with the same name and the extension AVB exists, then the extension AV0 is used, followed by AV1, AV2, and so on.

Delete

Deletes the infected file.

Cure

Attempts to cure the infected file.

-virus_scanarchive

Checks each file in compressed archives individually. Selecting this option might affect the performance of the restore but provides increased virus protection.

Global Filter Options

Using filters you can include or exclude specific files and directories from your restore jobs. Use the filters to help focus on the files you want. Filters can be applied globally (to the entire job), at the node level (to a specific node), or at the volume level. The position of the `-filter` switch in the `ca_restore` command determines the filter level applied.

Important! Incorrect use of filters could result in data being omitted during the restore. Use care when specifying or applying filters!

Note: CA ARCserve Backup accepts the wildcard characters asterisk `*` and question mark `?` for include and exclude filtering. The asterisk wildcard specifies to match any number of characters and the question mark wildcard specifies to match any one character.

The `ca_restore` command includes the following filter options:

```
ca_restore [-filter  
            [<include|exclude> <file|dir> <pattern>]  
            [<include|exclude> [<attribute> [hidden] [readonly] [system] [archive]]]  
            [<include|exclude> [<date> <modify|create|access> <on|before|on|after> <mm/dd/yy|yy>]]  
            [<include|exclude> [<date> <modify|create|access> <between> <mm/dd/yy|yy> <mm/dd/yy|yy>]]  
            [<include|exclude> [<date> <modify|create|access> <within> <count> <days|months|years>]]  
            [<include|exclude> [<size> <equalto|greaterthan|lessthan> <size val> <Bytes|KBytes|MBytes|GBytes>]]  
            [<include|exclude> [<size between> <<low size val> <Bytes|KBytes|MBytes|GBytes>> <<high size val>  
            <Bytes|KBytes|MBytes|GBytes>]]
```

include

Results will contain only those files that satisfy the filter specifications. For example, if you select to restore your entire local hard drive, and then set up a filter to include files in the `\SYSTEM` directory, the result would be that CA ARCserve Backup would only restore files from your `\SYSTEM` directory. No other files would be restored.

exclude

Exclusions always take precedence over inclusions. For example, if you add a filter to include files that have an `.exe` extension, and add another filter to exclude your `\SYSTEM` directory, then all the `.exe` files in the `\SYSTEM` directory would be excluded.

file | dir <pattern>

Specifies to include or exclude files or directories based on the specified pattern.

Note: If you select the include directory pattern filter and do not specify an absolute path, the empty directories for all the directories that do not match the user provided criteria will be restored. To avoid creating these empty directories during restore, disable the global restore option Create Empty Directories when creating your restore job.

attribute

Specifies to include or exclude files with the specified file attribute.

Hidden

Files that are not shown in a directory listing. For example, IO.SYS is a hidden file.

Read Only

Files that cannot be modified.

System

Files that are unique to the machine you are using.

Archive

Files whose archive bit is set.

**date <modify|create|access> <onorbefore |onorafter>
<mm/dd/yy[yy]>**

Specifies to include or exclude files that were modified, changed, or accessed on or before the specified date, or on or after the specified date.

**date <modify|create|access> <between <mm/dd/yy[yy]>
<mm/dd/yy[yy]>>**

Specifies to include or exclude files that were modified, changed, or accessed between the specified dates.

**date <modify|create|access> <within <count>
<days|months|years>>**

Specifies to include or exclude files that were last modified, changed, or accessed within the specified number of days, months, or years.

**size <equalto|greaterthan|lessthan> <size val>
<Bytes|KBytes|MBytes|GBytes>**

Specifies to include or exclude files whose size is equal, greater or less than the specified size.

**size between <<low size val> <Bytes|KBytes|MBytes|GBytes>>
<<high size val> <Bytes|KBytes|MBytes|GBytes>>**

Specifies to include or exclude files whose size is within the specified size range.

Note: For the Global Filter options, the following conditions exist:

- For UNIX servers, CA ARCserve Backup will automatically interpret the "-create" command as specifying the File Change date.
- Modified Time is different than Change Time. Modified Time means the content of a file has changed. Change Time means some properties or attributes of the file has changed (permission changes, owner information, etc), but not the content.
- Not all file systems record change or access dates, therefore some of these Global filters may not be available for your job.

Source Arguments

The `ca_restore` command line utility provides various methods to view the source information. Which method you choose depends on what you know about the files you want to restore and the media you will need to use.

- **Restore by Tree view:**
`-source [-group] [-filter]`
- **Restore by Session view:**
`-source -tape -session [-group] [-tapesession] [-filter]`
- **Restore by Media view (no database):**
`-tape -session [-group] [-tapesessionpw] [-filter]`

The `ca_restore` command line utility supports the following source arguments:

`ca_restore`

```
-source [<hostname> [<hostIP>]]<filelist>  
-tape <tapename> [<tapeID>]  
-session <session no>  
-group <groupname>  
-tapesessionpw <password/encryption key>
```

-source [*<hostname>* [*<hostIP>*]]*<filelist>*

Specifies the files/directories to restore.

If the `-source` switch is used alone, without `-tape` and `-session`, the restore is treated as a Restore by Tree view, and CA ARCserve Backup determines the version of the file to restore.

For example, if a file has been backed up several times, each time to a different session or even a different tape, and the user wants to restore it, but does not specify a tape or session, CA ARCserve Backup finds the most recent backup, and restores this file.

Examples:

To restore the most recent backup of `</myfiles>` use the following:

```
ca_restore -source /myfiles
```

To restore `/myfiles` that was backed up to session 24 on tape MYTAPE use the following:

```
ca_restore -source /myfiles -tape MYTAPE -session 24
```

-tape *<tapename>* [*<tapeID>*]

Specifies the tape to use for the restore job. The tape ID is optional, and is used if there are multiple tapes with the same name.

If the `-tape` switch is used with the `-source` switch, the restore is treated as a Restore by Session view, and the CA ARCserve Backup database is used in the restore. CA ARCserve Backup checks if it has a record of the file and tape specified for the restore. If not, the restore job is not submitted, even if all of the information provided is actually correct. This tape and session must be merged into the CA ARCserve Backup database before this restore job can be submitted.

If the `-tape` switch is not used with the `-source` switch, the restore is treated as a Restore by Media view, and the CA ARCserve Backup database is not used. If the tape name or session number provided are invalid, the restore job fails at run-time.

The `-tape` switch must be used with the `-session` switch.

-session *<session no>*

Specifies the tape session number to use for the restore job.

This switch must be used with the `-tape` switch.

-group *<group name>*

Specifies the tape group to use for the restore job.

-tapesessionpw *<session password/encryption key>*

Specifies the session password or encryption key needed to restore data from tape. Required only if a session password or encryption key was applied during the backup job.

Destination Arguments

The `ca_restore` command line utility supports the following destination arguments:

`ca_restore -dest`

`<hostname> <hosttype> <path> [-username <username> -password <password>]`

`<hostname> <orglocation>`

`<hostname> <hosttype> [-username <username> -password <password>] -database <dbase type> <dbase name> [dbase options]`

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

-dest [*<hostname>* *<hosttype>*] *<path>* [-username *<username>* -password *<password>*]

Specifies the destination machine and directory path to restore files to. The hostname is optional, and if not provided, the hostname defaults to the local machine.

If the hostname is provided, the hosttype is mandatory. Available hosttypes are: `unix`, `nt`, `nwagent`, `ntagent`, `w95agent`, and `mac`.

You must provide a user name and password to connect to the target agent, and you can restore to a remote location only if a CA ARCserve Backup Agent is running on the remote machine.

Examples:

To restore session two files from tape MYTAPE to `"/restoreDir"` on the local machine, use the following:

```
ca_restore -tape MYTAPE -session 2 -dest "/restoreDir"
```

To restore session 2 files from tape MYTAPE to `"/restoreDir"` on remote machine RMACHINE, use the following:

```
ca_restore -tape MYTAPE -session 2 -dest RMACHINE "/restoreDir"
```

-username *<user name>*

Specifies the user name of the destination machine to restore to. This is the user used to log into the desired machine.

Note: You must specify a `-username` if you use the `ca_restore -source` option or if you use `ca_restore` on a 64-bit machine.

-password <password>

Specifies the password for the user to use when logging into the destination machine.

Note: You must specify a `-username` if you use the `ca_restore -source` option or if you use `ca_restore` on a 64-bit machine.

-orglocation

Specifies that you want to restore your files to their original location of the backup (machine and path).

Database Options

When you select a database object to be restored, you can set certain database-specific options to be applied and display database-related information.

The `ca_restore` command includes the following database options:

`ca_restore`

```
[-dbusername <database username>]
[-dbpassword <database password>]
-database <database type> [database name]
```

```
[Oracle Database Options]
[Oracle RMAN Database Options]
[Exchange DOC Level Database Options]
[SQL Server Database Options]
[Sybase Agent Database Options]
[INFORMIX Agent Database Options]
[VSS Agent Database Options]
[LOTUS Agent Database Options]
```

-dbusername <database username>

Specify the database user name to use to log into the database to be restored.

-dbpassword <database password>

Specify the password for the database user to use to log into the database to be restored.

-database <dbase type> [dbase name]

Specifies the database type and name to restore to.

Supported, valid database types are:

- SQL Server (SQL)
- Exchange DOC Level (EXCHANGEDOC)
- Exchange DB Level (EXCHANGEDB)
- Sybase (SYBASE)
- Informix (INFORMIX)
- Oracle (ORACLE)
- Oracle RMAN (ORACLERMAN)
- Lotus (LOTUS)

Examples:

```
-database SQL  
-database EXCHANGEDOC  
-database EXCHANGEDB  
-database SYBASE  
-database INFORMIX  
-database ORACLE  
-database ORACLERMAN  
-database LOTUS
```

Note: If the Oracle instance name and the database name are different, the -database options should be "-database ORACLERMAN [instance name@database name]" instead of "-database ORACLERMAN [database name]".

Oracle Database Options

The `ca_restore` command includes the following Oracle database options:

`ca_restore`

`[-oracle_controlfile]` (for UNIX Oracle agent only)
`[-oracle_overwritelog]` (for UNIX Oracle agent only)
`[-oracle_multistream]` (for UNIX Oracle agent only)
`[-oracle_recover]` (for UNIX Oracle agent only)

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

Note: When using the CA ARCserve Backup CLI (command line interface) to back up or restore an Oracle object with a DBCS (double-byte character set) or a MBCS (multi-byte character set) in the name, you must ensure the CA ARCserve Backup server and the agent box have the same language setting.

-oracle_controlfile

Specifies that the control file should be restored. (for UNIX Oracle agent only)

-oracle_overwritelog

Specifies to overwrite existing logs during the restore. (for UNIX Oracle agent only)

-oracle_multistream

Specifies to restore Oracle using multiple streams. (for UNIX Oracle agent only)

-oracle_recover

Specifies to take a restored copy of the datafile and apply to it any changes that were recorded in the database redo logs. To recover a whole database is to perform recovery on each of its datafiles. (for UNIX Oracle agent only)

Examples:

The following are examples of syntax for the `ca_restore` ORACLE database command:

- Use the following command to restore a single tablespace (SYSAUX):

```
ca_restore -source [<hostname> [<hostIP>]] "dbora7@instance\DIRECT_ONLINE\2007_07_16-06:31
[40]SYSAUX" -dest [<hostname>] <-orglocation> -database ORACLE[<database name>] [<database options>]

ca_restore -source [<hostname> [<hostIP>]] "dbora7@instance\OFFLINE\2007_07_17-08:20
[44]SYSAUX" -dest [<hostname>] <-orglocation> -database ORACLE[<database name>] [<database options>]
```

- Use the following command to restore multiple tablespaces (SYSAUX and USERS):

```
ca_restore -source [<hostname> [<hostIP>]] " dbora7@instance\DIRECT_ONLINE\2007_07_16-06:31  
[40]\SYSAUX" " dbora7@instance\DIRECT_ONLINE\2007_07_16-06:31 [40]\USERS" -dest [<hostname>]  
<orglocation> -database ORACLE [dbase name] [dbase options]
```

- Use the following command to restore a control file:

```
ca_restore -source [<hostname> [<hostIP>]] " dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30  
[37]\CONTROL FILE" -dest [<hostname>] <orglocation> -database ORACLE [dbase name] [dbase options]
```

- Use the following command to restore an archive log:

```
ca_restore -source [<hostname> [<hostIP>]] " dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30  
[37]\ARCHIVE LOG" -dest [<hostname>] <orglocation> -database ORACLE [dbase name] [dbase options]
```

- Use the following command to restore a full database. Assume the database has 5 tablespaces (tbs1, tbs2, tbs3, tbs4, and tbs5) to restore the full database, and you want to restore all tablespaces, the archive log, and the control file:

```
ca_restore -source [<hostname> [<hostIP>]] " dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30  
[37]\tbs1" " dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30 [37]\tbs2" "  
dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30 [37]\tbs3" "  
dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30 [37]\tbs4" "  
dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30 [37]\tbs5" "  
dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30 [37]\ARCHIVE LOG" "  
dbora7@instance\DIRECT_ONLINE\2007_07_16-06:30 [37]\CONTROL FILE" -dest [<hostname>]  
<orglocation> -database <dbase type> [dbase name] [dbase options]
```

Oracle RMAN Database Options

The `ca_restore` command includes the following Oracle RMAN database options:

```
ca_restore [-use_rmancat -rman_cuser <RMAN Catalog User> -rman_catpassword <RMAN Catalog Password>]
ca_restore [-put_online]
ca_restore [-oracle_controlfile]
ca_restore [-listbackup]
ca_restore [-rman_archlogsel

    al_all |
    al_pattern [-rman_alpattern <Archive Log Pattern>] |
    al_time [-rman_alfromtime <Archive Log From Time>] [-rman_aluntiltime <Archive Log Until Time>] |
    al_scn [-rman_alfromscn <Archive Log From SCN>] [-rman_aluntilscn <Archive Log Until SCN>] |
    al_logseq [-rman_alfromlogseq <Archive Log From Sequence>] [-rman_aluntillogseq <Archive Log Until
    Sequence>] [-rman_althread <Archive Log Number of Threads>] |
    al_none]
ca_restore [-rman_script <RMAN Script>]
ca_restore [-rman_numberofchannels <Number of Channels>]
ca_restore [-rman_blocksize <Block Size (Bytes)>]
ca_restore [-rman_backupsetnum <Validate Backup Set Number>]
ca_restore [-rman_restoremethod

    rm_lastbackup |
    rm_time [-rman_restoretime <Restore From Backup Made On (Date/Time)>] |
    rm_tag -rman_backuptag <RMAN Backup Tag> ]
ca_restore [-rman_recoverytype

    rec_norec |
    rec_untilendoflogs |
    rec_untilscn [-rman_recoveruntilscn <Until SCN>] |
    rec_untillogseq [-rman_recoveruntilseq <Until Log Sequence>] [-rman_recthread <Recovery Thread
    Number>] |
    rec_untiltime [-rman_recoveruntiltime <Until Time>]]
```

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

Note: When using the CA ARCserve Backup CLI (command line interface) to back up or restore an Oracle object with a DBCS (double-byte character set) or a MBCS (multi-byte character set) in the name, you must ensure the CA ARCserve Backup server and the agent box have the same language setting.

Note: If the Oracle instance name and the database name are different, the `-database` options should be "`-database ORACLERMAN [instance name@database name]`" instead of "`-database ORACLERMAN [database name]`".

-use_rmancat

Specifies to use a catalog (recommended). Indicates if an RMAN catalog is to be used for the operation or not. It is always recommended to use one because RMAN will use the database control file if no catalog is to be used. The loss of this control file will prevent RMAN from restoring the database.

-rman_catuser <rman_catuser>

Specifies the name of the Oracle user who owns the RMAN catalog.

-rman_catpassword <rman_catpassword>

Specifies the password for that user that owns the RMAN catalog.

-put_online

Specifies to RMAN that the Oracle objects restored should be put online after the recovery is performed.

-oracle_controlfile

Specifies that the control file should be restored.

-listbakset

Specifies to list all backup sets that include the objects selected in the source node.

-rman_archlogsel

The "Archived Logs Selection" section of this panel allows the user to select which archived logs will be restored, assuming that the "archived logs" object has been included in the Source panel of the Restore Manager GUI. The selection is represented by radio button options. All indicates that all archived logs will be backed up.

Default: All

-rman_alpattern <rman_alpattern>

String pattern used to select the archived logs based on their name.

-rman_alfromtime <rman_alfromtime>

Use this option to indicate that the archived logs to be restored will be selected based on the time they were created. This field determines the lower time boundary for the archived logs selection. Only the archived logs created after this time will be restored.

-rman_aluntiltime <rman_aluntiltime>

Use this option to indicate that the archived logs to be restored will be selected based on the time they were created. This field determines the upper time boundary for the archived logs selection. Only the archived logs created before this time will be restored.

-rman_alfromscn <rman_alfromscn>

Use this option to indicate that the range of the archived logs to be restored is not determined by the time, rather by the SCN (System Change Number). This field indicates the lowest SCN boundary for the archived logs selection. It can be left empty, assuming that the Until SCN field is not.

-rman_aluntilscn <rman_aluntilscn>

Use this option to indicate that the range of the archived logs to be restored is not determined by the time, rather by the SCN (System Change Number). This field is used to determine the upper SCN boundary to the archived logs selection. It is optional, as long as the user has entered a value for the From SCN field.

-rman_alfromlogseq <rman_alfromlogseq>

Use this option to specify that archived logs selection is to be based on the archived log sequence number. This field corresponds to the lowest log sequence number used to determine which archived logs will be restored. This field can be left empty only if a value is provided for the Until Log Sequence one.

-rman_aluntillogseq <rman_aluntillogseq>

Use this option to indicate that the archived logs selection is to be based on the archived log sequence number. This field is used to enter the upper archived log sequence number boundary for the archived logs selection. Providing a value for this field is optional, as long as the user enters a value in the From Log Sequence field.

-rman_althread <rman_althread>

Use this option to specify the thread number used to identify the Oracle server that generated the archived logs. This parameter is only used with the Time Based, SCN Based or Log Sequence Based options described below. It will be ignored if the All or Pattern Based option is used.

Default: 1

Note: This value is only useful for OPS (Oracle Parallel Server, for Oracle 8 and 8i) or RAC (Real Application Clusters, for Oracle 9i and 10g), otherwise the thread number is always one.

-rman_script <rman_script>

Use this option to enter the path of an RMAN script. Providing a value for this field will cause the Oracle agent to ignore all other options that might have been entered by the user in the GUI. The script will be passed as is to RMAN and the Oracle agent will perform the restore operation normally.

-rman_numberofchannels <rman_numberofchannels>

Use this option to specify how many channels to be allocated by RMAN to perform the restore operation. RMAN will submit jobs in parallel, one for each channel.

Default: 1 channel

-rman_blocksize <rman_blocksize>

Use this option to specify a value that determines the size of the data blocks that RMAN will send to the Oracle agent when performing a restore. This field should be left empty by default. If the user enters a value for it during backup, then the same block size must also be entered by the user when he wants to restore. Otherwise, RMAN will produce an error message indicating that there is a mismatch between the backup block size and the restore one. In that case, the value used during the backup will be put in the error message. If no value is provided, then RMAN uses 64 KB for Oracle 8 or 8i and 256 KB for Oracle 9i.

This parameter does not exist anymore with Oracle 10g.

Default: Empty

-rman_baksetnum

Specifies to make sure that the copy of the data on the tape is valid and could be restored, if necessary. RMAN will not actually restore the data from this command.

The backup set number required can be obtained by connecting to RMAN in its environment and issuing the 'list backupset' command. The backup set number can also be obtained from the results of executing the -listbakset option in ca_restore command and view the available backup set information.

-rman_restoremethod

Specifies to perform a data restore based on the method to be performed.

rm_lastbackup

Specifies that RMAN should attempt to restore the data from the latest backup.

rm_time [-rman_restoretime <Restore From Backup Made On (Date/Time)>]

Specifies which sets RMAN will use to get the data from, based on the specified date and time.

rm_tag -rman_baktag <RMan Backup Tag>

Specifies that RMAN should attempt to restore the data according to the specified Tag. If you specified a backup Tag during the actual backup, you can then restore the data using Tag name.

-rman_recoverytype

Specifies to perform a data recovery based on the type of recovery to be performed.

rec_norec

The switch indicates that no recovery should be performed by RMAN after the data has been restored.

rec_untilendoflogs

Specifies to RMAN to recover the data as close as possible to the present time, until the end of the current logs.

rec_untilscn [-rman_recoveruntilscn <Until SCN>]

Specifies to RMAN to perform the recovery until the specified System Change Number (SCN) value.

rec_untillogseq [-rman_recoveruntilseq <Until Log Sequence>]

Specifies to perform the recovery on the entire database up to the point in time represented by the specified archived log sequence. This is the archived log that indicates where the recovery process will stop.

[-rman_recthread <Recovery Thread Number>] |

Specifies to perform the recovery of the entire database up to the point in time represented by the specifies recovery thread number. This value is used in an OPS or RAC environment to identify the Oracle server that generated the archived logs.

rec_untiltime [-rman_recoveruntiltime <Until Time>]

Specifies to perform the recovery of the entire database up to the specified point in time.

Exchange DOC Level Database Options

The `ca_restore` command includes the following Exchange DOC Level database options:

```
ca_restore -source <hostname> <absolute path of the exchaneg doc file> -username <username> -password <password>
-database EXCHANGEDOC <dbase name> [Exchange DOC options]
```

Exchange database options:

```
[-exsis_createmailbox
[-exsis_createuser <password>]
[-exsis_overwrite|-exsis_overwritemodified |-exsis_copyrestore|-exsis_copyrestoremodified]]
```

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

-exsis_createmailbox

Specifies to create a mailbox if it does not exist.

-exsis_createuser <password>

Specifies to create a user if it does not exist. If this switch is included, you must also include the default password for this user.

-exsis_overwrite

Specifies to overwrite the file being restored.

-exsis_overwritemodified

Specifies to overwrite the file being restored only when it has been modified.

-exsis_copyrestore

Specifies to restore the file as a copy (do not overwrite).

-exsis_copyrestoremodified

Specifies to restore as a copy only when the file has been modified.

Exchange DB Level Database Options

The `ca_restore` command includes the following Exchange DB Level database options:

```
ca_restore -source <hostname> <storage group name > -dest [<hostname>] [-username <username> -password
<password>]
-database EXCHANGEDB <dbase name> [Exchange DB options]
```

Exchange DB options:

```
[-exdb_dismountdb]
[-exdb_allow_db_overwritten -exdb_rest_orig_sg|-exdb_rest_recovery_sg|-exdb_rest_create_sg]]
[-exdb_lastset]
[-exdb_apply_logs]
[-exdb_mount_db]
[-exdb_wait_for_db_commit]
[-exdb_temp_location]
```

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

-exdb_dismountdb

Specifies to automatically dismount the database before the restore.

-exdb_allow_db_overwritten

Specifies to allow the database to be overwritten by the restore.

-exdb_rest_orig_sg

Specifies to restore the database to the original storage group.

-exdb_rest_recovery_sg

Specifies to restore the database to a recovery storage group if it exists.

-exdb_rest_create_sg

Specifies to create a recovery storage group if does not exist.

-exdb_lastset

Specifies to commit the database after the restore is completed. If you are restoring a set, use this switch only when you are restoring the last backup in the set. If this switch is not included, the database is left in an intermediate state and is not yet usable but is ready for subsequent differential or incremental restores.

-exdb_apply_logs

Specifies to commit after restore and apply logs.

-exdb_mount_db

Specifies to commit after restore and mount the database after restore.

-exdb_wait_for_db_commit

Specifies to commit after restore and wait for the database to commit.

-exdb_temp_location

Specifies a temporary location for the log and patch files.

SQL Server Database Options

The `ca_restore` command includes the following SQL Server database options:

```
ca_restore -source -tape -session [-group] [-tapesessionpw]
-dest [<hostname>] [-username <username> -password <password>]
-database SQL <Instance name> [SQL Server agent options]
```

SQL Server agent options:

```
[-sql_filegroup <filegroupname>][-partial_restore] | [[-sql_file [set the File Name variable]]..[-sql_file [set the File Name variable]]] | [-autorepair_online] | [-autorepair_offline][force_replace_exist]
```

```
[-sql_stopat [-time <timestamp>]-at_mark <markname> [-after <timestamp>]-before_mark <markname>
[-after <timestamp>]]
```

```
[-sql_db_op | -sql_db_noop | -sql_db_readonly <undo_filename>]
```

```
[-sql_dbcc <sql_after|sql_before> [-physical_only] [-no_indexes]]
```

```
[-sql_restrict_access]
```

```
[-sql_keep_replication]
```

```
[-sql_move_rule [[db]][fg <filegroup name>][drive <drive name>][path <path>]...]
```

```
[-sql_move_rule [file <filegroup name> <file name>][drive <drive name>][path <path name>][name <file name>]...[-location <target location>]]
```

```
[-sql_move_rule [sql_transactionlog [drive <drive name>][path <path name>]...]
```

```
[-sql_move_rule [sql_transactionlog <logfile name>][drive <drive name>][path <path name>][name <file name>]...[-location <target location>]]
```

```
[-sql_auto_off]
```

```
[-sql_forcenp]
```

```
[-sql_continue_after_checksum_failed]
```

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

-sql_filegroup <filegroupname>

Specifies the filegroups in the session to be restored.

-sql_file [set the File Name variable]

Specifies the files in the session to be restored.

-partial_restore

Specifies to perform a Partial Restore.

-autorepair_online

Specifies to automatically repair damaged pages in the data files and leaves the database in an online state.

Note: Applies to SQL2005 only.

-autorepair_offline

Specifies to automatically repair damaged pages in data files and leaves the database in an offline state.

Note: Applies to SQL2005 only.

-force_replace_exist

Specifies to perform a Force Restore over existing files.

-sql_stopat

Specifies to restore the database to the state it was in at a specified event (time or mark).

-time <timestamp>

Specifies to recover the database to the specified date and time. Microsoft SQL Server restores the record in each transaction log backup containing the start and finish time of the backup and then searches this record for the time you have specified.

This is the default option.

-at_mark <markname>

Specifies to stop the recovery at the specified mark. This option will recover the database to the specified log mark, including the transaction that contains the mark. If you do not include the -after option, the recovery will stop at the first mark with the specified name. If you include the -after option, the recovery will stop at the first mark with the specified name exactly at or after the date and time.

Mark names apply to log marks, which are specific to transaction logs and do not apply to files/file group restores.

-before _mark <markname>

Specifies to stop the recovery before log mark. This option will recover the database to the specified mark, but does not include the transaction that contains the mark. If you do not include the -after option, the recovery will stop at the first mark with the specified name. If you do include the -after option, the recovery will stop at the first mark with the specified name exactly at or after the date and time.

Mark names apply to log marks, which are specific to transaction logs and do not apply to files/file group restores.

-after <timestamp>

Specifies to stop the recovery after the specified date and time mark. The recovery stops at the specified mark only when the timestamp for the log mark is later than the specified time.

Use this option with the -at_mark or -before_mark options.

-sql_db_op

Specifies to leave the database operational and no additional transaction logs can be restored. This option instructs the restore operation to roll back any uncommitted transactions. After the recovery process, the database is ready for use and additional restores can be performed.

-sql_db_noop

Specifies to leave the database nonoperational, but able to restore additional transaction logs: This option instructs the restore operation not to roll back any uncommitted transactions. You must choose either this option or the leave database read-only option to apply another differential backup or Transaction log.

-sql_db_readonly [<undo_filename>]

Specifies to leave the database in a read-only mode and able to restore additional transaction logs.

Undo Filenames are for restores that leave the database in a read-only state.

-sql_dbcc

Specifies to perform a database consistency check (DBCC).

sql_after

Specifies to perform a DBCC after the restore of the database.

sql_before

Specifies to perform a DBCC before the restore of the database.

-physical_only

Specifies to check only the physical consistency of the database to verify the structural integrity of all the objects in the database.

-no_indexes

Specifies to check the database for consistency without checking indexes for user-defined tables.

-sql_restrict_access

Specifies to restrict user access to a newly restored database to members of the db_owner, dbcreator, or sysadmin roles.

-sql_keep_replication

Specifies to preserve the replication settings when restoring a published database to a server other than the one on which it was created.

-sql_move_rule

Specifies to move the database.

sql_move_rule [db]

Specifies that the move rules will be applied to the entire database.

-sql_move_rule [fg <filegroupname>]

Specifies that the move rules will be applied to the files in the specified filegroup.

-sql_move_rule [file <filegroupname> [set the File Name variable]]

Specifies that the move rules will be applied to the specified file.

-sql_transactionlog [<log_filename>]

Specifies that the move rules will be applied to the transactionlog filegroup. If the <log_filename> is specified, the move rules will be applied to the specified log file.

-drive <drive_name>

Specifies the target drive for the moved files.

-path <path_name>

Specifies the target path for moved files, such as:

sqlserver\restoreddata.

-name <file_name>

Specifies the target file name for specified moved file.

-location <target location>

Specifies the target location for the specified moved file. The value of the <target location> parameter should include the drive name, path name, and file name, such as:

c:\sqlserver\restoreddata\log.ldf.

-sql_auto_off

Specifies to turn off the automatic session dependency selection and allow manual selection of the restore options.

The automatic selection option automatically selects:

- Other sessions that must be restored with the restore job to be successful.
- Appropriate options for the restore job.

The automatic selection option is the default option for every restore job

-sql_forcenp

Specifies to use named pipes protocol.

Note: Applies to SQL2000 and prior versions only.

-sql_continue_after_checksum_failed

Specifies to continue with the restore job after a checksum failure.

Note: Applies to SQL2005 only.

Sybase Agent Database Options

The `ca_restore` command includes the following Sybase agent database options:

```
ca_restore [-database SYBASE -dbusername <dbusername> -dbpassword <dbpassword>]
```

The Sybase agent does not have any specific database options for restore.

Informix Agent Database Options

The `ca_restore` command includes the following Informix agent database options:

```
ca_restore [-database INFORMIX <instance> [-ifmx_method <both|physical|logical>]]
```

```
ca_restore [-database INFORMIX <instance> [-ifmx_lastlog <number (0-16959)> | -ifmx_time <time  
[MM/dd/yyyy,HH:mm:ss | yyyy-MM-dd,HH:mm:ss]>]]
```

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

-ifmx_method <both|physical|logical>

Specifies the restore method.

both

Specifies to use both the Physical and Logical restore methods and restore all dbspaces, blobspaces, and logical logs.

physical

Specifies to use only the Physical restore method and restore all dbspaces and blobspaces.

logical

Specifies to use only the Logical restore method and restore logs only.

-ifmx_lastlog <number (0-16959)>

Specifies the number of the last log to be restored. If any logs exist after this one, they will not be restored.

-ifmx_time <time [MM/dd/yyyy,HH:mm:ss | yyyy-MM-dd,HH:mm:ss]>

Specifies the point in time at which to stop the restore.

VSS Agent Database Options

The `ca_restore` command includes the following VSS agent database options:

```
ca_restore -source <vss_path>
```

```
    -dest [-vss [-vss_auth]]
```

-vss

Specifies to restore your data from a VSS backup.

-vss_auth

For a VSS restore, this option forces the restored copy to become the "authoritative" version. This means that, even if the restored replica set is older than the current replicas, the older data will be replicated to all of its replication partners. Authoritative restore is typically used to restore a system to a previously known state or if an administrator has accidentally deleted objects and that change has been replicated to all of the domain controllers. If the administrator is able to recreate these objects easily, then this should be chosen over an Authoritative Restore. An Authoritative Restore will not overwrite new objects that have been created after the backup was taken.

This option is only applicable if the VSS Writer supports Authoritative Restore, like the DFS (Distributed File System) Replication Service writer. If the writer does not support Authoritative Restore, this option will take no effect.

By default, CA ARCserve Backup uses the non-authoritative method.

Lotus Agent Database Options

The `ca_restore` command includes the following Lotus agent database options:

```
ca_restore [-database LOTUS <instance>] [-lotus_recovery [-lotus_pointintime <mm/dd/yyyy> <hh:mm:ss>]]  
-dbusername <dbusername> -dbpassword <dbpassword>
```

Note: The `ca_restore` database options are described in a separate topic titled "Database Options" and can be viewed from the actual CLI by entering the following command: `ca_restore allusage`.

-lotus_recovery

Recovers the database to the current date and time (latest recovery).

-lotus_pointintime <mm/dd/yyyy> <hh:mm:ss>

Recovers the database up to the specified point in time (date and time). Recovery is the process of applying database changes that occurred after the database was backed up. The recovery returns the database to a more recent state. Point-in-time recovery gives you further flexibility by allowing you to bring the state of the database to a particular point in time.

Run Job Arguments

The `ca_restore` command provides run job arguments to allow you to specify the run job methods for your restore job. The `ca_restore` run job options allow you to submit the job to be run immediately, or to submit the job on Hold, or to schedule the job for a later date and time. The method you choose determines when your restore jobs are run.

Important! To ensure that all jobs start at the scheduled time, you must synchronize the system time of the Member Servers with the system time of the corresponding Primary Server. Use the Windows Time Service to synchronize the time on all ARCserve servers in your domain.

The `ca_restore` command line utility supports the following run job arguments:

`ca_restore`

```
[-at <hh:mm>]
[-on <mm/dd/yy[yy]>]
[-hold|-runjobnow]
[-description <descriptionstring>]
```

-at <hh:mm>

Specifies the execution time of the restore job.

Note: All scheduled times for CA ARCserve Backup jobs are based upon the time zone where the CA ARCserve Backup server is located. If your agent machine is located in a different time zone than the CA ARCserve Backup server, you will need to calculate the equivalent local time that you want the job to be run.

-on <mm /dd/yy[yy]>

Specifies the execution date of the restore job.

-hold

Submits the restore job on hold.

Cannot be used with `-runjobnow`.

-runjobnow

Submits and execute the restore job immediately.

Cannot be used with `-hold`.

-description <description string>

Adds comments to the job. You must use double quotes " " to enclose the string and handle blank spaces.

Info Arguments

The `ca_restore` command line utility supports the following info arguments:

`ca_restore`

```
-listgroups  
-listtapes  
-listsessions <tapename>[<tapeID>]  
-version [<hostname>] <path>  
-findfile [set the File Name variable] <ignorecase|casesensitive> <<hostname>|any> <search path>  
-inclsudir|noinclsudir <<mm/dd/yy|yy>|today> <within #> <days|months|years>
```

-listgroups

Specifies to display a list of groups available for the restore job.

-listtapes

Specifies to display a list of tapes available for the restore job.

-listsessions <tapename> [<tapeID>]

Specifies to display a list of tape sessions that have been backed up to the specified tape and are available for restore.

-version [<hostname>] <path>

Specifies to display a version history of the specified file/directory that has been backed up. The host name is optional and defaults to the local machine if not provided.

**-findfile [set the File Name variable] <ignorecase|casesensitive>
<<hostname>|any> <search path> <inclsubdir|noinclsubdir>
<<mm/dd/yy[yy]>|today> <<within #> <days|months|years>>**

Determines whether a file has been backed up by searching the Recover Management Backup database.

You must specify the file name, and indicate whether the name is case-sensitive or not, the host name (or any if any host name applies), the path to search for the file (use "/" to search at the top-most level), and whether or not to include sub directories during the search.

You must also specify the time period for the file you are searching for. This time period is based upon a start time point and an end time point. The end time point is the date the file was created (not the date of the backup), and is represented by <<mm/dd/yy[yy]>|today>. The start time point is the number days, months, or years back from the end point to search from and is represented by <<within #> <days/months/years>>.

For example:

- To find all the backed up files that were created between 03/11/2007 and 03/15/2007.

The format is 03/15/2007 within 4 days.

- To find all the backed up files that were created between 03/11/2007 and 04/11/2007.

The format is 04/11/2007 within 31 days, or 04/11/2007 within 1months.

- To find all the backed up files that were created between 03/11/2006 and 03/11/2007.

The format is 03/11/2007 within 365 days, or 03/11/2007 within 12 months, or 03/11/2007 within 1 years.

Return Codes

The following codes are returned by the `ca_restore` command:

If the `-waitForJobStatus` option is not specified:

Return Codes:

- **0** – Command executed successfully.
(For commands which will not submit a job, like `allusage`, `-usage`, or `-list`)
- **N** (positive integer) – Command submitted the job successfully.
(For commands which will submit a job. The actual return value will be the job number)
- **-1** – An error occurred while executing a command.

If the `-waitForJobStatus` option is specified:

Return Codes:

- **0** – Job completed successfully
- **1** – Job failed
- **2** – Job is incomplete
- **3** – Job was cancelled
- **4** – Job status is unknown

Note: If you combine `-waitForjobstatus` with switches like `allusage`, `-usage`, or `-list`, the `-waitForjobstatus` switch will be ignored, and the rule for return codes without `-waitForjobstatus` take effect.

Examples

The following are examples of syntax for the `ca_restore` command:

- Use the following syntax to restore a folder to the original location with Restore By Tree:

```
ca_restore -source machine1 c:\DIR1 -dest machine1 c:\DIR1 -username Administrator -password abc
```

- Use the following syntax to restore a folder to an alternate location:

```
ca_restore -source machine1 c:\DIR1 -dest machine1 c:\ALTDIR -username Administrator -password abc
```

- Use the following syntax to restore a folder to the original location with Restore By Session:

```
ca_restore -tape TAPE1 -session3 -dest machine1 c:\DIR1 -username Administrator -password abc
```

- Use the following syntax to restore a folder to an alternate location:

```
ca_restore -tape TAPE1 -session3 -dest machine1 c:\DIR1 -username Administrator -password abc
ca_restore -tape TAPE1 -session7 -dest machine1 c:\temp2 -username Administrator -password abc
ca_restore -source machine2 c:\ca_lic\lic98.dll -dest machine1 D:\temp -username Administrator -password abc
ca_restore -source c:\ca_lic -dest machine1 ntagent c:\DIR1 -username Administrator -password abc
```

- Use the following syntax to display all tapes in the database:

```
ca_restore -listtapes
```

- Use the following syntax to display all sessions on TAPE1:

```
ca_restore -listsessions TAPE1
```

- Use the following syntax to search CA ARCserve Backup to check whether specific files have been backed up:

```
ca_restore -findfile lic98.dll ignorecase bluejays c:\ca_lic inclsubdir within 1 months
ca_restore -findfile * ignorecase any c:\noinclsubdir within 1 days
ca_restore -findfile * ignorecase any c:\inclsubdir within 1 months
ca_restore -findfile lic98.dll ignorecase any c:\inclsubdir within 1 months
ca_restore -findfile lic98.dll ignorecase any c:\ca_lic inclsubdir today 1 day
ca_restore -findfile lic98.dll ignorecase any c:\ca_lic inclsubdir today 1 months
```


Chapter 15: ca_scan - Scan Manager Command

The scan manager command (`ca_scan`) is the command line interface to the Scan Manager, and allows you to create and submit scan jobs to the Job Queue. Many of the features available from the Scan Manager are available from the command line. The `ca_scan` command also reports information about one or more backup sessions on media.

Syntax

The `ca_scan` command line syntax is formatted as follows:

```
ca_scan
```

```
[-cahost <hostname>] <source arguments> <run job arguments> <options>
```

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the `-cahost` switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that `-cahost` be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

Usage

The `ca_scan` commands allow you to set the following options and arguments:

- miscellaneous options
- source arguments
- run job arguments
- scan options

Miscellaneous Options

The `ca_scan` command contains miscellaneous options that are used to display all associated options and define basic policies and parameters for CA ARCserve Backup to use during a scan process.

The `ca_scan` command includes the following miscellaneous options:

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: The [-cahost <hostname>] switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the -cahost switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the -cahost switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that -cahost be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

-f [set the File Name variable]

Used to specify a file name that contains the switches and parameters for the command.

This switch overcomes the shell limitation of 1024 character input from command line. You can also use this switch to hide passwords by saving them in a file.

usage

Displays a list of basic `ca_scan` commands.

allusage

Displays a list of all `ca_scan` commands and their switches.

Source Arguments

The `ca_scan` command source arguments allow you to specify the data to be scanned. You can use these arguments to identify the group, tape, and sessions to be used in your scan operation. You can use the wildcard character `*` to scan media in all groups.

The `ca_scan` command includes the following source arguments:

`ca_scan`

`[-group <group name>]`

`[-tape <tape name> [<tape ID>]]`

`[-currenttapeseq]`

Windows Usage:

`[-allsessions | -session <session # | session range>]`

UNIX Usage:

`[-allsessions | -session <session range>]`

-group <group name>

Specifies the tape group name to use for the scan job.

If you do not know the name of the group, you can use the wildcard character `*` as in the following example: `Group *`.

However, when you use the wildcard character, `ca_scan` will only scan media that corresponds to the first available tape group in the list of groups to be scanned, for example, "Group0."

-tape <tape name> [<tape ID>]

Specifies the tape to use for the scan job. The tape ID is optional and is used if there are multiple tapes with the same name.

-currenttapeseq

Specifies use of the current tape sequence for the scan job.

-allsessions

Specifies to scan all the sessions of the tape for the scan job.

-session <session # | session range>

Specifies to scan a single session or multiple sessions of the tape.

To scan multiple sessions, specify a session range.

Examples:

To scan session 27 of a tape named "MYTAPE" use the following command:

```
ca_scan-tape MYTAPE \-session 27
```

To scan session 9 through 24 of a tape named "MYTAPE" use the following command:

```
ca_scan-tape MYTAPE \-session 9-24
```

Run Job Arguments

The `ca_scan` command provides run job arguments to allow you to specify the run job methods for your scan job. The `ca_scan` run job options allow you to submit the job to be run immediately, or to submit the job on Hold, or to schedule the job for a later date and time. The method you choose determines when your scan jobs are run.

Important! To ensure that all jobs start at the scheduled time, you must synchronize the system time of the Member Servers with the system time of the corresponding Primary Server. Use the Windows Time Service to synchronize the time on all ARCserve servers in your domain.

The `ca_scan` command includes the following run job arguments:

```
ca_scan  
  [-at <hh:mm>]  
  [-on <mm/dd/yy[yy]>]  
  [-hold | -runjobnow]  
  [-description <descriptionstring>]
```

-at <hh:mm >

Specify the execution time of the scan job.

Note: All scheduled times for CA ARCserve Backup jobs are based upon the time zone where the CA ARCserve Backup server is located. If your agent machine is located in a different time zone than the CA ARCserve Backup server, you will need to calculate the equivalent local time that you want the job to be run.

-on <mm/dd/yy[yy]>

Specify the execution date of the scan job.

-hold

Submit the scan job on hold.

Cannot be used with -runjobnow.

-runjobnow

Submit and execute the scan job immediately.

Cannot be used with -hold.

-description <description string>

Add comments to the scan job.

Note: You must use double quotes " " to enclose the string and handle blank spaces.

Scan Options

The `ca_scan` command allows you to specify various scan options that are applied to the job.

The `ca_scan` command includes the following scan options:

`ca_scan`

[Decryption Password List Option]

[Logging Options] (for UNIX and Linux use only)

[Pre/Post Options]

[Exit Code Options]

[Media Options]

[Miscellaneous Scan Options]

[Job Status Options]

Decryption Password List Options

The `ca_scan` command includes the following decryption password list options:

`ca_scan`

`[-decryptionpwdlist <password 1> [<password 2>] [<password 3>] ... [<password 8>]`

[decryptionpwdlist <password 1> [<password 2>] [<password 3>] ... [<password 8>]

Provides a list of decryption passwords to be used if the sessions are encrypted. If a scan job contains multiple sessions with different passwords, CA ARCserve Backup will not stop for each session and ask for a password. Instead, the specified decryption passwords will be packaged as a combined list and the list will automatically be checked as each encrypted session is scanned.

If the required password is supplied as part of the decryption password list, the job will continue without any further user input. If the required session password is not supplied as part of the decryption password list, you will be prompted to provide one prior to allowing that encrypted session to continue.

A maximum of eight passwords can be included in the decryption password list, with each password separated by a space. Each password can have a maximum of 23 characters and cannot contain any spaces or commas.

Logging Options

The `ca_scan` command includes the following logging options:

Note: For use on UNIX and Linux platforms only.

`ca_scan`

`[-logfile[set the File Name variable] [summary | allactivity]]`

`[-snmp] [-tng] [-email <email address>] [-printer <printer name>]`

-logfile [set the File Name variable] [summary | allactivity]

Record activities during the running of the scan job to the specified filename. Specify to record all activity or a summary of the activity.

-snmp

Enable SNMP (Simple Network Management Protocol) alert.

-tng

Enable Unicenter Network and Systems Management (NSM) alert (formerly known as TNG).

-email <email address>

Send a copy of the Activity log to the specified email address.

-printer <printer name>

Send a copy of the Activity log to the specified printer.

The printer must be set up in the configuration file
ARCServe_HOME/config/calloggerd.cfg

Pre/Post Options

The `ca_scan` command includes the following pre/post options:

`ca_scan`

```
[-preexec <command>]
[-preexec timeout <minutes>]
[-postexec <command>]
[-prepostuser <user name>]
[-prepostpassword <user password>]
```

-preexec <command>

Run the specified command before the job starts. The entire path of the command should be included.

-preexec timeout <minutes>

The time to wait, in minutes, before the scan job starts, to allow time for the pre-execute command to finish.

-postexec <command>

Run the specified command after the job finishes. The entire path of the command should be included.

Note: To use this option you must also specify the `-prepostuser` option.

-prepostuser <user name>

The name of the user who is submitting this scan job.

-prepostpassword <user password>

The password of the user submitting this scan job.

Exit Code Options

The `ca_scan` command includes the following exit code options:

```
ca_scan  
[-exitcode <exitcode>]  
[-skip_delay|skip_job]  
[-skip_post]
```

-exitcode <exit code>

Specify the exit code of the pre-execute command.

Used with the `-skip_delay`, `-skip_job`, and `-skip_post` switches.

Note: The skip delay, skip job, and skip post options will only be activated if CA ARCserve Backup detects that the returned exit codes meet the selected condition (Equal To, Greater Than, Less Than, or Not Equal to).

-skip_delay

Run the scan job immediately if the specified exit code is received.

-skip_job

Skip the scan job completely if the specified exit code is received.

-skip_post

Skip the post-execute command if the specified exit code is received.

Media Options

The `ca_scan` command includes the following media options:

```
ca_scan  
[-firsttapetimeout <minutes>]  
[-spantapetimeout <minutes>]
```

-firsttapetimeout <minutes>

Specify the time (in minutes) to wait for a usable media to be made available for the scan job. If a usable media is not made available within this specified time period, the job will time out and fail.

Default: 5 minutes

-spantapetimeout <minutes>

Specify the time (in minutes) to wait for a usable span media to be made available for the scan job. If a usable media is not loaded within this specified time period, the job will time out and fail.

If the infinite value is specified, the job continues to wait and prompt until a usable media is loaded or the user cancels the job.

Default: Infinite

Miscellaneous Scan Options

The `ca_scan` command includes the following miscellaneous scan options:

`ca_scan`

`[-list]`

UNIX only:

`[-savescript <script name>]`

-list

Displays a list of tapes available for the scan job.

-savescript <script name>

Instead of submitting this job to the job queue, the scan job is saved as a script that can be loaded into the job queue later.

Job Status Options

The `ca_scan` command includes the following global job status options:

`ca_scan`

`-waitForJobStatus <polling interval <secs>>`

-waitForJobStatus <polling interval <secs>>

When specified, the `ca_scan` command will wait until the job is completed, and exit with a return code that indicates the success or fail outcome of the job.

The `<polling interval>` value defines how often (in seconds) the `ca_scan` utility checks the job status with the Queue services. The default polling interval is 60 seconds.

Return Codes

The following codes are returned by the `ca_scan` command:

Return Codes:

- **0** – Command executed successfully.
- **-1** – An error occurred while executing a command.

Examples

The following are examples of syntax for the `ca_scan` command:

- Use the following syntax to list groups, with tape names, available on a host server:

```
ca_scan-cahost machine1 -list
```

- Use the following syntax to specify all sessions to scan for a tape:

```
ca_scan-tape TAPE1 -allsessions
```

- Use the following syntax to specify a session to scan for a tape:

```
ca_scan-tape Tape1 -session 2
```

Chapter 16: ca_vcbspopulatedb - VMware VCB Utility Command

The VMware VCB utility command (`ca_vcbspopulatedb`) is a data collection tool that lets you populate the CA ARCserve Backup database with information about the VMware-based VMs in your backup environment. You must execute this utility on the backup proxy system. The utility then retrieves all the information pertaining to all the VMs in the VMware ESX Host systems and the VMware vCenter Server systems and adds it to the database.

The `ca_vcbspopulatedb` utility populates the CA ARCserve Backup Database with information such as:

- VCB backup proxy system names
- VMware ESX/ESXi Host names and VMware vCenter Server names
- VM host names
- Name of the volumes contained within the VMs on Windows systems

You should run this utility periodically to ensure that the CA ARCserve Backup database contains up-to-date information about the VMs and volumes in ESX Host systems. If you have the CA ARCserve Backup server (primary/member) installed on the proxy machine, then you can use generic job scheduler to run this utility periodically.

Syntax

The `ca_vcbpopulatedb` command line syntax is formatted as follows:

```
ca_vcbpopulatedb
  -Primary <PrimaryServerName>
  -carootUser <ARCserve caroot User>
  -carootPass <ARCserve caroot Password>
  [-vcb <VCBMachineName>]
  -esxserver <ESXServerName>
  -esxUser <ESXAdmin>
  -esxUserPass <ESXAdminPassword>
  [-proto <https/http>]
  [-VCBMountableVM]
  [-DelProxydb]
  [-retainVMInDB]
  [-silent]
  [-debug]
  -insertvm <VMname>
  -deleteVM <VMname>
  [-stopAutoPopulate]
  -config <config_file_name>
```

Usage

The `ca_vcbpopulatedb` command contains arguments and options that are used to define actions to follow when populating VM information into the CA ARCserve Backup database.

The `ca_vcbpopulatedb` command includes the following arguments and options:

-Primary <PrimaryServerName>

Specifies the host name of the Primary CA ARCserve Backup system.

-carootUser <ARCserve caroot User>

Specifies the user name, with caroot privileges, for the Primary CA ARCserve Backup system.

-carootPass <ARCserve caroot password>

Specifies the password for the root user name.

-vcb <VCBMachineName>

Specifies the name of the VCB Proxy machine.

Note: This is an optional argument. If you omit this argument, the utility assumes that the current machine name will be used as VCB machine name.

-esxserver <ESXServerName>

Indicates the name of the VMware ESX Host system or the VMware vCenter Server system containing the VMs residing on the iSCSI/SAN LUN.

-esxUser <ESXAdmin>

Specifies the name of the VMware ESX Host system user with Administrator privileges.

-esxUserPass <ESXAdminPassword>

Specifies the password for the VMware ESX Host system Admin User.

-proto <https/http>

Indicates the communication protocol between the backup proxy system and the VMware ESX Host system or the VMware vCenter Server system.

Note: This is an optional argument. If you omit this argument, the utility assumes https is to be used as the communication protocol.

-VCBMountableVM

If this switch is specified as a parameter, the utility will populate the database with the running VMs that are residing only on the iSCSI/SAN LUN storage device. With this switch specified, the utility would skip VMs in the VMware ESX Host system residing on any storage media other than the iSCSI/SAN LUN.

You should run the `ca_vcbpopulatedb` command line utility with this switch, when you have VMs in VMware ESX Host systems residing on multiple storage media, such as the local disk of ESX Host systems, SAN LUN, NAS/NFS, or iSCSI storage device.

With this switch included, the utility would only populate the CA ARCserve Backup primary server database with information from the running VMs residing on the iSCSI/SAN LUN storage device.

Notes:

If you run the `ca_vcbpopulatedb` command line utility with this switch, you must run the utility on VCB proxy system.

If you run this utility with the `VCBMountableVM` switch, the utility would take longer to run, because it performs a mount and unmount operation of each running VM that is residing on the SAN LUN storage device.

-DelProxydb

Deletes all the VMs available in the database for the given VMware ESX Host system or the VMware vCenter Server system under the given backup proxy system.

-retainVMInDB

Lets you retain data (backup information) for VMs that are not available when you execute this command.

By default, this utility captures information from VMs that are available when you execute this utility. If a VM is not available (for example, the VM is powered off or deleted from the environment), CA ARCserve Backup deletes the data relating to the VM from the CA ARCserve Backup database. With this option enabled, CA ARCserve Backup captures information from VMs that are available, and retains the backup information from VMs that are not available.

-silent

Specifies to prevent the utility from printing messages to the command line console.

-debug

Specifies to direct the utility to write a detailed debug log. The log will be created in the current working directory.

Note: The name of the log file is `ca_vcbpopulatedb.log`.

-insertVM

Lets you add information about a specific VM that resides in the VM host system to the CA ARCserve Backup database.

Note: You cannot combine this argument with any other argument when you execute `ca_vcbpopulateDB`.

-deleteVM

Lets you delete information about a specific VM from the CA ARCserve Backup database.

Note: You cannot combine this argument with any other argument when you execute `ca_vcbpopulateDB`.

-stopAutoPopulate

Lets you disable the auto-populate process for the specified backup proxy system.

-config <config_file_name>

Specifies the name of the ca_vcbpopulatedb configuration file.

The ca_vcbpopulatedb utility uses the information specified in the configuration file to populate the CA ARCserve Backup database.

This configuration file contains details about Primary Server Machine, Primary User, Primary User's Password, VCB Systems Name, VMware ESX Host Name, and VMware ESX Host system User credentials.

You can have only one entry in the configuration file.

Note: You must create a configuration file to use this utility.

Create a ca_vcbpopulatedb Configuration File

You create a configuration file with details about the CA ARCserve Backup Primary server machine, the CA ARCserve Backup Primary user name, and so on. The ca_vcbpopulatedb utility uses the information specified in the configuration file to populate the CA ARCserve Backup database.

To create a ca_vcbpopulatedb configuration file

1. Open a text editing application such as Notepad. Save the configuration file with a .cfg file extension in the same directory as the ca_vcbpopulatedb utility.
2. Complete the arguments in the following syntax:

```
ca_vcbpopulatedb -Primary <PrimaryServerName> -carootUser <ARCserve caroot User> -carootPass  
<ARCserve caroot password> [-vcb <VCBMachineName>] -esxServer <ESXServerName> -esxUser  
<ESXAdmin> -esxUserPass <ESXAdminPassword> [-proto <https/http>] [-vcbMountableVM] [-delProxydb]  
[-retainVMinDB] [-silent] [-debug] -insertvm <VMname> -deleteVM <VMname> [-stopAutoPopulate]
```

Note: For information about the usage for this command, see [ca_vcbpopulatedb Usage](#) (see page 244).

3. Close and save the configuration file.

Utility Return Codes

The following codes are returned by the `ca_vcbpopulatedb` command:

Job Status Return Codes:

- **0** - Job completed successfully
- **1** - Invalid Argument was specified
- **2** - CA ARCserve Backup domain user authentication failure occurred
- **3** - A VMware ESX Host system user authentication failure occurred
- **4** - A VMware ESX Host system connection failure occurred
- **5** - A database operation failure occurred
- **6** - An XML creation failure occurred
- **7** - Microsoft .NET version 2.0 or later not found in your environment
- **8** - More than one instance of `ca_vcbpopulatedb` is running.
- **9** - An unknown error has occurred

Examples

The following are examples of syntax for the `ca_vcbpopulatedb` command:

- Use the following command populate the VM details of the VMware ESX Host system having a hostname "ESXServer1" into the ARCserve server "ARCserver1" database under VCB Proxy machine "VCBProxy1" using http protocol with the debug flag set:

```
ca_vcbpopulatedb.exe -Primary ARCserver1 -carootUser caroot -carootPass ca123 -vcb VCBProxy1  
-esxServer ESXServer1 -esxUser root -esxUserPass rootpasswd -proto http -debug
```

- Use the following command to remove the all VM details of the VMware ESX Host system having a hostname "ESXServer1" from the ARCserve server "ARCserver1" database available under VCB Proxy machine "VCBProxy1" with the debug flag unset:

```
ca_vcbpopulatedb.exe -Primary ARCserver1 -carootUser caroot -carootPass ca123 -vcb VCBProxy1  
-esxServer ESXServer1 -esxUser root -esxUserPass rootpasswd -delProxydb
```

- Use the following command to populate the VM details of the VMware ESX Host system having a hostname "ESXServer1" into the ARCserve server "ARCserver1" database, only the VM mountable inside the VCB proxy machine "VCBProxy1" with the debug flag set:

```
ca_vcbpopulatedb.exe -Primary ARCserver1 -carootUser caroot -carootPass ca123 -vcb VCBProxy1  
-esxServer ESXServer1 -esxUser root -esxUserPass rootpasswd -vcbMountable VM -debug
```

- Use the following command to stop populating the CA ARCserve Backup database automatically.
 - The server name is Myvirtualserver and the server resides in a VMware vCenter Server system:

```
ca_vcbpopulatedb.exe -stopAutoPopulate Myvirtualserver
```

- The server name is MyEsxserver and the server resides in a VMware ESX Host system:

```
ca_vcbpopulatedb.exe -stopAutoPopulate MyEsxserver
```


Chapter 17: ca_msvmpopulatedb - Hyper-V VM Utility Command

The ARCserve Hyper-V Configuration Tool utility command (ca_msvmpopulatedb) is a data collection tool that lets you populate the CA ARCserve Backup database with the information about the Virtual Machines (VMs) on your Hyper-V systems. You must execute this utility on the Hyper-V host system. The utility then retrieves all the information pertaining to all the VMs in the Hyper-V host system and adds it to the database.

The ca_msvmpopulatedb utility populates the CA ARCserve Backup Database with information such as:

- Hyper-V Host names
- VM host names
- Name of the volumes contained within the VMs on Windows systems

You should run this utility periodically to ensure that the CA ARCserve Backup database contains up-to-date information about the VMs and volumes in a Hyper-V host. If you have the CA ARCserve Backup server (primary/member) installed on the Hyper-V host, then you can use generic job scheduler to run this utility periodically.

Syntax

The ca_msvmpopulatedb command line syntax is formatted as follows:

```
ca_msvmpopulatedb
  -Primary <PrimaryServerName>
  [-Debug <Debug Level>]
  [-retainVMinDB]
  [-DeVMinDB]
```

Usage

The `ca_msvmpopulatedb` command contains arguments and options that are used to define actions to follow when populating VM information into the CA ARCserve Backup database.

The `ca_msvmpopulatedb` command includes the following arguments and options:

-Primary <PrimaryServerName >

Specifies the host name of the Primary CA ARCserve Backup system.

-debug

Specifies to direct the utility to write a detailed debug log. The log will be created in the current working directory.

Note: The name of the log file is `ca_msvmpopulatedb.log`.

Debug Level

Lets you specify the level of details that you require in the debug log (`ca_mshvpopulatedb.log`). A higher debug level value means more detailed information will be included in the debug log.

Default: 2

Range: 1 to 6

-retainVMInDB

Lets you retain data (backup information) for VMs that are not available when you execute this command.

By default, this utility captures information from VMs that are available when you execute this utility. If a VM is not available (for example, the VM is powered off or deleted from the environment), CA ARCserve Backup deletes the data relating to the VM from the CA ARCserve Backup database. With this option enabled, CA ARCserve Backup captures information from VMs that are available, and retains the backup information from VMs that are not available.

-DelVMInDB

Lets you delete the VMs available in the CA ARCserve Backup database for the specified Hyper-V server, and populate the latest VM data into the CA ARCserve Backup database.

Utility Return Codes

The following codes are returned by the `ca_msvmpopulatedb` command:

Job Status Return Codes:

- **0** - Job completed successfully
- **2** - CA ARCserve Backup domain user authentication failure occurred
- **5** - A database operation failure occurred
- **6** - An XML creation failure occurred
- **8** - More than one instance of `ca_msvmpopulatedb` is running.
- **9** - An unknown error has occurred

Examples

The following are examples of syntax for the `ca_msvmpopulatedb` command:

- Use the following command to add VMs to the CA ARCserve Backup Primary (or standalone) server "CASvr1" for the first time:

```
ca_msvmpopulatedb -P CASvr1
```

- Use the following command to add the VMs to the CA ARCserve Backup Primary (or standalone) server "CASvr1" but do not want to remove the existing VMs that may be unreachable or powered-off at this time:

```
ca_msvmpopulatedb -P CASvr1 -retainVMInDB
```

- Use the following command to delete the VMs registered with the CA ARCserve Backup Primary (or standalone) server "CASvr1" for this Hyper-V host:

```
ca_msvmpopulatedb -P CASvr1 -DeVMInDB
```


Chapter 18: cabatch - Batch Command

The batch command (cabatch) allows you to submit jobs to a local or remote CA ARCserve Backup job queue using an external script file, delete jobs from the job queue, and modify the execution times for all of the jobs in the job queue. For the cabatch utility to submit jobs to the CA ARCserve Backup job queue, the Backup Manager does not have to be running, but all CA ARCserve Backup engines must be running.

Note: To submit a job to the CA ARCserve Backup job queue of a remote server, you must have proper access privileges for that server.

To submit a job using the cabatch utility, you must create and save a job script using the Backup Manager or prepare a text file with a job description using the cabatch Job Information Template. When this template is completed, cabatch will read this job description file and submit the job to the CA ARCserve Backup job queue for execution. The cabatch Job Information Template (Template.txt) is located in the ARCserve Backup home directory.

The command also provides automation by using the Job Management Option component of Unicenter NSM (formerly known TNG) by using the /J (returns the job return code) and /W (wait for job completion) switches. For more information about how to use this to integrate with Unicenter NSM, see Unicenter NSM - Job Management Option Integration.

Note: Prior to Unicenter NSM r11, the Job Management Option was referred to as Workload Management.

Submit a Job

Use the following syntax to submit a job using a script file:

```
CABATCH/MODE=ExecuteSubmit /H=ServerName /S=<path>ScriptName
```

Example:

```
CABATCH/H=QANT/S=C:\BACKUP.ASX/W
```

Return Codes:

- 0** - The job finished successfully.
- 1** - The job is incomplete.
- 2** - The job was cancelled.
- 3** - The job failed.
- 4** - The job crashed.
- 5** - There was a system error.
- 6** - There was a parameter error.
- 7** - There was a memory failure. Close any non-critical applications that may be using memory and retry the job.
- 8** - There was a generic error.

Modes:

Submit

Specifies to run the job immediately. The job will be added to job queue according to the script file, then carunjob will get this job by number from job queue and launch it.

Execute

Specifies to run the job based on the specified schedule time (not immediately). The job will not be added to job queue, and carunjob will launch this job directly through the script file.

Options:

/H [server name]

Specify the name of the server whose job queue you are submitting jobs to. If you enter "*", cabatch determines and uses the local computer name as the CA ARCserve Backup Domain Server name.

/S [script name]

Specify the name of the binary script or the job description text file prepared with the cabatch Job Information Template (Template.txt).

/RS[Computer Name]

Specifies to replace the source computer name in script with a Computer Name.

Note: If you do not specify a computer name, the host name will be used.

/RD[Computer Name]

Specifies to replace the destination computer name in script with a Computer Name.

Note: If you do not specify a computer name, the host name will be used.

/D [MM/DD/YY]

Specifies the date you want to execute the job.

/T [HH:MM]

Specifies the time you want to execute the job.

/G [device group]

Specifies the device group name.

/TP[media name]

Specifies the media name.

/TID[media id]

Specifies the media ID.

/TSN[media sequence number]

Specifies the media sequence number.

/POST[command]

Runs the specified command after the job finishes. The entire path of the command should be included.

/PRE[command]

Runs the specified command before the job starts. The entire path of the command should be included.

/PREPOSTUSER=user

Specifies the credentials of the user running the pre or post command.

/PREPOSTPWD=password

Specifies the password for the user running the pre or post command.

/SSN[session number]

Specifies the session number for a restore job.

/RSessPW

Specifies to replace the session password in script.

/J

Specifies to use the CA ARCserve Backup job status as the return code.

/W

Specifies to wait for job completion.

Delete a Job

Use the following syntax to delete all or the specified jobs from the job queue:

```
CABATCH/E=AL|BK|RS|CP|CT/H=ServerName
```

Options

/H [server name]

Specifies the name of the server whose job queue you are deleting jobs from. If you enter "*", cabatch determines and uses the local computer name as the CA ARCserve Backup Domain Server name.

AL

Specifies to delete all jobs.

BK

Specifies to delete backup jobs.

RS

Specifies to delete restore jobs.

CP

Specifies to delete copy jobs.

CT

Specifies to delete count jobs.

Modify a Job

Use the following syntax to modify the execution time for all of the jobs in the job queue:

```
CABATCH/H=ServerName/MT=nnn
```

Options

/H [server name]

Specify the name of the server whose job queue you are modifying jobs from. If you enter "*", cabatch determines and uses the local computer name as the CA ARCserve Backup Domain Server name.

/MT[nnn]

Enter the number of minutes to modify the job time.

- For positive numbers, enter only the number.
- For negative numbers, type "-" (minus sign) and then the number. For example, 30 or -30.

Examples

The following are examples of syntax for the cabatch command:

- Use the following syntax to submit a job using a script file:

```
cabatch /MODE=Execute|Submit /H=ServerName /S=<path>ScriptName
```

- Use the following syntax to submit a job using a script file with /W switch:

Note: The cabatch command will not return immediately until completion of the job when you include the /W switch.

```
cabatch /MODE=Execute|Submit /H=ServerName /S=<path>ScriptName /W
```

- Use the following syntax to delete all jobs (AL) from the job queue:

```
cabatch /E=AL /H=ServerName
```

- Use the following syntax to delete backup jobs (BK) from the job queue:

```
cabatch /E=BK /H=ServerName
```

- Use the following syntax to delete restore jobs (RS) from the job queue:

```
cabatch /E=RS /H=ServerName
```

- Use the following syntax to modify the execution time for all jobs in the job queues and launch jobs to execute after 30 minutes:

```
cabatch /H=ServerName /MT=30
```

Chapter 19: careports - Report Writer Command

The report writer command (CAreports) provides access to the CA ARCserve Backup Report Writer utility dialog and allows you to create customized (Predefined and User-created) reports. You can also access the Report Writer dialog from the Utilities menu (or the Utilities section) in the CA ARCserve Backup home page.

The CAreports command provides options for running the report in silent mode and sending an alert via the CA ARCserve Backup Alert Manager. The reports created using Report Writer can be previewed, printed, or scheduled in Report Manager.

To view a description of all CAreports syntax, enter the following command:

```
CAreports /?
```

Syntax

The careports command line syntax is formatted as follows:

```
careports  
    [m <machine_name>]  
    [-r <report_name>]  
    [-s]  
    [-o <output_filename>]  
    [-alert]  
    [-f <format_type>]  
    [?]
```

Options

The careports provides various options for generating reports and sending alerts via the CA ARCserve Backup Alert Manager.

The careports command includes the following options:

-a

Enables the output of files automatically. Combined with the -o option (output file name), you can create new output files in a specific directory. The output file name follows the report template naming convention. Using the additional -o option, specifies that existing files will not be overwritten.

-s

Generates the report in silent mode (no dialogs or messages boxes).

The -s option works with the -r option (report template) and should be used when the report is scheduled from the "Job Scheduler Wizard" tool.

-r <report_name>

Specifies the name of the report template to be used for the report. If the -r option is not specified, the other options (-s, -o, and -alert) are ignored.

-o <output_filename>

Specifies the output file name where the results that are generated by running the report are saved. If a specified file exists, it is renamed with a .bak extension. For example, c:\temp\report.xml is renamed to: c:\temp\report.bak.xml.

-m <machine_name>

Specifies the name of the computer if you want to generate your report on a remote computer.

-f <format_type>

Specifies the format of the output file:

- XML (*.xml) (default)
- CSV (*.csv) (comma-separated format).

-alert

Sends an alert message when the report is completed. The alert messages should be set from Alert Manager, under "ARCserve" configuration.

-append

Appends a newly created report to an existing file.

Note: Both the newly created report and the existing report files must be in CSV format.

?

Displays the CA ARCserve Backup query report screen, which allows you to specify the information that you want to include in your report.

Examples

The following are examples of syntax for the careports command:

- Use the following command to open a report template and create output xml for <machine name> with silent mode:

```
careports -s -r <report name> -o <output name> -m <machine name>
```

- Use the following command to send the output to alert manager (alert):

```
careports -s -r <report name> -o <output name> -alert -m <machine name>
```

- Use the following command to open a report template and create output CSV (default value is XML) for <machine name> with silent mode:

```
careports -s -r <report name> -o <output name> -f CSV -m <machine name>
```


Chapter 20: caadvreports - Advanced Report Generator Command

The advanced report generator command (caadvreports) is a utility that can generate various reports that provide an overview of the current data protection status. The caadvreports utility puts all the log messages in file CAAdvReports.Log located at ARCServe_HOME\logs folder. This file provides detailed information about the actions taken by caadvreports in generating a report. This log file can be used as starting point to debug any problems with reports.

Syntax

The caadvreports command line syntax is formatted as follows:

```
caadvreports
  -ReportType <report_ID>
  -OutFile <output file name>
  -StartDate <mm/dd/yyyy> [hh:mm:ss]
  -EndDate <mm/dd/yyyy> [hh:mm:ss]
  -Server <remote server name>
  -JobDesc <string text>
  [-XML][[-CSV]
  -Percent <percent value>
  -Top <n>
  -Serial <serial>
  -PastDays <n>
  -AutoName
  -Alert
  -VaultCycle
```

caadvreports - Reports

The caadvreports command provides various options for generating advanced reports. The caadvreports command can accept and parse a variety of report parameters; however, not all parameters are required for all the reports. Based on the type of report that is being generated, only the parameters required and supported by that specified report will be used. Parameters that are not needed will be silently ignored.

To run any advanced report, you must specify at least the report type and the path of the file where the generated report will be saved. If one of the required parameters for a particular report is not specified, the utility will fail and the reason for failure will be entered in the log file.

The following report types, along with the corresponding supported filter parameters can be generated using the caadvreports command:

Backup Attempt Success Rate: Summary

This report provides information on what percentage of backup attempts that are successful and also shows percentage of incomplete and failed backup attempts.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- JobDesc (Limit output to only include jobs with matching description)

Backup Attempt Success Rate

This report provides information on what percentage of backup attempts that are successful on a per node basis.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- JobDesc (Limit output to only include jobs with matching description)
- Percent (Limit output to only include nodes with failure percent greater than the specified percentage).

Restore Attempt Success Rate

This report provides information on what percentage of all restore attempts that are successful.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- JobDesc (Limit output to only include jobs with matching description)

Drive Throughput

This report provides information about the average throughput that is being seen on the drives.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- Serial (Limit output to only include drives with serial number matching the filter)

Backup Error

This report shows the number of errors and warnings generated for the backup job for each of the backup paths during the reporting period.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- JobDesc (Limit output to only include jobs with matching description)

Failed Backup Attempt

This report shows the clients with the most failed backup attempts during the reporting period.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- JobDesc (Limit output to only include jobs with matching description)
- Top (Limit output to the top 'n' clients only)

Consecutive Failed Backup Attempt

This report shows the clients with the most consecutive failed backup attempts during the reporting period.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays

Partial Backups

This report shows the clients with the most number of partial backups.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- JobDesc (Limit output to only include jobs with matching description)
- Top (Limit output to the top 'n' clients only)

Full Backup Duration

This report shows the average backup time, average backup data, and average throughput for full backups of all backup paths during the reporting period.

Supported Filter Parameters:

- StartDate
- EndDate
- PastDays
- JobDesc (Limit output to only include jobs with matching description)

Last Backup Status Report

This report shows the status of last execution of all the backup jobs in the queue. If a job is still active, it shows the current status of the running job. This report only shows the status of the job in the queue at the time the report is generated.

Supported Filters

- None

Vaulting Report

This report shows the list of tapes that will move in or out of the vault on the day of reporting. You can use the `-VaultCycle` command to run the vault cycle before generating the report.

Supported Filters

None

caadvreports - Options

The `caadvreports` command provides various options for generating advanced reports and sending alerts via the CA ARCserve Backup Alert Manager.

The `caadvreports` command includes the following options:

-ReportType <n>

Specifies the type of report to be generated. This parameter is required for all the reports.

The value of `<n>` determines the type of report that will be generated.

The following list provides the value of `<n>` and the report that it generates.

<n>	Report Name
1	Backup Attempt Success Rate: Summary
2	Backup Attempt Success Rate
3	Restore Attempt Success Rate
4	Drive Throughput
5	Backup Error
6	Failed Backup Attempt
7	Consecutive Failed Backup Attempt
8	Partial Backups
9	Full Backup Duration
10	Last Backup Status Report
11	Vaulting Report

Note: For more information about each report, see [caadvreports - Reports](#) (see page 266).

-OutFile [set the File Name variable]

Specifies the full path of the file where the generated report will be saved. This is a required parameter for all the reports.

If '-AutoName' is used, this switch is not needed.

-StartDate <mm/dd/yyyy> [hh:mm:ss]

Specifies the start date and time of the reporting duration. The time parameter 'hh:mm:ss' is optional. If the time is not specified, it is assumed to be '00:00:00' (12:00 AM). If time is specified, it should be specified in 24 hour format.

Note: If the "-PastDays <n>" switch is included, then this switch is not needed.

-EndDate <mm/dd/yyyy> [hh:mm:ss]

Specifies the end date and time of the reporting duration. The time parameter 'hh:mm:ss' is optional. If the time is not specified, it is assumed to be '11:59:00' (11:59 PM). If time is specified, it should be specified in 24 hour format.

Note: If the "-PastDays <n>" switch is included, then this switch is not needed.

-Server <remote server>

Specifies the remote server on which the report is to be executed. Typically, reports are executed on the Primary server. This is included if the report is to be executed on a remote Member server.

-JobDesc <string text> [-XML | -CSV]

Specifies the job description string text. This is included by some reports to limit the output to include only certain jobs with job description matching the string text.

-XML

Specifies to generate a report in XML format. Generated XML reports can be used in conjunction with the provided response .xsl file to generate an HTML report.

This is a default option if no other overwriting option is specified and cannot be combined with -CSV parameter.

-CSV

Specifies to generate a report in Comma Separated Value format.

-Percent <percent value>

Specifies the percent value that can be used for filtering the report.

-Top <n>

Specifies to limit the report output to just the top 'n' count.

-Serial <serial>

Specifies to limit the report output to only those drives whose serial number matches the specified serial string pattern. Serial numbers are compared against device serial numbers in the Drive Throughput Report.

-PastDays <n>

Specifies the past number of days for which the report is to be generated starting from the current time. This switch can be used in place of the '-StartDate' and '-EndDate' switches to generate a report for a fixed duration.

For example, to generate a weekly report, the value of 'n' would be set to 7 and this specifies to generate a report for the last seven days.

-AutoName

Specifies that the output report name will be automatically generated. The auto generated file name is created by combining the report name and the execution date and time.

-Alert

Sends an alert message when the report is completed. The alert messages should be set from Alert Manager, under "ARCserve" configuration.

-VaultCycle

Used with the Vaulting Report to auto-run the Vaulting Cycle before generating the report.

Important! If using this switch, do not manually run the Vault Cycle before or after the report on the day on which this report is generated.

Examples

The following are examples of syntax for the caadvreports command:

- Use the following command to generate a 'Drive Throughput' report (Report Type 4) for the last seven days and store the result in an automatically generated file name:

```
CAAdvReports.exe -reporttype 4 -pastdays 7 -autoname
```

- Use the following command to generate a 'Full Backup Duration' report (Report Type 9) for all jobs executed between 1/1/2007 and 3/30/2007 and send the output to a file titled 'full_backup_report.xml':

```
CAAdvReports.exe -reporttype 9 -startdate 01/01/2007 -enddate 03/30/2007 -outfile full_backup_report.xml
```

- Use the following command to generate a 'Full Backup Duration' report (Report Type 9) for all jobs executed between 1/1/2007 and 3/30/2007 and send the output to a file titled 'full_backup_report.csv' in a 'comma separated value' file. Limit the output to jobs with job description containing 'ACCT':

```
CAAdvReports.exe -reporttype 9 -startdate 01/01/2007 -enddate 03/30/2007 -outfile full_backup_report.csv  
-CSV -JobDesc 'ACCT'
```

Chapter 21: pfc - Preflight Checklist Utility Command

The preflight checklist utility command (pfc) allows you to run vital checks on the CA ARCserve Backup server and Agents to detect conditions that may cause backup jobs to fail. This command is intended to run while CA ARCserve Backup is up and running.

The checks performed by pfc fall into four categories: System Checks, ARCserve Checks, Agent Checks, and Media Checks.

System Checks

These include checking system requirements for the server, available disk space for the database, and RPC (Remote Procedure Calls) service registration.

ARCserve Checks

These include checking the ARCserve system account and its privileges, the status of the CA ARCserve Backup engines, SAN server connectivity (if the SAN option is installed), and the health of the tape devices attached to the server.

Agent Checks

These include checking the connection and credentials for any client and database agents needed for the job.

Media Checks

These include checking the availability of media in the scratch set (if a media pool is specified for the job), the media expiration dates, and for source and destination conflicts for file system devices.

Every time you use the pfc utility it creates the following a log:

```
PFC_SERVERNAME_#####.LOG
```

This log includes the same information that appears in the output generated in the Command Prompt windows when you run pfc and is located in the CA ARCserve Backup LOG directory - ARCserve Home Directory/logs/pfclogs. You can change this directory by using the -logpath option.

Syntax

The pfc command line syntax is formatted as follows:

```
pfc[-cahost <hostname>][options][filename(s)]
```

Usage

The pfc commands allow you to set the following checks:

- System Checks
- ARCserve Checks
- Agent Checks
- Media Checks

Preflight Checks

The pfc system preflight checks include checking system requirements for the server, checking the CA ARCserve Backup system account, checking the client and database agents needed for the job, and checking the availability of media in the scratch set (if applicable).

The pfc command includes the following options:

```
pfc[-cahost <hostname>][options][filename(s)]
```

```
-allchecks  
-syschecks  
-bchecks  
-agentchecks  
-mediachecks  
-a  
-n  
-s  
-v  
-logpath <path>  
-alert
```

-cahost <hostname>

Identifies the name of the system hosting the operation.

If you want to execute the operation on a remote system, this switch must be included in the command.

If you want to execute this operation on your local system, this switch is not required and should not be included in the command.

Note: The [-cahost <hostname>] switch is optional. This switch is not needed if you are using these commands locally; however, a hostname is required if you are performing these commands remotely. The host specified by the -cahost switch can be a member server or primary server. However, CA ARCserve Backup will always add the job to the job queue of the primary server, and the primary server will then dispatch the job to the proper server (primary/member) according to this switch when the job is processed.

Note: If you installed CA ARCserve Backup using the "ARCserve Manager (Console)" mode, you must include the -cahost switch to execute this command from your local machine. Because this Console installation mode does not actually install all CA ARCserve Backup capabilities on your local machine, it is mandatory that -cahost be included when submitting this command remotely to the primary or member server containing CA ARCserve Backup or else the command will fail.

filename(s)

Specifies a job script file name if you want to perform a check on a specific job. For example, 00000005.job. These files are located in the 00000001.qsd directory under the directory where CA ARCserve Backup was installed.

-allchecks

Performs all checks of the parameters of CA ARCserve Backup, including system checks, ARCserve checks, agent checks, and media checks. These checks are performed in non-interactive mode on all Ready jobs in the job queue. You cannot specify filenames when you use this switch.

-syschecks

Performs system-related checks, including disk space, RPC (Remote Procedure Calls) communication, system resources, and so on.

-bchecks

Performs process and resource-related checks, including the status of CA ARCserve Backup daemons, database checks, tape changer checks, and so on.

-agentchecks <filenames>

Performs check of the agent resources required by the backup jobs specified. When you use this, you must specify one or more job script file names. These files are located in the 00000001.qsd directory under the directory CA ARCserve Backup was installed to.

For this command, you would need to specify the job file under \$ARCSERVE_HOME\00000001.qsd directory as the last parameter.

For example, if you want to run an Agent check for a job that has a job number of 3, then there should be a job file "00000003.job" under \$ARCSERVE_HOME\00000001.qsd directory, and the pfc command for this check would be:

```
pfc-agentchecks 00000003.job
```

Note: You can also use the -a switch with this option to run Agent checks for all jobs in the queue.

Note: The Master server credentials cannot be verified by the Preflight Checklist (PFC) utility.

-mediachecks <filenames>

Performs media checks. When you use this, you must specify one or more job script file names. These files are located in the 00000001.qsd directory under the directory CA ARCserve Backup was installed to. For example, pfc -mediachecks job105.

For this command, you would need to specify the job file under \$ARCSERVE_HOME\00000001.qsd directory as the last parameter.

For example, if you want to run a Media check for a job that has a job number of 3, then there should be a job file "00000003.job" under \$ARCSERVE_HOME\00000001.qsd directory, and the pfc command for this check would be:

```
pfc-mediachecks 00000003.job
```

Note: You can also use the -a switch with this option to run media checks for all jobs in the queue.

-a

Specifies all Ready jobs in the job queue. You cannot specify filenames when you use this switch.

-n

Runs in non-interactive mode. When you use this, pfc does not stop during execution to prompt for input.

-s

Attempts to start any CA ARCserve Backup engines that are not running. The -bchecks option must also be used or -s has no affect.

-v

Runs in verbose mode. When you use this option, pfc provides detailed information in its output to the Command Prompt window and log about the checks being performed. This includes information used for debugging, such as the name of the failing function and the error code returned when an API call fails.

-logpath <path>

Sets the path for log files. The default path is the CA ARCserve Backup LOG directory (ARCServe_HOME/logs/pfclogs). You can change this location by specifying a path for the -logpath option.

-alert

If you configured the Alert feature, this command lets you send an alert. For example, if you configured Alert to send email and use the -alert command, the PFC log is sent as an email attachment.

For more information about configuring alerts, see the chapter Administering the Backup Server in the CA ARCserve Backup Administration Guide.

Examples

The following are examples of syntax for the pfc command:

- Use the following syntax to perform all checks, in non-interactive mode, on all READY jobs in the job queue:

```
pfc-allchecks
```

- Use the following syntax to perform system checks in verbose and non-interactive mode:

```
pfc-syschecks -v -n
```

- Use the following syntax to perform ARCserve checks and to start any CA ARCserve Backup engines that are not running:

```
pfc-bchecks -s
```

- Use the following syntax to perform agent checks for all READY jobs in the queue:

```
pfc-agentchecks -a
```

- Use the following syntax to perform agent checks for job 9:

```
pfc-agentchecks 00000009.job
```

- Use the following syntax to perform media checks for jobs 8 and 9:

```
pfc-mediachecks 00000008.job 00000009.job
```

- Use the following syntax to perform media checks for job 9, display the output on the console, and also log the output in a file in the /tmp directory:

```
pfc-mediachecks -logpath /tmp/ 00000009.job
```

- Use the following syntax to perform agent checks for a job, which is on HOLD:

```
pfc-agentchecks 00000009.job
```

Chapter 22: tapecomp - Tape Compare Utility

The tape compare command (tapecomp) is the command line interface utility that allows you to compare media to media. This utility can be used only with CA ARCserve Backup generated media and must be used in the CA ARCserve Backup home directory.

Syntax

The tapecomp command line syntax is formatted as follows:

```
tapecomp[options]
-s<SourceGroup>
-d<DestGroup>
-r<Source TapeName>
-t<Dest TapeName>
-r#
-x#
```

Options

The tapecomp utility provides various options for comparing CA ARCserve Backup media to media.

The tapecomp utility includes the following options:

-s <source group name>

Specifies the source group name where your tape is located.

-d <destination group name>

Specifies the destination group name. This switch must be used in all cases.

-r <source tape name>

Specifies the source tape name of the tape you want to compare.

-t <dest tape name>

Specifies the destination tape name of the tape you want to compare.

-n#

Specifies the beginning source session number.
The default is 1.

-x#

Specifies the beginning target session number.
The default is 1.

Notes:

- This utility supports all CA ARCserve Backup certified tape drives. The source and target can be different tape drive models.
- A log file is generated for each copy operation.
- The tape compare utility can compare from one particular session to the end or the entire media set.
- The source and target can have multiple media. The utility will ask for the next sequence media when it hits the end of the media.
- Utility progress can be monitored from the CA ARCserve Backup Device Manager.
- The tape compare utility does not support comparing tapes that were created using multiplexing or encryption.
- The tape compare utility does not support comparing two tapes that have identical names within the same group.

Examples

The following are examples of syntax for the `tapecomp` command:

- Use the following command to compare all sessions on Tape1 in Source Group 0 to Tape2 in Destination Group 1:

```
tapecomp -sGROUP0 -rTAPE1 -dGROUP1 -tTAPE2
```
- Use the following command to compare all sessions from Session 3 on TAPE1 TEST in Source Group 0 with all sessions from Session 4 on target TAPE2 TEST in Destination Group 1:

```
tapecomp -sGROUP0 -r"TAPE1 TEST" -n3 -dGROUP1 -t"TAPE2 TEST" -x4
```

Chapter 23: tapecopy - Tape Copy Tool Command

The tape copy command (tapecopy) is the command line interface to the Tape Copy Tool utility, which allows you to quickly copy data from one media to another. These media do not have to be similar. You can copy entire tapes or sessions. You can do this either by stating the source of what you want to copy, or by stating search criteria against the sessions stored in the CA ARCserve Backup database.

When tapecopy performs a tape copy function a return exit code is generated to indicate the status of the process.

Note: You cannot use tapecopy to copy data to VM:Tape media.

Syntax

The tapecopy command line syntax is formatted as follows:

Tape Copy Job (User Specified Source):

```
<Base Install Path>/tapecopy -s[source group] -d[destination group] -t[source tape name] {[source options] [destination options]}
```

Tape Consolidation Job (Database Specified Source):

```
<Base Install Path>/tapecopy -d[destination group] [query options] [-c[destination tape name] [destination options]}
```

Usage

The tapecopy commands allow you to set the following options and arguments:

- database query options
- source arguments
- destination arguments

Database Query Options

The database query options let you select source sessions based on specific attributes. When you specify a database option, the database is queried and all of the sessions that meet the search criteria become source sessions for tapecopy. One or more of these switches can be used to specify a complex query.

By default, the tapecopy operation copies all sessions that the query finds to one tape in the destination group. The tapecopy looks for a blank tape in the destination group and formats it with the tape name as mm/dd/yyyy-hh:mm.

The tapecopy command includes the following query options:

tapecopy

```
[qType <Backup Session Type>]
[qMethod <Backup Session Method>]
[qNode <Backup Session Node>]
[qOnOrBefore <MM/DD/YYYY>[<hh:mm>]]
[qOnOrAfter <MM/DD/YYYY>[<hh:mm>]]
[qMID <Master Job Number>]
[qJobNo <Job No Query>]
[qMediaPool <Media Pool Name>]
[qPreview (View Query Details)]
[qIgnoreRep (Ignore Replication Flag)]
[qExclude <Exclude List File Name>]
[qPastTime <Number of Days>]
[qCA_RHA Type <Type of CA RHA Session>](Used only with -qType CA_RHA)
```

-qType <Backup Session Type>

Queries the CA ARCserve Backup database to include only selected type of sessions for copy.

You can query multiple session types at the same time, by specifying the session types separated by comma.

For example:

```
tapecopy -d PGROUP0 -qType SQL,WindowsNT
```

Available session types include:

NetWare, MSNetDrive, UNIX, BABDatabase, OracleLog, DBAGENT, SYBASE, LotusNotes, Informix, TAR, CPIO, UNIXImage, WindowsNT (Includes WinNT/2000/XP), Windows98 (Includes Win95/98/ME), NTSAP, UNIXSAP, ORACLE, ORACLE8, ORACLE9I, NTOracle, UNIXRAW, UNIXSYBASE, UNIXORACLERMAN, WINORACLERMAN, DRTAR, CA_RHA, DBAEXDB, DBAEXDBVSS, DBAEXSIS, SQL, ASDBSQL, SQLDR, ASDBSQL, and SPA2007.

-qMethod <Backup Session Method>

Queries the CA ARCserve Backup database to include only those sessions that were backed up using the specified backup method.

Available session methods include:

FULL, DIFF, and INCR.

(Where FULL = full backup, DIFF = differential backup, and INCR = incremental backup)

-qNode <Backup Session Node>

Queries the CA ARCserve Backup database to include sessions backed up from the specified node only.

-qOnOrBefore <MM/DD/YYYY> [<hh:mm>]

Queries the CA ARCserve Backup database to include sessions that were backed up on or before the specified date and time. It is optional to specify the time. Date and time should be separated by a space.

-qOnOrAfter <MM/DD/YYYY> [<hh:mm>]

Queries the CA ARCserve Backup database to include sessions that were backed up on or after the specified date and time. It is optional to specify the time. Date and time should be separated by a space.

-qMID <Master Job Number>

Queries the CA ARCserve Backup database to include all sessions subordinate to the Master Job Number.

This option is used for consolidating multistreaming sessions. It queries the CA ARCserve Backup database for all sessions subordinate to the master job number of a multistreaming job. The Master Job Number represents the job number of the parent multistreaming job.

-qJobNo <Job No Query>

Queries the CA ARCserve Backup database to include all sessions subordinate to the specified job number. Will search for sessions which belong to the specified job number and copy them to the destination media. For rotation jobs, this command will query the database for all sessions related to each job ID for the specified job number and then copy all sessions to the destination media.

This switch can also be used in conjunction with other query switches to further limit the sessions to be copied.

-qMediaPool <Media Pool Name>

Queries the CA ARCserve Backup database to include tapes belonging to the specified Media Pool. It supports searches based on wildcard characters like * and ?.

-qPreview (View Query Details)

Puts tapecopy in Preview mode so that tapecopy only displays a list of sessions that satisfy the query criteria. The actual tapecopy operation is not performed.

This option gives a more in-depth view of the query result set. Use this with the database query options so that you do not commit to executing a copy routine. Instead, you will view the query result set in detail.

-qIgnoreRep (Ignore Replication Flag)

Used to ignore the replication flag so that sessions that were already copied by tapecopy are included. If you ignore the flag, the previously copied sessions are ignored by tapecopy.

-qExclude <Exclude List File Name>

Queries the CA ARCserve Backup database to exclude the specified list of file host names stored in a file located in the config directory under the CA ARCserve Backup home directory.

-qPastTime <Number of Days>

Queries the CA ARCserve Backup database to include sessions that were backed up during the last specified number of days. Days are counted in duration of 24 hours starting from the time the tapecopy operation is run. The difference in number of days in each month is taken into consideration.

Cannot be used in conjunction with the -qOnOrBefore or -qOnOrAfter options.

-qCA_RHAType <Type of CA RHA Session>

Note: Used only with -qType CA_RHA.

Queries the CA ARCserve Backup database to include only the specified type of CA_RHA sessions for copy. Available CA_RHA sessions are FileSystem, MSSQL, and Exchange.

If you do not specify the type of CA_RHA session to be queried, by default all CA_RHA sessions will be included.

Destination Arguments

The `tapecopy` command destination arguments allow you to specify where the selected media is copied to. After you have selected the media you want to copy, you can select the destination and destination options for the `tapecopy` job.

Note: `Tapecopy` cannot create a target tape which is exactly same as the source tape when the source or target is a deduplication device. The exact same means that three items (tape name, sequence number, and random ID) are the same for the source tape and the target tape. In order to avoid this case, you must use `-c` or `-idr` switch to make the destination deduplication device different from the source tape.

The `tapecopy` command line utility supports the following destination arguments:

```
tapecopy
  [-rd <remote server name>]
  [-zd <destination sequence no.>]
  [-d <destination group name>]
  [-c <destination tape name>]
  [-v <vault name>]
  [-k (Force Vaulting on Incomplete Copy)]
  [-m <Assign Media Pool Name>]
  [-max <# of days>]
  [-idd <Destination Random ID>]
  [-idr (Auto-Generate Random ID)]
  [-o (Overwrite)]
  [-off (Offline)]
  [-ex (Export)]
  [-wd <Wait On Destination Tape in Minutes>]
  [-g]
  [-forceMerge (Turn on Detail Merge)]
  [-jid <Job ID>]
  [-wormDst]
  [-fDstMux]
  [-eject <Eject Media>]
  [-dIgnoreFSDGroup]
  [-dpp <weeks:days:hours:minutes>]
```

-rd <remote server name>

Specifies the name of the remote destination server to copy to. Use this when you want to send data to a remote host.

When using the -rd switch, the following limitations apply:

- The -rd switch should not be used when the destination is a remote deduplication device or an FSD.
- The -rd switch should only be used between CA ARCserve Backup servers.

-zd <destination sequence no.>

Specifies the destination sequence number to copy to. This distinguishes between sequence numbers when you use the -c option.

-d <destination group name>

Specifies the name of the group to copy to. If you omit this option, any available group is used. Omitting the -d switch allows the Tape Copy program to decide the best available destination group for your tape copy operation.

-c <destination tape name>

Specifies the target tape name to copy to. Use this to specify the format name for blank tapes. If the target tape is part of a specified tape key (uniquely identified target tape), use this to specify the name of a tape to search for and append or overwrite to.

Note: You can use this switch when the destination tape is a deduplication device.

-v <vault name>

Specifies a vault name for the newly created tape to be added to. You must have MMO configured so that you can specify vaulting tapes from the command line.

-k (Force Vaulting on Incomplete Copy)

Used only with the -v option. If you use this, the destination tapes will still be marked as vaulted on an incomplete tapecopy.

-m <Assign Media Pool Name>

Assign tape to media pool option. Use this option when you want to assign your newly consolidated tape to a media pool.

This switch helps automate scheduled, unattended tapecopy jobs. When you use this, the tapecopy job searches for a target Save Set tape in the specified media pool to append to. If a Save Set tape does not exist, it searches for a scratch tape to format and use as the target tape. If a save or scratch tape does not exist, it tries to connect to a blank tape and format it as its target tape.

-max <# of days>

This option is used with the -m option and specifies the maximum number of days you are allowed to append to the target Save Set tape in the specified media pool.

If the current number of days since the last format time is greater than the specified maximum number of days, the tapecopy will skip this media as the destination media.

If the end user does not use this option, the default value maximum number of days is 2000 days.

-idd <Destination Random ID>

Specifies the random ID of the destination tape.

-idr (Auto-Generate Random ID)

Destination random ID option. Use this option to copy to tapes with an auto generated random ID.

Note: You can use this switch when the destination tape is a deduplication device.

-o (Overwrite)

Overwrite option. Use this when specifying a target tape key (tape name, random ID, and sequence number). If you use this option, you must also use -c, -zd, and -idd.

-off (Offline)

Offline option. Offlines the target tapes at the end of the copy operation. This switch is valid for changers only.

-ex (Export)

Exports target tapes at the end of the copy operation. This switch is valid for changers only.

-wd <Wait On Destination Tape in Minutes>

Specifies the timeout in minutes for a successful connection to a destination tape. The default is 60 minutes.

-g

When called, will inform you that Tapecopy command will not automatically merge tapes into the database after the tapecopy operation is completed. Instead the Tapecopy command will link the copied session with the source session in the database during the tapecopy operation. If you still want to merge sessions after tapecopy, you can use the -forceMerge switch.

It is not necessary to include this switch in command line if you just want to link the sessions. Tapecopy will link the sessions even if this switch is not present.

-forceMerge

Specifies to the `tapcopy` command to force running the merge process after the `tapcopy` operation is completed. Generally, using this switch is not necessary because the `Tapcopy` command will automatically link the copied session with the source session in the database during the `tapcopy` operation. However, if for some reason the source session is not in the database (information may have been purged or source tape may have been moved to a different location), this linking will not occur. In these cases, you can use this switch to force the merging of the copied session with the source session.

-jid <Job ID>

Specifies the Job ID.

`Tapcopy` will write its activity log information into the activity log that belongs to the job that is specified by this parameter.

- If you are using this parameter and the job id exists, all the `tapcopy` activity log information will be included in the activity log for the specified job.
- If you are using this parameter and the job id does not exist, all the `tapcopy` activity log information will be ignored.
- If you do not use this parameter, all the `tapcopy` activity log information will be included in a generic log.

-wormDst

Filters destination media such that only WORM capable media are included in the collection of destination media to choose from. This option ensures that you are copying to WORM media.

-fDstMux

Use this if you want source sessions to be copied in a multiplexing (MUX) format to the destination media. If your destination media is blank, it will be formatted as a multiplexing media.

Notes:

- You cannot append a multiplexing session to a non-multiplexing media format.
- `Tapcopy` does not support MUX-to-MUX copying of encrypted data.

-eject <Eject Media >

The `eject` option. Use this option to eject the target media.

-dIgnoreFSDGroup

Specifies to ignore or not allow using the FSD group as the target group.

-dpp <weeks:days:hours:minutes>

Specifies a purge policy time for destination sessions.

CA ARCserve Backup will purge these sessions after this purge policy time expired. This option can only be used when destination tape is a deduplication device.

This option is divided into four time fields: weeks, days, hours and minutes, and should be set to zero if not needed. By default, the purge policy time is four weeks.

- If you included this option, but destination is not a deduplication device, `tapecopy` will display a prompt to inform you that this option can only be used for a deduplication target and the purge policy you specified will be ignored.
- If you included this option and the destination is a deduplication tape, `tapecopy` will display a prompt to inform you that the target sessions will be purged after XX weeks, XX days, XX hours, and XX minutes.
- If you have not included this option, but the destination is a deduplication device, `tapecopy` will display a prompt to inform you that by default, a 4-week purge policy will be used.

Source Arguments

The `tapecopy` command source arguments allow you to specify the data to be copied. You can use these arguments to identify the group, tape, and sessions to be used in your tape copy operation.

The `tapecopy` command includes the following source arguments:

`tapecopy`

```
[-n <beginning session number to be copied>]
[-ntotal <number of sessions>]
[-rs <Remote Server Name>]
[-entire (copy all non-blank in group)]
[-t <source tape name>]
[-zs <source sequence no.>]
[-s <source group name>]
[-ids <source random ID>]
[-ws <wait on source in minutes>]
[-wormSrc]
[-srcPassList [<source password list file name>]]
```

-n <beginning session number to be copied>

Specifies the starting session number to begin copying from on the source tape. This cannot be used with query switches.

-ntotal <number of sessions>

Use this with the -n option. Allows you to specify the total number of sessions to copy beginning with the -n value you enter. This cannot be used with query switches.

-rs <Remote Server Name>

The remote source server name. Use this when you want to receive data from a remote host.

-entire (copy all non-blank in group)

Copy group option. Use this to copy all of the tapes in a group to another group. This switch is valid only within a changer.

-t <source tape name>

The source tape name. Use this to specify the name of the tape you want to copy. This cannot be used with the query switches.

-zs <source sequence no.>

The source sequence number. Use this to distinguish between the sequence numbers when you use the -t option. This cannot be used with query switches.

-s <source group name>

The source group name. Use this to specify the source group name where your tape is located. Do not use this with the query switches.

-ids <source random ID>

Source random ID option. Use this to copy tapes with a specific random ID.

-ws <wait on source in minutes>

Specifies a timeout limit for session availability. The session may be on a tape that is currently being used.

Default timeout: 60 minutes.

-srcPassList [`< source password list file name >`]

Specifies to get the password list to decrypt any encrypted source sessions (server side encryption sessions only).

There are two modes to initialize a password list: automatic mode and interactive mode.

The automatic mode allows you to provide a password list file using a command such as `"-srcPassList < passwords.txt"`.

In this mode, all required session passwords will be searched in the specified password list file and the copy process will proceed without any further user input. If you don't specify a password list file, you will be prompted to provide the password in the interactive mode.

For example:

```
Please enter source password[Enter when done]: ****
Please enter source password[Enter when done]: ****
Please enter source password[Enter when done]: <enter>
Received 2 passwords for source.
```

Each password should be included in a separate line in the password list file.

If you specify this option, `tapecopy` will attempt to find a matching encrypted session password for the source password provided. If it fails find a match, `tapecopy` will then query the session password from the CA ARCserve Backup database. If `tapecopy` still cannot find any matched session password this encrypted session will be skipped from the copy process. In addition, agent side encryption will not be treated as an encrypted session for `tapecopy`. As a result, this type of session will be treated as a normal session and `tapecopy` will not perform a password check.

When all passwords for the sessions to be copied have been saved in the CA ARCserve Backup database, you do not need to specify this option. All session passwords will then be queried from the CA ARCserve Backup database using the password management utility. However, if all passwords for the sessions to be copied have not been saved in the CA ARCserve Backup database, you will need to specify this option to provide session passwords.

Note: `Tapecopy` can accept a maximum of 8 passwords at the same time, with each password containing a maximum of 24 characters.

Examples

The following are examples of syntax for the `tapecopy` command:

Note: For each `tapecopy` command, you must include a blank space between the switch and the syntax that follows the switch.

- Use the following command to copy all sessions from nodes named AL2000 before noon, September 25, 2006:

```
tapecopy -d GROUP1 -qNode AL2000 -qOnOrBefore (9/25/2006,12:00)
```

- Use the following command to copy all incremental sessions after noon, September 25, 2006:

```
tapecopy -d GROUP1 -qMethod INCR -qOnOrAfter (9/25/2006,12:00)
```

- Use the following command to append all multistreaming sessions from a given Master Job ID to a tape named "Everything":

```
tapecopy -d GROUP1 -qMID 232 -c Everything -idd F56 -zd 1
```

- Use the following command to copy all sessions from all hosts except those in an Exclude List and specify a timeout of 10 minutes on connecting to source media and two hours on connecting to target media:

```
tapecopy -d GROUP1 -qNode * -qExclude AcctExcludes.txt -ws 10 -wd 120
```

- Use the following command to copy all sessions from nodes named AL2000 in the last 24 hours and add to Media Pool "MyPool."

Note: Using the `-m` switch causes the `tapecopy` job to search for a target save/scratch/blank tape in the specified media pool. If a Save Set tape does not exist, CA ARCserve Backup searches for a scratch/blank tape to format and use as the target tape:

```
tapecopy -d GROUP1 -qNode AL2000 -qPastTime 1 -m "MyPool"
```

- Use the following command to copy all sessions between noon, September 25, 2006 and September 26, 2006 by its Job Number:

```
tapecopy -d GROUP1 -qOnOrAfter (9/25/2006,12:00) -qOnOrBefore "(9/26/2006,12:00)" -qJobNo 21
```

- Use the following command to append all session from source tape name "TAPE 1" to target name "TAPE 2":

```
tapecopy -s GROUP0 -d GROUP1 -t "TAPE 1" -c "TAPE 2" -idd C86 -zd 1
```

- Use the following command to copy all session from source tape name "TAPE 1" and format blank target tape name to "TAPE 2":

```
tapecopy -s GROUP0 -d GROUP1 -t "TAPE 1" -c "TAPE 2"
```

- Use the following command to copy from local source tape to remote blank tape:

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -rd SERVERNAME
```

- Use the following command to copy from remote source tape to local blank tape:

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -rs SERVERNAME
```

- Use the following command to copy all sessions from source tape and export the target tape:

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -ex
```

- Use the following command to copy all sessions from source tape and offline the target tape:

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -off
```

- Use this command to copy all sessions starting from session 3 on source tape:

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -n 3
```

- Use the following command to copy all non-blank tapes from source group and export target tapes:

```
tapecopy -s GROUP0 -d GROUP1 -entire -ex
```

- Use the following command to copy the 3 sessions after session 6 starting from session 6 on source tape:

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -n 6 -ntotal 3
```

- Use the following command to copy from a source tape to a destination tape when the session has been encrypted on the server side (interactive mode):

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -srcPassList
```

- Use the following command to copy from a source tape to a destination tape when the session has been encrypted on the server side (automatic mode):

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -srcPassList < passwords.txt
```

- Use the following command to copy all sessions that were created during last 1 day to a blank tape in group PGROUP0. During the copy, it will link the source and destination sessions.

```
tapecopy -q PastTime 1 -d pgroup0 -g
```

- Use the following command to copy all sessions that were created during last 1 day to a blank tape in group PGROUP0. After the copy operation is complete, it will submit a merge job to merge all the copied sessions from the target tape into the database.

```
tapecopy -q PastTime 1 -d pgroup0 -forceMerge
```

- Use the following command to copy all sessions created by job number 100 (-qJobNo 100) to a blank tape in group PGROUP0 (-d pgroup0).

```
tapecopy -qJobNo 100 -d pgroup0
```

- Use the following command to copy all sessions created by job number 100 (-qJobNo 100) within last 1 day (-qPastTime 1) to a blank tape in group PRGROUP0 (-d pgroup0).

```
tapecopy -qJobNo 100 -qPastTime 1 -d pgroup0
```

- Use the following command to set a 1 minute purge policy for a deduplication device target session (you need to specify target tapename using -c switch).

```
tapecopy -s GROUP0 -d GROUP1 -t TAPE1 -c TAPE2 -dpp 00:0:1
```

Chapter 24: Miscellaneous Utility Commands

The following miscellaneous utility commands are used with CA ARCserve Backup:

- DumpDB
- IsSafe.bat
- Mergecat.exe
- MergeOLF.exe

DumpDB Utility

The DumpDB utility is used to import and export session passwords to and from the CA ARCserve Backup database. The DumpDB utility dumps only session passwords, it will not export other information about a session. You should run the DumpDB utility on a regular basis so that you can import the session password information back into the database.

Important! If you execute this utility after a database has been purged or pruned, session passwords will not be exported. Therefore, it is important that this utility is run prior to purging or pruning a database.

Syntax

```
DumpDB.exe -ExportTo <filename> [-from startTime] [-to endTime] [-password <password>]
```

```
DumpDB.exe -ImportFrom <filename> [-password <password>]
```

```
DumpDB.exe -as [[-domain\]primary] -exportTo [filename] [-from startTime] [-to endTime] [-password <password>]
```

```
DumpDB.exe -as [[-domain\]primary] -importFrom [filename] [-password <password>]
```

-as

Lists all of the domains in the CA ARCserve Backup database that are used by the local CA ARCserve Backup server, and then closes.

Important! The DumpDB -as argument lets you analyze only the CA ARCserve Backup database associated with the CA ARCserve Backup server where you execute the utility. The utility not analyze data in any other CA ARCserve Backup database.

-as primary

If you specify a primary server name, DumpDB searches the CA ARCserve Backup database and responds as follows:

- If DumpDB does not detect the server name in the CA ARCserve Backup database, DumpDB closes.
- If DumpDB detects one record of the server name in the CA ARCserve Backup database, DumpDB completes the execution.
- If DumpDB detects more than one record of the server name in the CA ARCserve Backup database, DumpDB warns you and then closes.

Note: This argument must be used with -exportTo and -importFrom.

-as domain\primary

If you specify a primary server name and a domain name, DumpDB searches the CA ARCserve Backup database and responds as follows:

- If DumpDB does not detect the server name and domain name in the CA ARCserve Backup database, DumpDB closes.
- If DumpDB detects one record of the server name and domain name in the CA ARCserve Backup database, DumpDB completes the execution.
- If DumpDB detects more than one record of the server name and domain name in the CA ARCserve Backup database, DumpDB warns you and then closes.

Note: This argument must be used with -exportTo and -importFrom.

-ExportTo

Exports session passwords stored in a database to specified target file.

-password

If include this switch and specify a password during exporting, the output file will be encrypted by this password.

-ImportFrom

Imports session passwords stored in a specified file to a database.

-password

If you included a password during exporting, you will need to input the correct password during importing, otherwise the import operation will fail.

Time format:

The time format for scheduling when to run the DumpDB utility can be specified as a calendar time period or a number of days ago time period.

- To specify calendar date, use the following format:

YYYYMMDD[hh[mm[ss]]]

Note: The year, month, and day are required. The hours, minutes, and seconds are optional.

- To specify a number of days ago, use the following format:

nnnn(0 <= nnnn <= 9999)

Note: The parameter range for number of days ago is 0-9999.

Examples: Syntax

The following are examples of syntax for the DumpDB utility:

- The example that follows exports session passwords for the previous 100 days:

```
DumpDB.exe -exportto "c:\sesspwd\dump.out" -from100
```

- The example that follows exports session passwords for all days since January 1, 2008:

```
DumpDB.exe -exportto "c:\sesspwd\dump.out" -from20080101
```

- The example that follows imports session passwords to the database:

```
DumpDB.exe -importfrom "c:\sesspwd\dump.out"
```

Note: The imported session passwords can only be accessed by current ARCserve Domain

- The example that follows lists all of the domains in the CA ARCserve Backup database that are used by the local CA ARCserve Backup server.

```
DumpDB.exe -as
```

- The example that follows exports session passwords for specified primary:

```
DumpDB.exe -as primaryname -exportto "c:\sesspwd\dump.out"
```

- The example that follows imports session passwords to the database for specified primary:

```
DumpDB.exe -as primaryname -importfrom "c:\sesspw d.dump.out"
```

Note: The imported session passwords can only be accessed by the CA ARCserve Backup domain that relates to the specified primary server.

- The example that follows exports session passwords from domain "GREEN" with primary server "APPLE" and imports them into domain "PURPLE" with primary server "GRAPE:"

```
DumpDB.exe -as green\apple -exportto "c:\sesspw d.green.out"
```

```
DumpDB.exe -as purple\grape -importfrom "c:\sesspw d.green.out"
```

- The example that follows exports session passwords from domains "GREEN" with primary server "APPLE" and "RED" with primary server "GRAPE", and imports them into domains "PURPLE" with primary server "PLUM" and "ORANGE" with primary server "MANGO," when domains "GREEN" and "RED" are from of an ARCserve Database that was restored over the ARCserve Database used by domains "PURPLE" and "ORANGE" using the "Preserve ARCserve Domain Memberships" option:

```
DumpDB.exe -as green$apple$ -exportto "c:\sesspw d.green.out"
```

```
DumpDB.exe -as red$grape$ -exportto "c:\sesspw d2.red.out"
```

```
DumpDB.exe -as purple\plum -importfrom "c:\sesspw d.green.out"
```

```
DumpDB.exe -as orange\mango -importfrom "c:\sesspw d2.red.out"
```

IsSafe.bat Utility

The IsSafe.bat utility checks the operating system for any CA ARCserve Backup processes that are active to determine if it is safe to shutdown the system.

- If the utility detects that a CA ARCserve Backup process is active and it is in the backup stage, it will prompt you that it is not safe to shutdown the operating system.

System is running backup job now. It is not safe to shutdown.

- If the utility detects that a CA ARCserve Backup process is active and it is in the merge stage, it will prompt you that it is not safe to shutdown the operating system.

System is running merge job now. It is not safe to shutdown.

- If the utility detects that there are no active CA ARCserve Backup processes, it will prompt you that it is safe to shutdown the operating system.

It is now safe to shutdown your system.

- If the utility detects that the current OS is earlier than Windows XP SP2, it will prompt the following message.

IsSafe.bat does not support the current operating system version.

The following codes are returned by the IsSafe.bat utility:

Return Codes:

- 0** - It is now safe to shut down your system
- 1** - System is running backup job now. It is not safe to shut down.
- 2** - System is running merge job now. It is not safe to shut down.
- 3** - IsSafe.bat does not support the current operating system version.

Mergecat Utility

The Merge Catalog utility (mergecat.exe) can be used to manually merge in any .cat files that remain in the ARCserve Backup\temp directory.

During a backup, the database information is written to a .tmp file. At the end of that backup session the .tmp is changed to a .cat file and is written to tape as the last file in that session. In addition, at the end of a backup the mergecat.exe utility is spawned and will merge all the *.cat files into the database regardless of which job they are from.

By running the mergecat utility, CA ARCserve Backup will take all the .cat files from the ARCserve Backup\catalog.db directory, and merge them into the database.

Note: The mergecat.exe utility is not to be used to manually merge cat files from tape, rather it is to be used to merge .cat files that have been leftover in the ARCserve Backup\catalog.db directory.

The mergecat utility is located in the following directory:

```
C:\Program Files\CA\ARCserve Backup>mergecat.exe
```

Usage :

```
MERGECAT.EXE /F:00000000.CAT /D:[0/1]
  /F: CATALOG.CAT - Default is to merge all catalogs
  /D:1 - Default is to delete catalog file after merging it
```

When a .cat file is initially written, the Read attribute is disabled for that file. After the .cat files are processed by the mergecat utility, the Read-Only attribute is automatically applied by default. If you need to merge a .cat file into a SQL database with the Read-Only attribute applied, run the following command:

```
mergecat /F:"<fulpath>.cat" /R
```

This will merge this catalog file into SQL database even if the Read-Only attribute is applied.

MergeOLF Utility

The MergeOLF utility lets you move licenses from one ARCserve system to another ARCserve system.

With this utility you can install new licenses on an ARCserve system that has existing licenses and merges multiple license files into a single file. This utility displays messages about the status in the console and generates the output in a file you specify. You run the command from a command line.

Syntax:

```
MERGEOLF <new_olf>[-c <current_olf>] [-o <output_olf>] [-b <backup_olf>] [-d <debug_log>]
```

-n <new_olf>

Specifies the name of the new OLF file to merge.

-c <current_olf>

Specifies the path and name of the current OLF file to merge.

Default: ca.olf

-o <output_olf>

Specifies the path and name of the new OLF file to create.

Default: ca.olf

-b <backup_olf>

Specifies the path and name of the backup of the current OLF file.

Default: ca.old

-d <debug_log>

Enables debugging and places information in the mergeolf.log file.

Example: Merge New License Into Old License File

The following example merges a new olf file that has been renamed to ca.nol into an existing ca.olf file

```
MERGEOLF -n ca.nol -c c:\program files\ca\SharedComponents\ca_lc\ca.olf -o c:\program files\ca\SharedComponents\ca_lc\ca.olf -b c:\program files\ca\SharedComponents\ca_lc\ca.old
```


Index

A

- Advanced Options - ca_backup • 53
- Advanced Reports Generator Command - caadvreports • 265
 - Introduction • 265
 - Options • 269
 - Reports • 266
- Arguments and Options • 14
- Authentication Command - ca_auth • 25
- Authentication Setup Command - authsetup • 17
- authsetup • 17
 - Examples • 18
 - Introduction • 17
 - Syntax • 17
 - Usage • 17

B

- bab • 19
 - Examples • 23
 - Introduction • 19
 - Syntax • 20
 - Usage • 21
- Backup Manager Command - ca_backup • 35
- Backup Media Options • 39
- Batch Command - ca_batch • 255
 - Delete a Job • 258
 - Introduction • 255
 - Modify a Job • 259
 - Submit a Job • 256
- Brackets - Square and Angle • 14

C

- ca_auth • 25
 - Equivalence Arguments • 32
 - Examples • 33
 - Introduction • 25
 - Miscellaneous Options • 27
 - Syntax • 26
 - Usage • 26
 - User Arguments • 28
- ca_backup • 35
 - Database Options • 64
 - Database Options - Exchange DB Level • 75
 - Database Options - Exchange DOC Level • 72

- Database Options - Informix Agent • 80
- Database Options - Lotus Agent • 84
- Database Options - Oracle • 65
- Database Options - Oracle RMAN • 67
- Database Options - SQL Server PUSH Agent • 76
- Database Options - Sybase Agent • 79
- Database Options - VSS Agent • 81
- Destination Arguments • 84
- Examples • 107
- Global Filters • 56
- Global Job Options • 39
- Global Job Options - Advanced Options • 53
- Global Job Options - Backup Media Options • 39
- Global Job Options - File Retry/Sharing Options • 44
- Global Job Options - Introduction • 39
- Global Job Options - Log Options • 50
- Global Job Options - Media Exporting Options • 52
- Global Job Options - Operation Options • 45
- Global Job Options - Pre/Post Options • 48
- Global Job Options - Verification Options • 43
- Global Job Options - Virus Options • 51
- Global Job Options - VSS Options • 55
- Introduction • 35, 64
- Job Status Return Codes • 106
- Miscellaneous Options • 37
- Node Options • 61
- Run Job Arguments • 94
- Schedule Arguments • 86
- Source Arguments • 59
- Staging Options • 95
- Staging Options - Full Backup Options • 99
- Staging Options - Incremental/Differential Backup Options • 100
- Staging Options - Introduction • 95
- Staging Options - Miscellaneous Options • 96
- Syntax • 35
- Usage • 36
- Volume Options • 63
- ca_dbmgr • 111
 - Database Management Options • 117
 - Display Options • 114
 - Examples • 120

Introduction • 111
Maintenance Options • 118
Media Pool Management Options • 116
Migration Status Options • 119
Miscellaneous Options • 113
Syntax • 111
Usage • 112

ca_devmgr • 123
Examples • 145
FSD Options • 134
General Options • 125
Introduction • 123
Miscellaneous Options • 124
Syntax • 123
Tape Drive Options • 127
Tape Library Options • 129
Usage • 124

ca_jobsecmgr • 147
Current Security • 148
Examples • 149
Introduction • 147
New Security Options • 149
Server Arguments • 148
Syntax • 147
Usage • 147

ca_log • 151
Examples • 156
Introduction • 151
Log Name Manipulation Options • 152
Miscellaneous Options • 152
Purge Options • 155
Syntax • 151
Usage • 151
View Options • 153

ca_merge • 157
Examples • 166
Introduction • 157
Job Status Return Codes • 166
Merge Options • 161
Miscellaneous Options • 158
Run Job Arguments • 160
Source Arguments • 159
Syntax • 157
Usage • 158

ca_mmo • 169
Examples • 173
Introduction • 169
Options • 171
Syntax • 170

ca_qmgr • 175
Examples • 185
Introduction • 175
Job Queue Commands • 178
Job Script Commands • 180
Job Specific Commands • 180
Miscellaneous Options • 177
Syntax • 176
Usage • 177

ca_recoverdb • 187
Options • 189
Syntax • 188

ca_restore • 191
Database Options • 207
Database Options - Exchange DB Level • 216, 217
Database Options - Informix Agent • 224
Database Options - Introduction • 207
Database Options - Lotus Agent • 226
Database Options - Oracle • 209
Database Options - Oracle RMAN • 211
Database Options - SQL Server PULL Agent • 219
Database Options - Sybase Agent • 224
Database Options - VSS Agent • 225
Destination Arguments • 206
Examples • 231
Global Filter Options • 202
Global Job Options • 194
Global Job Options - Destination Options • 195
Global Job Options - Introduction • 194
Global Job Options - Log Options • 200
Global Job Options - Operation Options • 197
Global Job Options - Pre/Post Options • 199
Global Job Options - Restore Media Options • 194
Global Job Options - Virus Options • 201
Info Arguments • 228
Introduction • 191
Miscellaneous Options • 192
Run Job Arguments • 227
Source Arguments • 204
Syntax • 191
Usage • 192

ca_scan • 233
Decryption Password List Options • 238
Examples • 242
Exit Code Options • 240

- Introduction • 237
- Introduction • 233
- Job Status Options • 241
- Logging Options • 238
- Media Options • 240
- Miscellaneous Options • 234
- Miscellaneous Scan Options • 241
- Pre/Post Options • 239
- Run Job Arguments • 236
- Source Arguments • 235
- Syntax • 233
- Usage • 233
- caadvreports • 265
 - Examples • 272
 - Introduction • 265
 - Options • 269
 - Reports • 266
 - Syntax • 265
- cabatch • 255
 - Delete a Job • 258
 - Examples • 260
 - Introduction • 255
 - Modify a Job • 259
 - Submit a Job • 256
- careports • 261
 - Examples • 263
 - Introduction • 261
 - Options • 262
 - Syntax • 261
- CLI • 13
- Current Security Options • 148
- D**
- Database Management Options - ca_dbmgr • 117
- Database Manager Command - ca_dbmgr • 111
- Database Options
 - ca_backup Database Options • 64
 - ca_restore Database Options • 207
- Database Query Options - tapecopy • 282
- Database Recovery Command - ca_recoverdb • 187
- Delete a Job • 258
- Destination Arguments
 - ca_backup Destination Arguments • 84
 - ca_restore Destination Options • 206
 - ca_restore Global Destination Options • 195
 - tapecopy Destination Arguments • 285
- Device Manager Command - ca_devmgr • 123

- Disk Staging Options
 - Introduction • 95
 - Staging Options - Full Backup Options • 99
 - Staging Options - Incremental/Differential Backup Options • 100
 - Staging Options - Miscellaneous Options • 96
- Display Options - ca_dbmgr • 114
- DumpDB Utility • 295

E

- Ellipsis • 14
- Examples
 - authsetup Examples • 18
 - bab Examples • 23
 - ca_auth Examples • 33
 - ca_backup Examples • 107
 - ca_dbmgr Examples • 120
 - ca_devmgr Examples • 145
 - ca_jobsecmgr Examples • 149
 - ca_log Examples • 156
 - ca_merge Examples • 166
 - ca_mmo Examples • 173
 - ca_qmgr Examples • 185
 - ca_restore Examples • 231
 - ca_scan Examples • 242
 - caadvreports Examples • 272
 - cabatch Examples • 260
 - careports Examples • 263
 - pfc Examples • 278
 - tapecomp Examples • 280
 - tapecopy Examples • 292
- Exchange Database Options
 - ca_backup Exchange DB Options • 75
 - ca_backup Exchange DOC Options • 72
 - ca_restore Exchange DB Options • 217
 - ca_restore Exchange DOC Options • 216

F

- File Retry/Sharing Options • 44
- File System Device Options - ca_devmgr • 134
- Filters
 - ca_backup Global Filter Options • 56
 - ca_restore Global Filter Options • 202
- FSD Options - ca_devmgr • 134

G

- General Options - ca_devmgr • 125
- Global Filters
 - ca_backup Global Filter Options • 56

- ca_restore Global Filter Options • 202
- Global Job Options
 - ca_backup Global Job Options • 39
 - ca_restore Global Job Options • 194

I

- Info Arguments - ca_restore • 228
- Informix Database Options
 - ca_backup Informix Options • 80
 - ca_restore Informix Options • 224
- Introduction • 13
- IsSafe.bat Utility • 299
- Italics • 14

J

- Job Queue Commands - ca_qmgr • 178
- Job Script Commands - ca_qmgr • 183
- Job Security Manager Command - ca_jobsecmgr • 147
- Job Specific Commands - ca_qmgr • 180

L

- Log Name Manipulation Options - ca_log • 152
- Log Options
 - ca_backup Log Options • 50
 - ca_restore Log Options • 200
- Lotus Database Options
 - ca_backup Lotus Options • 84
 - ca_restore Lotus Options • 226

M

- Maintenance Options - ca_dbmgr • 118
- Media Exporting Options • 52
- Media Management Administrator Command - ca_mmo • 169
- Media Options - ca_scan • 240
- Media Pool Management Options - ca_dbmgr • 116
- Merge Manager Command - ca_merge • 157
- Merge Options - ca_merge • 161
- MergeCat Utility • 300
- MergeOLF Utility • 301
- Migration Status Options - ca_dbmgr • 119
- Miscellaneous Options
 - ca_auth Miscellaneous Options • 27
 - ca_backup Miscellaneous Options • 37
 - ca_dbmgr Miscellaneous Options • 113
 - ca_devmgr Miscellaneous Options • 124
 - ca_log Miscellaneous Options • 152

- ca_merge Miscellaneous Options • 158
- ca_qmgr Miscellaneous Options • 177
- ca_restore Miscellaneous Options • 192
- ca_scan Miscellaneous Options • 234
- Miscellaneous Scan Options • 241
- Modify a Job • 259

N

- New Security Options - ca_jobsecmgr • 149
- Node Options - ca_backup • 61

O

- Operation Options
 - ca_backup Operation Options • 45
 - ca_restore Operation Options • 197
- Options - ca_mmo • 171
- Options and Arguments • 14
- Oracle Database Options
 - ca_backup Oracle Options • 65
 - ca_restore Oracle Options • 209
- Oracle RMAN Database Options
 - ca_backup Oracle RMAN Options • 67
 - ca_restore Oracle RMAN Options • 211

P

- pfc • 273
 - Examples • 278
 - Introduction • 273
 - Preflight Checks • 274
 - Syntax • 274
 - Usage • 274
- Pipes • 14
- Pre/Post Options
 - ca_backup Pre/Post Options • 48
 - ca_restore Pre/Post Options • 199
 - ca_scan Pre/Post Options • 239
- Preflight Checklist Utility Command - pfc • 273
- Preflight Checks • 274
- Purge Options - ca_log • 155

Q

- Queue Manager Command - ca_qmgr • 175

R

- Report Manager Command - ca_log • 151
- Report Writer Command - careports • 261
- Reports • 266
- Restore Media Options • 194

Run Job Arguments

- ca_backup Run Job Arguments • 94
- ca_merge Run Job Arguments • 160
- ca_restore Run Job Arguments • 227
- ca_scan Run Job Arguments • 236

S

Scan Manager Command - ca_scan • 233

Scan Options

- Decryption Password List Options • 238
- Logging Options • 238
- Pre/Post Options • 239

Schedule Arguments - ca_backup • 86

Security Options

- Current Security Options • 148
- New Security Options - ca_jobsecmgr • 149

Server Arguments - ca_jobsecmgr • 148

Source Arguments

- ca_backup Source Arguments • 59
- ca_merge Source Arguments • 159
- ca_restore Source Options • 204
- ca_scan Source Arguments • 235
- tapecopy Source Arguments • 289

SQL Server Database Options

- ca_backup SQL Server PUSH Options • 76
- ca_restore SQL Server PULL Options • 219

Staging Options

- Staging Options - Full Backup Options • 99
- Staging Options - Incremental/Differential Backup Options • 100
- Staging Options - Miscellaneous Options • 96

Submit a Job • 256

Sybase Database Options

- ca_backup Sybase Options • 79
- ca_restore Sybase Options • 224

Syntax

- authsetup Syntax • 17
- bab Syntax • 20
- ca_auth Syntax • 26
- ca_backup Syntax • 35
- ca_dbmgr Syntax • 111
- ca_devmgr Syntax • 123
- ca_jobsecmgr Syntax • 147
- ca_log Syntax • 151
- ca_merge Syntax • 157
- ca_mmo Syntax • 170
- ca_qmgr Syntax • 176
- ca_recoverdb Syntax • 188
- ca_restore Syntax • 191

- ca_scan Syntax • 233
- caadvreports Syntax • 265
- careports Syntax • 261
- pfcsyntax Syntax • 274
- tapecomp Syntax • 279
- tapecopy Syntax • 281
- Syntax Characters • 14

T

Tape Compare Command - tapecomp • 279

Tape Copy Tool Command - tapecopy • 281

Tape Drive Options - ca_devmgr • 127

Tape Library Options - ca_devmgr • 129

- tapecomp • 279
- Examples - tapecomp • 280
- Options - tapecomp • 279
- Syntax - tapecomp • 279

tapecopy • 281

- Database Query Options • 282
- Destination Arguments • 285
- Examples • 292
- Introduction • 281
- Source Arguments • 289
- Syntax • 281
- Usage • 281

U

Usage

- authsetup Usage • 17
- bab Usage • 21
- ca_auth Usage • 26
- ca_backup Usage • 36
- ca_dbmgr Usage • 112
- ca_devmgr Usage • 124
- ca_jobsecmgr Usage • 147
- ca_log Usage • 151
- ca_merge Usage • 158
- ca_qmgr Usage • 177
- ca_restore Usage • 192
- ca_scan Usage • 233
- pfcsyntax Usage • 274
- tapecopy Usage • 281
- User Arguments - ca_auth • 28

V

Verification Options • 43

View Options - ca_log • 153

Virus Options

- ca_backup Virus Options • 51

ca_restore Virus Options • 201
Volume Options - ca_backup • 63
VSS Database Options
ca_backup VSS Options • 81
ca_restore VSS Options • 225
VSS Options - ca_backup • 55