

CA SYSVIEW® Performance Management

User Guide

Version 14.0



This Documentation, which includes embedded help systems and electronically distributed materials, (hereinafter referred to as the "Documentation") is for your informational purposes only and is subject to change or withdrawal by CA at any time.

This Documentation may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of CA. This Documentation is confidential and proprietary information of CA and may not be disclosed by you or used for any purpose other than as may be permitted in (i) a separate agreement between you and CA governing your use of the CA software to which the Documentation relates; or (ii) a separate confidentiality agreement between you and CA.

Notwithstanding the foregoing, if you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all CA copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to CA that all copies and partial copies of the Documentation have been returned to CA or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, CA PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL CA BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF CA IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is CA.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2014 CA. All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

CA Technologies Product References

This document references the following CA Technologies products:

- CA Datacom®/DB (CA Datacom/DB)
- CA Easytrieve® Report Generator (CA Easytrieve)
- CA MIA Tape Sharing (CA MIA)
- CA MII Data Sharing (CA MII)
- CA MIM™ Resource Sharing (CA MIM)
- CA OPS/MVS® Event Management and Automation (CA OPS/MVS)
- CA Roscoe® Interactive Environment (CA Roscoe)
- CA Graphical Management Interface (CA GMI)
- CA SYSVIEW® Performance Management (CA SYSVIEW)
- CA SYSVIEW® Performance Management CA Datacom® Option (CA SYSVIEW CA Datacom Option)
- CA SYSVIEW® Performance Management Option for CICS (CA SYSVIEW Option for CICS)
- CA SYSVIEW® Performance Management Option for IMS (CA SYSVIEW Option for IMS)
- CA SYSVIEW® Performance Management Option for TCP/IP (CA SYSVIEW Option for TCP/IP)
- CA SYSVIEW® Performance Management Option for WebSphere MQ (CA SYSVIEW Option for WebSphere MQ)
- CA SYSVIEW® Performance Management for CA Application Performance Management (CA SYSVIEW for CA APM)

Contact CA Technologies

Contact CA Support

For your convenience, CA Technologies provides one site where you can access the information that you need for your Home Office, Small Business, and Enterprise CA Technologies products. At <http://ca.com/support>, you can access the following resources:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- CA Support policies and guidelines
- Other helpful resources appropriate for your product

Providing Feedback About Product Documentation

If you have comments or questions about CA Technologies product documentation, you can send a message to techpubs@ca.com.

To provide feedback about CA Technologies product documentation, complete our short customer survey which is available on the CA Support website at <http://ca.com/docs>.

Documentation Changes

The following documentation updates have been made since the last release of this documentation:

- Updated the [System Configuration Toolkit and Utilities](#) (see page 23) section - Removed SVC table.

Contents

Chapter 1: Overview 15

What Is CA SYSVIEW	15
Monitoring and Management for z/OS	16
Customize and Secure the Displays and Commands	17
Performance Monitor	17
Threshold-based Alerts	18
Command Facility	18
Interfaces	19
User Interface	19
The Options	20
Base Components	20
Toolkit and Utilities	21
The Options in More Detail	21
Option for z/OS	21
JES Feature	24
Option for CICS	26
Option for WebSphere MQ	29
CA Datacom Option	31
Option for IMS	32
Event Capture Option	33
Option for TCP/IP	33
The Components in More Detail	34
CA SYSVIEW for CA Insight DPM for DB2 Component	34
CA MIM Component	34
UNIX System Services Component	34
Workload Manager Component	35
CA Roscoe	36
MIB Browser	36
System Overview	36
System Condition Monitor	36

Chapter 2: Basic Skills 39

Menu Navigation	39
The Primary Option Menu	40
The Menu Command	40
Select an Option on a Menu	41

Learn the Displays	41
System Activity Display	42
Display Areas	43
Scroll the Displays	48
View the PF Key Settings	49
Default PK Key Settings	49
How to Enter Commands, Parameters, Subcommands, and Line Commands	49
Primary and Function Commands	50
Parameter Conventions	50
Enter Subcommands	53
Enter Line Commands	54
Create External Line Commands	54
Information about Commands	55
FIND Command—Find Information on a Display	56
Use the FIND PF Key	57
Number of Lines Searched	58
Obtaining Help	58
Access Online Help	58
Access Online Help from the Main Menu	60
Obtain Help within a Help Topic	64

Chapter 3: Basic Tasks **67**

Overview of Your Profile	67
Use the PROFILE Command	68
SET Command—Change Your Profile	69
Access the PROFILE Command Displays	69
How You Access Profile Displays	70
Change Your Options Using the PROFILE Displays	71
Review the PROFILE Sections	71
Update Your Profile	72
How to Change Your Display Format	72
Change the Initial Display Format Name	73
Define Command Line Placement	73
Change the Divider Lines Character	74
Change the Row/Col Field Display	74
Change the Separator Area	75
Change the PF Message Area	76
Display the PF Key Settings	76
How to Change PF Key Definitions	76
Change ISPF PF Keys	77
Change the PF Key Values for Different Displays	77

Initialization Command Options in the Profile	78
Change the Masking Characters.....	78
How to Work with Data on a Display	79
Change the Data Display Format.....	79
Change Parameter Values Using the Parameter Area	83
Change the Data Fields	84
Change the Order of Data on a Display	85
Select Particular Rows of Data to Display	88
Customize Your Display	90
Print a Display.....	91

Chapter 4: MVS Displays **93**

About the MVS Displays	93
DASD Units Display.....	93
Tasks Performed from the DASD Units Display.....	95
MVS Exception Alerts Display.....	95
Tasks Performed from the MVS Exception Alerts Display	96
Console Display	97
Tasks Performed from the Console Display	98
Processor Information Display	98
Tasks Performed from the Processor Information Display	99
Access the APF List Display.....	99
Tasks Performed from the APF List Display.....	100
Access the LINKLIST Libraries Display.....	100
Tasks Performed from the LINKLIST Libraries Display.....	101
Subsystem Detail Display	102
Tasks Performed from the Subsystem Display.....	103

Chapter 5: Job and Output Management **105**

About the Job and Output Management Displays	105
Job and Output System Activity Display.....	105
Tasks Performed from the System Activity Display	106
Job Summary Display	107
Tasks Performed from the Job Summary Display	107
Job Queues Display	108
Tasks Performed from the Job Queues Display	109
Printers Display	110
Tasks Performed from the Printers Display	110
System Log Display.....	111
Tasks Performed from the System Log Display.....	112

Chapter 6: System Overview Displays **113**

About the System Overview Displays.....	113
Accessing and Controlling the Displays	113
System Overview Menu	114
Displaying the Information Lines	114
Sample Displays.....	116
Screen Attributes	117
System Overview Data	118
Graph Fields	119
Condition Fields.....	119
Ready Fields	120
I/O Fields	120
Paging Fields.....	120
Common Fields.....	121

Chapter 7: UNIX System Services Displays **123**

About the USS Displays	123
USS Address Space List Display	123
Tasks Performed from the USS Address Space List Display	124
USS Mounted File Systems Display	125
Tasks Performed from the USS Mounted File Systems Display	125
System Configuration Options Display	126

Chapter 8: CICS Displays **127**

About the CICS Displays	127
CICS System Activity Display.....	127
Tasks Performed from the CICS System Activity Display	128
CICS Active Tasks Display	129
Tasks Performed from the CICS Active Tasks Display	130
CICS Dynamic Storage Areas Display	130
Tasks Performed from the CICS Dynamic Storage Areas Display	131
Transaction Log Display	132
Tasks Performed from the Transaction Log Display.....	133
CICS Degradation Analysis Display	133

Chapter 9: WebSphere MQ Displays **135**

About the MQ Displays	135
MQ Subsystem List Display	135
Tasks Performed from the MQ Subsystem List Display	136

MQ Exception Alerts Display	137
Tasks Performed from the MQ Exception Alerts Display	137
MQ Channel Status Display	138
Tasks Performed from the MQ Channel Status Display	139
MQ Local Queues Display.....	139
Tasks Performed from the MQ Local Queues Display.....	140
MQ Queue Manager Display	141

Chapter 10: IMS Displays **143**

About IMS Displays.....	143
IMS Subsystem List Display	143
Tasks Performed from the IMS Subsystem List Display	144
IMS Exception Alerts Display	144
IMS Pools Display	145
IMS Dependent Region List Display.....	146
IMS Common Queue Subtask.....	146
Display IMS Subsystem Shared Queues Group Information	146
Use the IMS SPOC to Issue IMS Commands	147

Chapter 11: CA Datacom Displays **149**

About the DATACOM Displays	149
DATACOM System Activity Display	149
Tasks Performed from the DATACOM System Activity Display	150
DATACOM Directory Areas Display	150
Tasks Performed from the DATACOM Directory Areas Display	151
DATACOM Directory Databases Display.....	152
Tasks Performed from the DATACOM Directory Databases Display	152
DATACOM MUF Identity Display	153
DATACOM MUF Active Tasks Display.....	153

Chapter 12: TCP/IP Displays **155**

About the TCP/IP Displays.....	155
Access the TCP/IP Stacks Display	155
Tasks Performed from the TCP/IP Stacks Display	156
Access the IP Users Display	157
Tasks Performed from the IP Users Display	158
Access the TCP/IP Connections Display.....	158
Tasks Performed from the TCP/IP Connections Display	159
Access the IP Devices Display	160
Tasks Performed from the IP Devices Display.....	160

Chapter 13: System Condition Monitor Displays **163**

How the System Condition Monitor Works	163
Access the SCM Display.....	164

Chapter 14: Cross-System Resource Monitoring Displays **167**

Cross-System Resource Monitoring	167
Display the Cross-System Connections	168
Control the Display of Cross-System Data.....	169
XSCMDS Command Display	171

Chapter 15: Using SDSFMIGRATE to Migrate from SDSF **173**

How to Activate the SDSFMIGRATE Option	173
Masking Characters for the SDSFMIGRATE Option	174

Chapter 16: Create Reports Using the CA Easytrieve Reporting Service **175**

About CA Easytrieve	175
Planning Reports	175
Generating Canned Reports	176
Sample JCL.....	176
Canned Report Keywords.....	177
Sample Output from Canned Reports	178
CICS Canned Reports.....	178
IMS Canned Reports.....	184
MVS Reports	185
WebSphere MQ Reports	192
Report Structure.....	194
Macros.....	195
SYSVCDEF Macro	196
SYSVPROC Macro	198
FILTERID Macro	199
SMFDATE Macro	199
SMFTIME Macro	200
STCKCONV Macro.....	200
SYSVFOR Macro.....	201
TOP Macro	202
SMF Record Descriptions	202

Chapter 17: Creating Command Displays **205**

User-Defined Displays	205
-----------------------------	-----

How to Create Displays206

Index **207**

Chapter 1: Overview

This section contains the following topics:

- [What Is CA SYSVIEW](#) (see page 15)
- [Performance Monitor](#) (see page 17)
- [Command Facility](#) (see page 18)
- [Interfaces](#) (see page 19)
- [User Interface](#) (see page 19)
- [The Options](#) (see page 20)
- [Base Components](#) (see page 20)
- [Toolkit and Utilities](#) (see page 21)
- [The Options in More Detail](#) (see page 21)
- [The Components in More Detail](#) (see page 34)

What Is CA SYSVIEW

This guide provides basic information for all users who are new to CA SYSVIEW and want to get started using it right away. In addition, the guide provides an overview of basic tasks you perform when you are using the resource displays. Users who work with those resources can:

- Perform these basic tasks
- Apply the knowledge they gain to their everyday work

CA SYSVIEW is a performance monitoring and management tool for your z/OS system environment. Using the full-screen displays, operators, systems programmers, performance analysts, and end users can monitor and manage the following resources:

Options

- CA SYSVIEW Option for z/OS (Base)
- CA SYSVIEW Option for CICS
- CA SYSVIEW Option for WebSphere MQ
- CA SYSVIEW Option for IMS
- CA SYSVIEW CA Datacom Option
- CA SYSVIEW Event Capture Option
- CA SYSVIEW for TCP/IP Option
- CA SYSVIEW for CA APM

Components

- CA SYSVIEW for CA Insight DPM for DB2 component
- CA MIM component
- CA Roscoe component
- Cross-System component
- System Condition Monitor (SCM) component
- UNIX System Services (USS) component

In addition to its monitoring and analysis tools, CA SYSVIEW allows authorized users to change dynamically the system to avoid costly outages and unscheduled IPLs.

Note: References to the MVS and z/OS operating systems throughout this guide pertain to the supported versions of z/OS operating systems.

Monitoring and Management for z/OS

CA SYSVIEW:

- Combines many displays for system resources with a powerful command facility that lets you take appropriate actions in managing your z/OS environment.
- Enables, from a single session, the monitoring of, but not limited to, the following resources:
 - Overall z/OS system activity
 - DASD and CPU usage
 - I/O rates and storage usage of a particular address space
 - CICS task and transaction details
 - A selected CA Datacom/DB MUF
 - A WebSphere MQ queue
 - An IMS region
 - TCP/IP configuration, and more
- Provides the ability for you to:
 - Fully manage JES2 resources and jobs.
 - Show the system configuration and definitions.
- Provides the Cross-System Resource Monitoring facility. This facility lets you view, monitor, and manage multiple z/OS images remotely from one interface without using a session manager.

- Provides a System Condition Monitor (SCM), which is a color-coded, high-level summary screen of resources that are currently being monitored. SCM uses intelligent modules (IMODs) written in compiled REXX with more CA supplied functions, or IMODs, to communicate with monitored subsystems. For more IMOD information, see the *Administration Guide*.
- Provides a System Overview menu, which lets you display an overview of the current z/OS system status. This component enhances the monitoring of all CA SYSVIEW commands and functions.

Customize and Secure the Displays and Commands

In addition to its vast monitoring capabilities, you can:

- Dynamically change your systems and environments.
Using CA SYSVIEW commands, you can initiate actions such as altering, deleting, or canceling system resources.
- Visualize key resources using graphical displays.
The graphical displays show resource usage and let you visualize key resources. You can select or sort data based on real-time values in each column.
- Obtain information from displays.
A batch interface and a REXX API are also provided to make information available programmatically and to assist with the automation.
Note: For more information, see the chapters "Using the Batch Interface" and "Using the Application Programming Interface" in the *Administration Guide*.
- Secure your displays and commands.
You can fully secure access to the displays and use of the command set.
- Expand the product.
You can easily expand CA SYSVIEW to keep current with the ever-changing systems and new environments that you manage. Development of new components never stops.

Performance Monitor

The CA SYSVIEW data collection and monitoring functions let you:

- Customize the data you collect and how often it is collected
- Activate the CA SYSVIEW performance monitoring by setting options in parameter files

Threshold-based Alerts

CA SYSVIEW issues alerts if a resource exceeds a usage limit or a resource is in an undesirable state.

You can set the thresholds by assigning values that issues an alert when the following scenarios occur:

- The percentage of CPU usage is greater than 90
- The amount of free common storage is less than 256 KB
- The CICS/PROD is in the INACTIVE state
- The WebSphere MQ channel is in the STOPPED state

The THRESH command displays the current z/OS threshold values, which you can modify by overtyping the entry. The ALERTS command displays z/OS system data collection exception alerts for both warning and problem thresholds.

When a threshold value is exceeded, CA SYSVIEW logs the event and issues a warning message. The message could trigger automated operations using REXX programs and CA OPS/MVS, when installed.

Command Facility

The CA SYSVIEW powerful and comprehensive command facility lets you monitor and manage your z/OS environment using over 700 commands. Extensive online help is provided for each command.

The command facility combines with navigational features, including:

- Hierarchical menus
- Fast-path commands
- Drill down using cursor point-and-shoot

Interfaces

CA SYSVIEW comes with many interfaces. You can run and access it from environments including VTAM, TSO, ISPF, CICS, or CA Roscoe.

The following interfaces are provided:

- 3270
The local 3270 device interface lets you run CA SYSVIEW in a dedicated mode from any locally attached 3270 device. This interface makes it possible for you to use CA SYSVIEW even when TSO, VTAM, and JES2 are not active.
- Batch
Run CA SYSVIEW as a batch job.
- API
The application programming interface obtains information from CA SYSVIEW displays for use in other programs. You access the API using TSO/E REXX.
- CA SYSVIEW Option for CICS Monitor Exit Interface
Customize your CICS applications for passing information to CA SYSVIEW.
- Console
Execute CA SYSVIEW commands with the output displayed on the console.
- Terminal Interfaces
Run and access CA SYSVIEW from the following 3270 Terminal Interfaces: VTAM, TSO, ISPF, CICS, and CA Roscoe.
- GUI Interfaces
CA SYSVIEW using CA Graphical Management Interface (CA GMI) now provides a GUI interface.

User Interface

CA SYSVIEW provides a flexible and easy-to-use user interface, which makes problem determination intuitive.

Because the displays are menu-driven, they are easy to navigate. You can select a display by name, number, or cursor position.

You are not limited to using menus. You can issue a CA SYSVIEW command by name or by its synonym from the option or command input entry area of any display.

You can customize the format of the displays yourself by setting up a profile.

Online help is available for every display and command. For the displays, the online help is cursor sensitive so that you can easily obtain information for each field. For the commands, the online help provides complete command syntax.

The Options

CA SYSVIEW consists of the following Options:

- CA SYSVIEW Option for z/OS
- CA SYSVIEW Option for CICS
- CA SYSVIEW Option for IMS
- CA SYSVIEW Option for WebSphere MQ
- CA SYSVIEW CA Datacom Option
- CA SYSVIEW Event Capture Option
- CA SYSVIEW Option for TCP/IP
- CA SYSVIEW for CA APM

Base Components

The base CA SYSVIEW product consists of the CA SYSVIEW Option for z/OS, which includes monitoring and management capabilities for the following z/OS environments:

- CA MIM
- JES2 and JES3, which includes the job and output management feature for end users
- Workload Manager
- UNIX System Services
- CA Roscoe
- CA SYSVIEW GUI enabled with CA GMI

The base product also includes the z/OS Toolkit and Utilities, which let you change the z/OS system environment without having to restart or IPL. The Toolkit and Utilities consist of an easy-to-use interface for issuing the JES commands.

Toolkit and Utilities

Each component has its own toolkit and utilities. They let you proactively manage your systems by issuing CA SYSVIEW commands to initiate actions such as altering, deleting, or canceling system resources. An interface is also provided to operator commands.

The Options in More Detail

The following sections explore some of the monitoring and management capabilities within each option.

Option for z/OS

The CA SYSVIEW Option for z/OS lets you monitor your z/OS system, JES2, Workload Manager, and UNIX System Services resources.

The following system resources are monitored:

- System status, including:
 - Number of active address spaces
 - CPU usage for z/OS, PR/SM, LPARs
 - Enqueue conflicts
 - Exception alerts
 - System console, log, and master trace table
 - Reserved DASD devices
 - Availability of the VTAM applications
- Devices, including:
 - Device allocation status
 - Catalogs
 - I/O configurations
 - DASD and tape units
 - Volume information (VTOC and extents)
 - Cache controllers

- Storage, including:
 - Common storage: CSA, ECSA, SQA, ESQA, orphaned
 - Data spaces
 - Expanded storage
 - Page and swap data sets
 - Real storage frames
 - Private storage
- Sysplex, including:
 - Automatic Restart Manager (ARM)
 - Couple data sets
 - Groups and members
 - Paths
 - Pending messages
 - Systems in the sysplex
- Coupling Facility, including:
 - Configuration
 - I/O paths
 - Processors
 - Structures
 - Users
- Address spaces, including:
 - Allocated data sets
 - Allocated devices
 - Loaded modules
 - Storage-common, expanded, private, real, pages
 - Tasks

z/OS Toolkit

The z/OS Toolkit and Utilities let you:

- Manage virtual and real storage, including:
 - Display storage by address or symbol
 - Map storage to control block or DSECT
 - Alter storage of any type
- Display and alter DASD records for:
 - Data sets: extents, PDS member, and CSECT name
 - JES spool
 - Volumes: all extents, VTOC, VTOC index, Volume labels

System Configuration Toolkit and Utilities

In addition, you can dynamically modify the following resource definitions using the following System Configuration Toolkit and Utilities actions:

APF data sets

You can use add, delete, and verify actions for this resource definition.

Dump data sets

You can use add, clear, and delete actions for this resource definition.

Linklist data sets

You can use add, delete, and rebuild actions for this resource definition.

Link pack area

You can use load, delete, enable, and disable actions for this resource definition.

SMF data sets

You can use dump and switch actions for this resource definition.

Subsystem entries

You can use add and delete actions for this resource definition.

JES Feature

The JES feature of the CA SYSVIEW Option for z/OS supports both JES2 and JES3 and is comprised of these features:

- Job Management lets you monitor and manage:
 - Active address spaces
 - Input/output queues
 - Initiators
 - Input job priorities
 - Job classes
- Output Management lets you monitor and manage:
 - Job summary
 - Output files
 - Job classes
 - Output classes
 - Output descriptors
 - Output queues
 - Spool volumes
 - SYSLOG
- Device Management lets you view and control devices specific to JES such as:
 - Internal readers
 - NJE and RJE lines
 - Nodes
 - Offloaders
 - Printers
 - Punches
 - Readers
 - Spool volumes

- Resource Definitions let you view the following information:
 - Resource usage overview, such as JOEs, JQEs, and JES buffers
 - Logon information
 - Network paths
 - Remote devices
 - VTAM sessions

JES Toolkit

The JES Toolkit lets you manage the following JES resources using the following actions:

Jobs

You can use the cancel, force, and release actions for this JES resource.

Initiators

You can use the start, stop, and halt actions for this JES resource.

Output

You can use the delete and release actions for this JES resource.

Printers

You can use the start, stop, and halt actions for this JES resource.

Reader and punch

You can use the start, stop, and halt actions for this JES resource.

Spool volumes

You can use the cancel and format actions for this JES resource.

Option for CICS

The CA SYSVIEW Option for CICS monitors all supported releases of CICS. The CICS displays show:

- Status information, including:
 - Active and suspended tasks: transactions running on the system
 - Degradation wait analysis: where transactions have been spending most of their time, which provides a bottleneck analysis
 - CICS domains
 - Dump statistics
 - Enqueues and enqueue pools
 - Automatic initiate descriptors (AIDS)
 - Interval control elements (ICE)
- Storage information, including:
 - Dynamic Storage Areas (DSAs)
Contains the extents, subpools, and elements.
 - Subspace areas
Provides transaction isolation. The display shows who is using which subspaces.
 - Temporary storage, such as CSA
Often overlooked after allocation.

- Information about the following CICS resources:
 - Global user exits
 - Files
 - Journals/logs
 - Kernel tasks
 - LSR pools
 - Programs
 - System Initialization Tables
 - MRO/ISC links
 - Transaction classes
 - Transient data
 - Terminals
 - Timers
 - Transactions
 - VSAM files
- Historical data, in the following forms:
 - System interval analysis, which shows the CICS region as a whole.
 - Detailed transaction log, which includes each transaction.
 - Transaction interval summary
 - Exception log, which shows CICS exceptions and CA SYSVIEW generated alerts.CA SYSVIEW also logs historical performance records to SMF.

Administrative Options

You can customize how CA SYSVIEW monitors CICS. You can define what and how much data to collect by specifying:

- Configuration options
- Transaction groups
- Threshold definitions
- Transaction definitions

Toolkit and Utilities for CICS

The CICS Toolkit includes:

- Resource management functions
 - Automated Response Time Management (ARTM)
You define a target and CA SYSVIEW adjusts the priority of the transaction to meet target response time.
 - Transaction cancellation at shutdown
CA SYSVIEW can cancel a transaction automatically and the region shuts down cleanly.
 - CICS dump management
CA SYSVIEW extends the normal CICS suppression policies by providing suppression that is based on transaction name, terminal name, or program name.
 - CICS SMF 110 record suppression
CA SYSVIEW lets you suppress records by transaction name.
- Interface to operator commands. You can overtype a field to modify a CICS resource, such as:
 - Cancel a CICS transaction.
 - Open or close a file.
 - Delete temporary storage queues.

Option for WebSphere MQ

The CA SYSVIEW Option for WebSphere MQ lets you monitor and manage queue managers, channels, and queues.

- Queue Managers

For queue managers, you can monitor and manage:

- Active threads
- Distributed queue manager
- Exception alerts
- Indoubt threads
- Name lists
- Page sets
- Processes
- Security
- Storage class
- Traces
- Users and connections
- Cluster queue managers

- Channels

For the channels that connect queue managers, you can monitor and manage:

- Channel definitions
- Client connections
- Receiver
- Requester
- Sender
- Server
- Server connections
- Status and resource usage

- Queues

For queues, you can monitor and manage:

- Alias queue
- Dead letter queue
- Event queue
- Local queue
- Model queue
- Remote queue
- Queue definitions
- Status and resource usage

Toolkit and Utilities for WebSphere MQ

The toolkit and utilities let you issue commands to perform administrative and configuration tasks on the following resources by taking the following actions:

Channels

You can use the actions start, stop, back out, commit, define, alter, delete, and reset for this resource.

Queues

You can use the actions browse, clear, define, delete, purge, edit, alter, import, and export for this resource.

Queue Managers

You can use the actions start, stop, and alter for this resource.

Cluster Queue Managers

You can use the actions remove, resume, and suspend for this resource.

Processes

You can use the actions define, alter, and delete for this resource.

Name list

You can use the actions define, alter, and delete for this resource.

Storage Classes

You can use the actions define, alter, and delete for this resource.

Channel Initiator

You can use the actions start and stop for this resource.

Page Sets

You can use the actions define and alter for this resource.

CA Datacom Option

The CA SYSVIEW CA Datacom Option supports the CA Datacom/DB database product.

CA SYSVIEW makes important metrics available online, eliminating the need to run batch CXX reports. Details are shown on CA SYSVIEW CA Datacom directories and directory areas, elements, fields, keys, and tables.

Three categories of performance statistics are shown:

- CICS Service Facility (CSF) information, which includes statistics on:
 - Users
 - Load modules
 - Trace
 - Return codes
 - Requests
 - URT
 - TCB tasks
 - TCB usage
 - TCB usage
 - TCB start I/O
- Directory information, which includes statistics on:
 - Database
 - Areas
 - Tables
 - Elements
 - Keys
 - Columns
 - Volumes
 - Data sets

- Multi-user facility information, which includes statistics on:
 - Accounting
 - Areas
 - Buffers
 - Databases
 - Logs
 - Options
 - Requests
 - Tables
 - Tasks
 - XCF

Toolkit and Utilities for CA Datacom

This toolkit lets you issue commands to cancel CA Datacom tasks.

Option for IMS

The CA SYSVIEW Option for IMS lets you monitor and manage the following resources within IMS control regions:

- Databases
- Output
- IMS nodes
- Programs
- Program Specification Blocks
- IMS control region and its dependent regions
- IMS shared queue
- IMS state definitions
- List of transaction codes
- Pools and Buffers
- VSAM

You can set performance thresholds and display exception alerts.

Toolkit and Utilities for IMS

This toolkit lets you issue IMS commands, the IMSSPOC command, and type two commands to the currently selected IMS control region.

Event Capture Option

The CA SYSVIEW Event Capture Option provides an automated and fully customizable data gathering tool. This option lets you collect and analyze historical and captured event data for problem determination or systems tuning.

The Event Capture Option lets you:

- Capture any CA SYSVIEW command
- Specify the level of data that is collected
- Specify when it is collected
- Specify how long to retain the information
- View or analyze the data on any system at any time

This option enables the SYSVIEW RMF historical displays.

For more information, see the chapter “Event Capture” in the *Administration Guide*.

Option for TCP/IP

CA SYSVIEW Option for TCP/IP simplifies your problem management of existing z/OS console displays of TCP/IP configuration data. These displays are complex and return large volumes of data. This option helps you manage your TCP/IP configuration definitions through basic discovery and viewing of TCP/IP configuration data.

The Option for TCP/IP provides the following benefits:

- Manages the existing use of TCP/IP for communication
- Provides basic TCP/IP information
- Monitors TCP/IP through a simple interface
- Lets you customize data collection
- Indicates whether a problem resides on the network

The Components in More Detail

The following sections explore some of the monitoring and management capabilities within each component.

CA SYSVIEW for CA Insight DPM for DB2 Component

The component CA SYSVIEW for CA Insight DPM for DB2 supports displaying DB2 information for DB2 subsystems that CA Insight DPM for DB2 monitors.

CA MIM Component

The CA MIM component provides a set of CA MIM commands that let you capture information from the following three areas of MIM functionality:

- CA MIM data provides information for managing and tuning MIM.
- CA MIA data provides information about tape device status from multiple systems such as online, offline, allocation, and mount pending times.
- CA MII data provides information about the ENQ workload and activity.

UNIX System Services Component

The UNIX System Services (USS) component lets you monitor and manage the following USS resources:

- USS Interprocess Communication (IPC)
 - Message queues
 - Semaphore sets
 - Shared memory
- File Systems
 - USS file and directory names and attributes
 - Open HFS and ZFS files for all USS processes in an address space
 - Mounted USS file systems
- System Information
 - Summary of USS resource monitoring statistics that the z/OS data collector collected
 - USS system configuration options

- Processes
 - Resource information about USS processes
 - z/OS address spaces that contain USS processes
 - Thread information for all active processes
- User and Group Information
 - Contents of the USS group database
 - Contents of the USS user database

Toolkit and Utilities for USS

The USS toolkit and utilities let you take the following actions:

- Terminate a process
- Send a signal to a process
- Browse and edit files

Workload Manager Component

The Workload Manager component lets you monitor and manage the following Workload Manager resources:

- Workload Manager policy and definitions as a graphical tree structure
- Workload activity resource data
- Workload activity delay data by address space
- Graphs of workload activity delay data by address space
- Workload Manager group information and independent and dependent enclave CPU usage by address space
- Service class and service class period information
- Workload activity delay data by service class
- Workload activity response time distribution data
- Group definition and group values
- Workload Manager service policy information
- Report class information
- Workload activity response time data
- Resource group definitions

- Subsystem and classification rules
- Summary of the workload activity response time and delay data
- Workload definition information

CA Roscoe

For CA Roscoe, CA SYSVIEW monitors the following resources:

- User activity
- Buffer usage
- Response times
- Monitor routines
- AWS data sets
- MPL stack usage

MIB Browser

You can browse or walk a MIB on any operating environment or device from z/OS. This ability requires TCP/IP on z/OS and uses SNMP for communication to IP addresses.

System Overview

The System Overview component lets you display a select group of metrics and conditions as a single package. These metrics display in the information section of a SYSVIEW command or menu display. Each user can control the time and placement of the system overview information about a display.

The information can also be displayed in a cross-system view showing multiple z/OS images by using the SYSTEMS command.

System Condition Monitor

The System Condition Monitor (SCM):

- Clearly provides a color-coded, high-level summary of the resources that are currently being monitored. The SCM tells you at a glance where the problems are, so that you do not have to search multiple areas to find problem sources.
- Lets the Helpdesk personnel and operators notify appropriate personnel when a problem exists. System programmers can drill down and can find the source of the problem.

- Lists all your subsystems and resources using the primary SCM screen. For example: DASD, file systems, CICS regions, and more. Each entry has a color indicator that shows whether a problem exists and, if so, the severity of the problem. For each entry, you can easily drill down to see more detail.
- Clearly describes problems; for example, “WTOs requiring replies is 34.” Also provided are positive statements about system health, such as “No TAPE devices require attention.”
- Simply provides an out-of-the-box experience. In addition, you can easily customize it to monitor any data that is available on your systems. You can also expand it easily by adding your own data to monitor more resources.
- Uses intelligent modules that are written in compiled REXX with additional CA supplied functions, or IMODs, that communicate with the monitored subsystems. You use IMODs to automate system monitoring and regulate resources or to create your own online reports on system activities.

Important! When upgrading to a new release of CA SYSVIEW, the new release and the IMOD libraries that are shipped with the new release match. The new IMOD libraries overlay and therefore replace the IMOD libraries from the previous release. If you decide to modify the IMOD libraries, CA suggests creating a site-specific IMOD library for those locally written IMODs.

Chapter 2: Basic Skills

This section contains the following topics:

[Menu Navigation](#) (see page 39)

[Learn the Displays](#) (see page 41)

[Scroll the Displays](#) (see page 48)

[View the PF Key Settings](#) (see page 49)

[How to Enter Commands, Parameters, Subcommands, and Line Commands](#) (see page 49)

[FIND Command—Find Information on a Display](#) (see page 56)

[Obtaining Help](#) (see page 58)

Menu Navigation

Learning how to use CA SYSVIEW begins with understanding the CA SYSVIEW menu structure. Knowing how menus are set up and how to use them lets you easily:

- Learn to access the displays
- Perform many useful tasks

The Primary Option Menu

By default, the first CA SYSVIEW menu you see is the Primary Option Menu. This menu appears when you first logon to CA SYSVIEW. The Primary Option Menu contains a list of other menus you can access to perform tasks. From the Primary Option Menu, you can also select the option MENU HELP to display the online help information menu.

A sample Primary Option Menu:

```
SYSVIEW ----- MENU, Primary Option Menu ----- 15:22:56
Option ==>                                         Scroll *==> PAGE
----- Lvl 1 Row 1-18/18
Option Command      Description
-   1 MENU OVERVIEW  System overview
-   2 MENU MVS        MVS displays
-   3 MENU JES        JES job and output management
-   4 MENU CICS       CICS displays
-   5 MENU DATACOM    CA Datacom displays
-   6 MENU IMS        IMS displays
-   7 MENU MQ         WebSphere MQ displays
-   8 MENU NETWORK    Network and TCP/IP displays
-   9 MENU USS        UNIX system services displays
-  10 MENU CAPTURE    Event capture and SMF/RMF collection

-  11 MENU SCM        System condition monitor
-  12 MENU ADMIN      SYSVIEW administration
-  13 MENU PRODUCTS   Product integration menu

-  14 MENU HELP       Online help information
-  15 END             Terminate SYSVIEW session
```

The Menu Command

If you are viewing a CA SYSVIEW display and you type the MENU command without parameters at the command line, the Primary Option Menu appears. However, you can also access other CA SYSVIEW menus by specifying a menu name as a parameter on the MENU command. To see a list of CA SYSVIEW menus that you can access using the MENU command, type HELP MENU on the command line.

Not all menus may be available at your site. If you are not authorized to use a menu, you cannot display it. If you would like to know more about the menus that you have access to, contact your system administrator.

Select an Option on a Menu

You can select an option on a menu in one of three ways.

Follow these steps:

1. Select an option from the Primary Option Menu using one of the following methods. In this case, we are choosing option 3, the MENU JES command:
 - Enter **3**, the number of the option, in the command input field and press Enter.
 - Place the cursor in the input field to the left of the number 3 option, MENU OPERATOR, and press Enter.
 - Type the command name, **MENU JES**, in the command input field and press Enter.

The JES Menu displays.

2. Select a command from the JES Menu the same way you chose the menu from the Primary Options Menu and press enter.

The new menu that you drilled down to displays.

Note: The Option numbers can be different for different users, depending on which commands the user is authorized to use.

Learn the Displays

When you select a command from one of the CA SYSVIEW menus, you access a display. Use the display to look at data and perform tasks the command is designed for.

CA SYSVIEW is distributed with a default display format. The following description of a display format is based on this default format. Your displays can be different from this default display when your security administrator has changed your profile.

You can change your display to make it more convenient for you to perform your work tasks. For example, you can change the location of different fields on the screen or the color of the screen fields. To perform some tasks to change your default display, see the chapter [“Basic Tasks](#) (see page 78).”

System Activity Display

The following screen is an example of the System Activity Display that provides a good sample of a screen in default format.

```

SYSVIEW ACTIVITY ----- System Activity ----- 10:25:20
Command =====>                               Scroll *====> HALF
----- Lvl 2 Row 69-77/762 Col 1-79/484
(r)  CP% IFA% Pct% ...50..100 -Condition- ---Ready--- --Paging-- -Storage-
CPU   35%  0%  28%             ENQ NoSMF ASIDs   3  Slots  41% ECSA  87%
LCPU  35%  0%  28%             RES NoWTO Tasks   3  Rate   3  ESQA  95%
                                           NoDMP  TAP  ---I/O--- AFQA 10649  SQA  97%
Spool                51%                Rate 27113  UICA 2540  CSA  64%
-----
Formats DEFAULT CPU CPU1 PERF STORAGE
Status  SORT
XSStat  Data NO  Group ALL  MsgLvl ERROR  Limit NONE  RemDup NO  Type SYST
-----
*
          ALL          ALL
Cmd Jobname  Stepname Procstep Type  Jobnr Jc Status CPU-Time Limit Clocktime
___ BLADA08   CATSO    A55TG129 TSU   62337 @ LSW   8.985128 3600 01:04:18
___ BLX1PROC  BLX1PROC BLXSPCAS STC   17660 $  NS    0.109452 86400 85:03:33
___ BPXAS     BPXAS    IEFPROC  INIT  62799 $  LSW   0.005464
___ BPX0INIT  BPX0INIT BPX0INIT  SYS           IN   12.87126 86400 85:03:28
___ BRAMA15   CATSO    A55TU051 TSU   61449 @ LSW   1.634794 3600 02:00:27
___ BRESMA1   CATSO    A55TG050 TSU   61350 @ LSW   1.059153 3600 02:07:10
___ BRESM01   CATSO    A55TG083 TSU   61358 @ LSW   4.798934 3600 02:06:18
___ BRORI09   CATSO    A55TG084 TSU   61384 @ LSW   2.863388 3600 02:04:19
___ BUILD     STEP1     OTX    31918 $  LSW   1.357302 1048 41:43:00

```

The sections that follow describe the areas on the display in the default format.

Display Areas

The following figure labels the areas of the default format display. These areas are described in the following sections. After you read the description, see the screen for examples of the particular areas. You may want to come back to this screen later on when you change your display format. For ways you can do this, see the chapter “[Basic Tasks](#) (see page 78).”

Title	SYSVIEW ACTIVITY ----- System Activity ----- 10:27:02
Command	Command ==>>> Scroll *==>> HALF
Divider	----- Lvl 2 Row 757-762/762 Col 1-79/484
Overview Menu	(r) CP% IFA% Pct% ...50..100 -Condition- ---Ready--- --Paging-- -Storage-
Overview Menu	CPU 100% 0% 80% ENQ NoSMF ASIDs 6 Slots 41% ECSA 87%
Overview Menu	LCPU 90% 0% 72% NoRES NoWTO Tasks 6 Rate 14 ESQA 95%
Overview Menu	NoDMP TAP ----I/O---- AFQA 14418 SQA 98%
Overview Menu	Spool 51% Rate 30706 UICA 2540 CSA 64%
Divider	-----
Formats	Formats DEFAULT CPU CPU1 PERF STORAGE
Status	Status SORT
XSSstatus	XSSStat Data NO Group ALL MsgLvl ERROR Limit NONE RemDup NO Type SYST
Divider	-----
Parameter	* ALL ALL
Header	Cmd Jobname Stepname Procstep Type Jobnr Jc Status CPU-Time Limit Clocktime
Data	--- YUACH01 CATSO A55TG173 TSU 63056 @ LSW 0.885417 3600 00:20:48
.	--- YUASDRAS \$\$\$\$\$@ JOB 29025 C NS 0.107233 86400 48:45:50
.	--- YUA3DRAS \$\$\$\$\$@ JOB 29027 C NS 0.125544 86400 48:45:43
.	--- ZARMA01 CATSO A55TG012 TSU 61798 @ LSW 0.124484 3600 01:32:16
.	--- ZELJOB2 CATSO A55TG005 TSU 60365 @ LSW 9.217070 3600 04:04:23
.	--- ZEMKE01 CATSO A55TG065 TSU 62408 @ LSW 2.884281 3600 01:00:23
End-Of-Data	===== End of Data =====
PF Message	1=HELP 2=SPLIT 3=RETURN 4=TOP 5=FOUND 6=DUMP 7=UP 8=DOWN 9=SWAP 10=LEFT 11=RIGHT
PF Message	12=RECALL 13=QUICKREF 14=QLIST 15=SORT

Title Line

The first line on the display is the title line. The title line identifies the display and shows, in the following order, these items:

- Product name
- Product release number (not shown in the example)
- The system name where CA SYSVIEW is executing (not shown in the example)
- Name of the display
- Current date (not shown in the example)
- Current time (not shown in the example)

Command Line

The command line contains two fields:

- The command input field, where you enter a command to the right of the prompt (Command ==>>).
- The Scroll field, which displays the current scroll value when you scroll up, down, left, or right.

More information:

[Scroll the Displays](#) (see page 48)

Divider Line

The divider line separates the title and the command areas from the remainder of the display. Messages issued by CA SYSVIEW overlay the divider line.

The divider line has the following fields:

- HOP Count (not shown)
Indicates the number of cross-system connections deep you are from the original local system when you are connected to a remote system through a cross-system connection.
- Level Number
Indicates how many levels deep you are from the Primary Option Menu.
- Row
Displays information to help you determine which rows of data in the data area are currently displayed.

The Row field shows row information in the following format:

first-last/ [total]

first

Indicates the number of the first row displayed.

last

Indicates the number of the last row displayed.

total

Indicates the total number of rows. This number is not displayed when the total number of rows is not yet known.

- Column

Displays information to help you determine which columns of data in the data area are currently displayed.

The Column field is shown in this format:

*[1 -lastncol&] firstscol-lastscol/totalcols
1-lastncol&*

Indicates the number of the nonscrollable columns displayed. This information is shown only when there are nonscrollable and scrollable columns, and you have scrolled the display to the right. Nonscrollable columns always start in column 1, and they end in *lastncol*.

firstscol

Indicates the number of the first scrollable column displayed.

lastscol

Indicates the number of the last scrollable column displayed.

totalcols

Indicates the total number of columns.

Format

The format line displays when the following are in effect and you have at least one profile format defined:

- SET FORMATLINE YES
- SET FORMATLINE COND

The format line shows the DEFAULT format name with the names of any formats you have defined. The format currently in use is highlighted. You can switch to another format by placing your cursor a format name that is not highlighted and hitting the ENTER key.

Status Line

The status line is displayed only when requested and describes particular status information regarding the display.

Status Divider Line

A status divider line can be shown after the status line and is included only if a status line is present. (It is not shown on the sample screen.)

Information Area

The information area is present on some of the CA SYSVIEW displays and contains information unique to the command. The information area length is from 1 to 16 lines.

Information Area Divider Line

A divider line separates the information area from the remainder of the display and is included only if an information area is present.

Parameter Line

The parameter line is present on some of the CA SYSVIEW displays. This line contains the current parameter settings for the display. The parameters appear above their associated field headings. The parameter area is redisplayed when you scroll up and down, but it scrolls with the display when you scroll left and right.

Header Line

The header line identifies the fields (columns) in the display. Field names are redisplayed when you scroll up and down, but they scroll with the display when you scroll left and right.

When you scroll left and right, a break character marks the first scrollable column, and this gives a reference point when you scroll. For example, if you scroll to the right in the partial display shown in the first screen, you will get the result shown in the second example.

Example 1

```

SYSVIEW ACTIVITY ----- System Activity ----- 10:25:20
Command ==>>>                                     Scroll *==>> HALF
----- Lvl 2 Row 69-77/762 Col 1-79/484
(r) CP% IFA% Pct% ...50..100 -Condition- ---Ready--- --Paging-- -Storage-
CPU 35% 0% 28%                ENQ NoSMF ASIDs 3 Slots 41% ECSA 87%
LCPU 35% 0% 28%                RES NoWTO Tasks 3 Rate 3 ESQA 95%
                                   NoDMP TAP ----I/O---- AFQA 10649 SQA 97%
Spool                51%                Rate 27113 UICA 2540 CSA 64%
-----
Formats DEFAULT CPU CPU1 PERF STORAGE
Status SORT
XSStat Data NO Group ALL MsgLvl ERROR Limit NONE RemDup NO Type SYST
-----
*                ALL                ALL
...+...10...+...20...+...30...+...40...+...50...+...60...+...70...+
Cmd Jobname Stepname Procstep Type Jobnr Jc Status CPU-Time Limit Clocktime
___ BLADA08 CATSO A55TG129 TSU 62337 @ LSW 8.985128 3600 01:04:18
___ BLX1PROC BLX1PROC BLXSPCAS STC 17660 $ NS 0.109452 86400 85:03:33
    
```

Example 2

```

SYSVIEW ACTIVITY ----- System Activity ----- 10:25:20
Command ==>>>                                     Scroll *==>> HALF
----- Lvl 2 Row 69-77/762 Col 1-13680-145/348
(r)  CP% IFA% Pct% ...50..100 -Condition- ---Ready--- --Paging-- -Storage-
CPU  35%  0%  28%             ENQ NoSMF ASIDs   3  Slots  41% ECSA  87%
LCPU 35%  0%  28%             RES NoWTO Tasks  3  Rate   3  ESQA  95%
                                   NoDMP  TAP  ----I/O---- AFQA 10649  SQA  97%
Spool                51%             Rate 27113  UICA 2540  CSA  64%
-----
Formats DEFAULT CPU CPU1 PERF STORAGE
Status  SORT
XSStat  Data NO  Group ALL  MsgLvl ERROR  Limit NONE  RemDup NO  Type SYST
-----
*
...+....10.|80...+....90...+....100...+....110...+....120...+....130...+....140...+
Cmd Jobname |SRB-Time  I/O-Count R-Stg Dp Pgn Dmn ASID -CPU%- Paging I0/Sec
___ BLADA08  | 4.505      19320    FF 12  8 005F  0.00  0.00
___ BLX1PROC | 0.026       271      FF  2  4 0060  0.00  0.00

```

Separator Line

The separator line, not shown in the sample screen, follows the header line to separate it from the data area. If present, this line is blank or contains the column ruler.

Data Area

The data area of the display contains the data fields for a display that you have accessed by issuing one of the CA SYSVIEW commands. The data area is most often composed of rows and columns. Some columns scroll and some do not. The information in a column is referred to as a field.

The first data line in the display (regardless of which line it is) is known as the current line.

End of Data Line

The end of data line indicates the end of data for the display. A few displays (DUMP, for example) do not contain an end of data line. If the display does not contain any data, the line says "No Data Available" instead of "End of Data."

Filler Area

The filler area is blank space used to fill out the display.

PF Message Area

The PF message area displays one to four lines of information. You specify what you want displayed in this area. By default, the PF keys are displayed, and they are shown in this area.

Note: For information about specifying what is displayed in this area, see the chapter “[Basic Tasks](#) (see page 78)” or the PROFILE command online help.

Scroll the Displays

You can scroll the CA SYSVIEW displays using the following commands:

- LEFT
- RIGHT
- UP
- DOWN

You can also issue the TOP and BOTTOM commands to go to the top and the bottom of the display, respectively.

If a display contains more data than can fit on one screen, you can view the additional data by scrolling right. To return to your original position, scroll left.

You can use PF keys or function commands to scroll as follows:

- Use PF keys

By default, your PF keys for scrolling commands (LEFT, RIGHT, UP, and DOWN) have been set for how much data to scroll at one time. You can change these settings using the SET SCROLLVALUE command.

For the values you can specify for SCROLLVALUE, see the SET command online help.

For more information about how to use the SET command, see [SET Command--Change Your Profile](#) (see page 69) in the chapter “Basic Tasks.”

- Issuing function commands

To scroll a display using a function command, type the scrolling command at the command line. If you want, you can add parameters to the command. For example, if you would like to scroll down eight lines, you would specify the following command at the command line:

```
DOWN 8
```

To learn about the parameters for scrolling commands, look up the command in the CA SYSVIEW online help. For more information about using online help, see [Obtaining Help](#) (see page 58) in this chapter.

View the PF Key Settings

By default, your PF key settings are displayed at the bottom of your screen. If for some reason they are not, you can set them to be displayed.

When you are using a display, you can display the PF key settings by specifying the following command in the command input area:

```
PFSHOW ON
```

To display PF key settings for all displays, specify the following command:

```
PFSHOW ON ALL
```

Default PK Key Settings

The PF key definitions that are distributed on the installation tape are the default definitions. The PF keys are initially the same on every display.

CA SYSVIEW provides the following default PF key settings:

- PF1/PF13 - HELP
- PF3/PF15 - RETURN
- PF5/PF17 - FIND
- PF7/PF19 - UP
- PF8/PF20 - DOWN
- PF10/PF22 - LEFT
- PF11/PF23 - RIGHT
- PF12/PF24 - RECALL

For information about how to change your PF key settings, see the chapter “[Basic Tasks](#) (see page 78).”

How to Enter Commands, Parameters, Subcommands, and Line Commands

The CA SYSVIEW commands can have parameters and subcommands. You can also use line commands on a command display. The following sections describe how to enter commands, parameters, subcommands, and line commands.

Primary and Function Commands

The COMMANDS command distinguishes the type of command to use. COMMANDS has PRI, FUNC, or SUB for Primary, Function, and Subcommand.

PRI

The primary command returns a display.

FUNC

The function command takes an action and returns a message on the current display.

Parameter Conventions

Knowing how to enter parameters for a command is essential. Properly entering parameters lets you access the display that you want.

Enter the parameters using the following conventions:

- When you enter a parameter, separate the command from the parameters with a space.
- When you enter more than one parameter, separate the individual parameters with a comma or a space.

Example: Add Parameters to a Command

This example adds parameters to the ACTIVITY command.

```
ACTIVITY [jobname][, type][, status]
```

Mark an Omitted Parameter Position

A *positional parameter* must be placed in a specific position among the parameters you enter. The positional parameters are interpreted based on their order in a series of parameters. You account for any omitted positional parameter by entering a comma in its place. Except, however, if the omitted parameters are to the right of the last parameter you entered. Then you do not need to enter commas to show where they would be placed.

The following examples show parameters that are entered on the ACTIVITY command. When the *jobname* and *type* parameters are not specified, commas are inserted in their places.

ACTIVITY ABC

This example uses the *jobname* parameter.

ACTIVITY ,TSU

This example omits the *jobname* parameter, but uses the *type* parameter. The comma before the TSU represents the omitted *jobname*.

ACTIVITY ,,OUT

This example omits both the *jobname* and *type* parameters, and uses the status parameter OUT. The two commas preceding OUT represent the omitted *jobname* and *type*.

ACTIVITY ABC22,NOI,ALL

This example shows how you can enter all three parameters. Commas separate the parameters. You can use spaces to separate the parameters instead of commas.

Parameter Masks

You can use *masks* to enter some command parameter values. A mask is a partial or generic parameter name. For example, you could use masking characters to indicate a partial (or masked) job name as a value for the ACTIVITY *jobname* parameter.

Default masking characters are the asterisk (*) and the equal sign (=). The asterisk replaces any single character, and the equal sign replaces any number of characters in the name being masked.

Change Masking Characters

You can change these masking characters to other characters.

To change masking characters, go to the Input character options area in the Miscellaneous Section of your general profile and change the following values:

- Fixed-length masking character (default *)
- Variable-length masking character (default =)

Your default masking characters are changed.

You can also use the SET command to change these characters. For full instructions on how to perform this task, see the chapter “[Basic Tasks](#) (see page 78).”

Examples: Using Masking Characters

The following examples show how to use masking characters to mask a *jobname* parameter. These examples reflect the use of default characters.

=

Matches all characters of a job name.

ABC=

Matches job names starting with ABC and ending in any other characters.

A=C

Matches job names that begin with A and end with C.

****ABC=**

Matches job names with ABC as their third, fourth, and fifth characters, any specific first or second characters, and any remaining characters after the fifth (C).

***ABC**

Matches job names with ABC as their second, third, and last characters.

AB****

Matches job names with AB as their first two characters, and four remaining characters in their names.

Enter Parameters with PF Keys

You can include a parameter with a command for which you have defined a PF key.

Follow these steps:

1. Type the parameter on the command line.
2. Press the PF key.

For information about how to define default parameters for a command, see the topic [Initialization Command Options in the Profile](#) (see page 78) in the chapter “Basic Tasks.”

Enter Subcommands

Some commands have subcommands you can use when you are on the display of that command. These subcommands provide extra functionality that let you perform the following tasks:

- Access more specific displays
- Locate information that is on a display
- Refresh a display
- Add or replace information that is on a display

You enter subcommands on the command line in much the same way you enter commands. Also, subcommands can have parameters, and if they have multiple parameters, those parameters are treated as positional parameters.

Enter Line Commands

Line commands are commands that you issue on many displays to affect a line on a display. You can use the abbreviated uppercase part of a line command to issue the command.

Follow these steps:

1. Tab to the input area under the Cmd heading to the left of the line on the display for the job you want affect.
2. Type the line command (cancel) or the abbreviated part of the line command (C), and press Enter.

The command is processed, in this case the job is canceled, and a refresh of the screen displays.

3. Display a list of available line commands for the display by placing the cursor on the line command field and press the HELP PF key.

The available line commands are displayed.

4. Type the line command and press Enter.

The command is processed.

You have entered both a specific line command and a line command that you selected from the Help.

Block commands are available for use with line commands, and for other purposes. For more information about entering block commands, see the online help Topics.

Create External Line Commands

You can externally define your own line commands for any given display. This ability lets you drill down or initiate an action to satisfy your own requests. The parmlib member LINECMDS contains example definitions. Using these example definitions, you can define your own set of external line commands specific to your needs.

Follow these steps:

1. Access user definitions from the following location:

```
user.sysview.parmLib(LINECMDS)
```

The LINECMDS parmlib member displays.

2. Code your own external line commands in this member. Use the provided example definitions in this member as a template.
3. Save your changes.

Your line commands are defined.

Information about Commands

The following list provides miscellaneous information about CA SYSVIEW commands.

- **Commands Executed in the Current ASID**

When executing commands for CA SYSVIEW, the current address space ID is used. To change the address space ID when appropriate, you can use either the ASID function command or an ASID parameter of a command.

- **Dynamic Changes Not Saved at Next IPL**

Some changes that you can make when you issue CA SYSVIEW commands are only in effect until the next system IPL.

For example, use the ADD subcommand to add a data set to the LINKLIST. That data set addition is in effect only until the next IPL of your system. To see if this restriction applies to a particular command, see the online help for that command.

- **Save time with the RECALL and REVIEW Commands**

The RECALL and REVIEW commands help you save time when you are issuing commands.

- **RECALL Command**

The *RECALL command* displays, on the command line of the current display, the last command that you executed. This recall helps you to remember previously executed commands so that you can issue them again without having to type them in. When the command you issued has been recalled, you can issue it again by pressing Enter.

Note: You cannot recall scrolling commands (unless they contain a parameter) or the REFRESH command. You can recall only one copy of a command that you have entered several times in succession.

- **REVIEW Command**

The *REVIEW command* displays the contents of the command input stack. Your previously issued commands are shown and you can optionally modify them and issue them again.

Note: For specific details on using these commands, see online help.

FIND Command—Find Information on a Display

Use the FIND command for locating information that is on a display. The FIND command searches the display data for a specified character string.

Note: The DUMP command has its own FIND subcommand. For information about issuing FIND from the DUMP display, see the DUMP command in online help.

The FIND command has the following format:

```
FIND {string}[ ,keyword1][ ,keyword2][ ,col1][ ,col2][ ,fieldname]
```

string

This required parameter specifies the string that you want to find. If a string contains embedded blanks or commands, it must be contained in character delimiters. The default character delimiter is the apostrophe ('). You can change this default in your profile.

The following formats qualify a string:

- *C'string'* indicates a character string
- *T'string'* indicates a text string
- *X'string'* indicates a hex string
- *P'string'* indicates a picture string

Example: The following command finds the string JOB1:

```
FIND JOB1
```

The *string* parameter must be specified before you can specify any of the other parameters.

keyword1

This first keyword finds multiple occurrences of the string. Values of keyword1 are NEXT, PREV, FIRST, LAST, and ALL.

Example: Find a previous occurrence of the string JOB1, specify the following command:

```
FIND JOB1 PREV
```

When you use the value ALL for keyword1, the command:

1. Searches for all occurrences of the string
2. Positions the display at the first occurrence

To see the remaining occurrences, repeat the FIND command (without any parameters). By default, you can use the FIND PF key to repeat the find.

keyword2

This second keyword finds all occurrences of a string according to its position in a word. Values of keyword2 are CHARs (ignores the position), PREFIX (beginning of a word), SUFFIX (end of a word), INFIX (middle of a word).

Some examples of the previous keywords follow. The capitalized characters indicate the strings that are found.

```
FIND 'DO' CHAR DO D0nt aD0 aD0pt 'DO' +aD0 (D0nt) aD0-
FIND 'DO' PRE do D0nt ado adopt 'do' +ado (D0nt) ado-
FIND 'DO' SUF do dont aD0 adopt 'do' +aD0 (dont) ado-
FIND 'DO' WORD DO dont ado adopt 'DO' +ado (dont) ado-
FIND 'DO' INFIX do dont ado aD0pt 'do' +ado (dont) ado-
```

col1 and col2

Specify to find a string in a column that these column numbers defined.

Note: To see column numbers on your display, specify SET COLS ON at the command line.

To find the string 3658 between columns 42 and 48, specify:

```
FIND 3658 42 48
```

fieldname

Specify to find a string in a column defined by a field on the display.

To find the string 3658 in the Jobnr field, specify:

```
FIND 3658 Jobnr
```

Use the FIND PF Key

The default setting for the FIND command you issued without parameters is FIND NEXT. Unless you or your system administrator has changed the setting of your PF 5 key, it is by default set to FIND. Use your default FIND NEXT PF key for finding other occurrences of a string you located by issuing the FIND command at the command line.

For example, type the following command on the command line:

```
FIND jobname
```

After the FIND command locates an instance of the job name you are searching for, use your PF 5 key to find other occurrences.

Number of Lines Searched

The Find limit option setting determines the maximum number of lines searched by the FIND command. This setting is in the Command options area of the general profile Miscellaneous section.

Obtaining Help

You can obtain online help for using CA SYSVIEW in the following ways:

- Use the Help commands, the online reference materials in the CA SYSVIEW Online Help Information Menu, or both. You can access the Online Help Information Menu either through the Primary Option Menu or issue the MENU HELP command.
- Use the CA SYSVIEW Bookshelf available at <http://ca.com/support>.

Note: For more information about accessing the documentation, see the *Installation Guide*.

Access Online Help

CA SYSVIEW provides online help for all commands and messages. You can access CA SYSVIEW online help in several different ways.

- From a Display

If you are on a command display, you can obtain help for that command by any of the following methods:

- Press the default PF key for online help (F1).
- Type the HELP command at the command line.

By default, issuing the HELP command with no parameters and your cursor is on a field that online help has been defined causes help information to display for that particular field within the online help panel.

- From Anywhere

On any display, to obtain online help for any command or message ID:

- Type the HELP command at the command line
- Include the appropriate parameters

To obtain online help for a command and the display you receive when you issue the command, use the following format:

```
HELP cmdname
```

For example, if you would like to see online help for the ACTIVITY command, type the following command:

```
HELP ACTIVITY
```

To obtain online help for a message you have received, use the following format:

```
HELP msgid
```

For example, to obtain online help for message GSVX537A, from the command line specify:

```
HELP GSVX537A
```

- For a Message

Issue the HELP command with the message displayed on the screen. By default, you can see help for a message, if online help is defined for that message.

- From the Main Menu

The Online Help Information Menu is organized to let you quickly access the following information:

- Changes in this release
- List of commands and subcommands
- Help information
- MVS/QuickRef from Chicago-Soft
- Online reference materials

Access Online Help from the Main Menu

Choose the MENU HELP option from the Primary Option Menu or issue the MENU HELP command from any menu to access the following Online Help Information Menu:

```
SYSVIEW MENU ----- Online Help Information Menu ----- 10:35:33
Option ==>                                                    Scroll *==> HALF
----- Lvl 2 Row 1-20/23
Option Command Parameters Description
- 1 CHANGES What's new in this release?
- 2 COMMANDS List commands and subcommands
- 3 FIELDS ALL List command display fields
- 4 FINDHELP Search online help topics
- 5 QUICKREF MVS/QuickRef from Chicago-Soft
- 6 SUPPORT SYSVIEW support diagnostics
- 7 TOPICS Online reference topics

Option Online Reference Materials
- 8 Glossary of Terminology
- 9 How to topics
- 10 Online command reference
- 11 Online message reference
- 12 CA DATACOM online reference
- 13 CICS online reference
- 14 IMS online reference
- 15 UNIX System Services online reference
- 16 WebSphere for MQ online reference
- 17 Work Load Manager online Reference
- 18 Print command reference manual
- 19 Print information and how-to topics
- 20 Print all help topics
```

Search the Online Help

You can search the online help system for a specified text string by:

- Using the FINDHELP option on Online Help Information Menu
- Issuing the FINDHELP command from any menu

The search is performed against a list of predefined online help topics. Each topic corresponds to a HELPLIB member.

The following functions can be performed:

- Locate all online help information that is on selected topics.
- Ask for the commands that provide information about a desired topic. For example: "What commands display alert information?"
- Create user-customized search lists.

Use FINDHELP

To find information about alerts, issue the following command:

```
FINDHELP alert
```

To find information about alerts using the Online Help Information Menu, enter **alert** in the parameters column next to the FINDHELP option as follows:

```

SYSVIEW ----- MENU, Online Help Information Menu ---
Option ==>>>                                         Scroll *==>> PAGE
----- Lvl 2 Row 1-15/15 Col 1-79/79
Option Command Parameters                          Description
- 1 CHANGES                                       What's new in this release?
- 2 COMMANDS                                       List commands and subcommands
- 3 FINDHELP alert                               Search online help topics
- 4 QUICKREF                                       MVS/QuickRef from Chicago-Soft
- 5 TOPICS                                         Online reference topics
. . .
. . .

```

The following help screen is displayed:

```

SYSVIEW FINDHELP ----- Search Online Help Topics -----
Command ==>>>                                         Scroll *==>> PAGE
----- Lvl 3 Row 1-16/30 Col 1-79/158
List TOPICS Topics 679 Lines 113016 Hits 39
Options ALL CHARS Section
String alert
-----
Cmd Help      ....+....1....+....2....+....3....+....4....+....5....+....6...
---- ALERTS  | ALERTs      <Normal>
---- .       | ALERTS Command
---- .       | The ALERTS command displays z/OS system data collection excepti
---- .       | Data collection values will be displayed by the ALERTS command
---- .       | displayed alert.
---- .       | GSVXEXTR_OPTIONS_ALERTS. EXTRACT is only val
---- DASDRESP | Alert status is only displayed if the "CURRENT" interval is
---- IMSALERT | displayed alert.
---- .       | IMSALERT Command
---- .       | The IMSALERT command displays IMS data collection exception
---- .       | alerts. Data collection values will be displayed by the
---- .       | IMSALERT command if the current value exceeds a threshold defin
---- .       | IMSALERT      <Normal>
---- IMSSTATE | displayed alert from the IMSALERT command.
---- IMSTHRSH | displayed alert from the IMSALERT command.

```

Online Reference Topics

You can display the Help Topics screen by:

- Choosing the TOPICS option on the Online Help Information Menu
- Issuing the TOPICS command from any menu

The topics are listed in categories. Press Enter next to the help topic you want to display.

A sample Help Topics screen:

```
SYSVIEW TOPICS ----- Help Topics ----- 10:56:48
Command ==>                               Scroll *==> HALF
----- Lvl 3 Row 1-18/880 Col 1-79/87
Member TOPICS Dsn SYSVIEW.CNM4BPRM
-----
Cmd Class Description
___ INFO What's new in this release?
___ . API return codes
___ . ASID and System Linkage Index (LX) Reuse
___ . CA SYSVIEW address spaces
___ . Contacting Technical Support
___ . Decimal and Hexadecimal Suffixes
___ . Help topic naming conventions
___ . Library caching
___ . Online message library
___ . Operating system names - MVS, OS/390, z/OS
___ . Operating system versions
___ . Parmlib member contents
___ . Program Status Word (PSW) information
___ . SMF records created by CA SYSVIEW
___ . System Condition Monitor IMODS - SCM
___ . System overview information
___ . CA SYSVIEW User abend codes
___ . What is a CLIST or CLISTLIB member?
```

Online Reference Materials

The Online Help Information Menu lets you display the list of Commands and Messages. This menu also includes their explanations and reference information for the following options and components:

- CA SYSVIEW CA Datacom Option
- CA SYSVIEW Option for CICS
- CA SYSVIEW Option for IMS
- UNIX System Services (USS) Component
- CA SYSVIEW Option for WebSphere MQ
- Workload Manager Component

Sample of the CICS online reference:

```

SYSVIEW ----- TOPICS, Help Topics -----
Command ==>                               Scroll *==> PAGE
----- Lvl 3 Row 1-14/81 Col 1-79/87
Member TOPICS
-----
Cmd Class Description
--- HOWTO Displaying currently active CICS address spaces
--- INSTALL CA DATACOM CICS Service Facility data collection
--- CICS Automatic initiate descriptors - AIDS
--- . Auxiliary temporary storage
--- . Common storage area
--- . Configuration options
--- . Global commands
--- . REGION= parameter
--- . System and transaction variables
--- . System variables
--- . Temporary storage
--- . Transaction variables
--- COMMANDS CAIDS - CICS auto initiate descriptors
--- . CARTM - CICS auto response time mgmt
-----
1=HELP 2=SPLIT 3=RETURN 4=ASDF 5=FIND 7=UP 8=DOWN 9=SWAP 10=LEFT 11=RIGHT
12=RECALL

```

Print Online Help Topics

You can use the PRINT command to print all or part of a command display. The printed output can be placed in a system output unit or disk data set.

Follow these steps:

- Execute the PRINT command with no parameters prints the entire current display to the current print data set.
- Execute the PRINT command with parameters prints the specified lines to the specified print data set.

Obtain Help within a Help Topic

Within the online help panel for a command, sections of information are labeled according to content. One or more of these labels are used in the online help panel of each command. You can use a label as a parameter on the LOCATE command to find specific information. When you do so, you need only use the uppercased portion of the label as the parameter.

This command has the following format:

Locate L

The following labels can be used within the online help panel of a command:

Command

Displays the command name, which is at the top of the online help panel.

Datafields

Displays the data fields on the display.

Format

Displays the command format.

Infofields

Displays the information fields on the display.

Linecommands

Displays the line available commands for this display.

Messages

Displays the messages that you could receive when issuing the command.

Notes

Displays usage notes for the command.

Parameters

Displays command parameters and their explanations.

Relatedinfo

Displays information that is related to the command.

Subcommands

Displays the subcommands that you can use on the display.

Example: Locate Valid Line Commands

You are looking at the online help for the SCMSYS command and want to see what line commands are valid for SCMSYS. At the command line of the SCMSYS online help panel, issue this command:

LOCATE *linecommands*

Chapter 3: Basic Tasks

This section contains the following topics:

[Overview of Your Profile](#) (see page 67)

[How to Change Your Display Format](#) (see page 72)

[How to Change PF Key Definitions](#) (see page 76)

[Initialization Command Options in the Profile](#) (see page 78)

[Change the Masking Characters](#) (see page 78)

[How to Work with Data on a Display](#) (see page 79)

[Customize Your Display](#) (see page 90)

[Print a Display](#) (see page 91)

Overview of Your Profile

As a CA SYSVIEW user, you have a profile that determines:

- How you can use the product
- What you see on your screen

Your system administrator could have defined or altered a profile for you, or you could be using a default profile. However, you can change your profile in ways that can help you use CA SYSVIEW to meet your own needs and the needs of your site. Knowing how to change your profile is basic to begin using CA SYSVIEW.

Use the PROFILE Command

The PROFILE command displays let you perform the following tasks:

- Define the synonyms for commands, values for PF keys, and formats for the command displays
- Change your general profile for all displays, or change only specific command displays
- Switch to the profile of another user

Switching to another profile means that you can acquire the settings from the profile of that user for your own. You can switch to the profile of another user by issuing this command:

```
PROFILE SWITCH,userid
```

userid

Specifies any CA SYSVIEW user ID.

Note: Switching to the profile of another user does not give you the command authority of that user. The security administrator sets the ability to use particular commands. Also, when you use the PROFILE command after switching profiles, the profile values of the profile you switched to will be displayed.

To see all the options you can set using the PROFILE command, see the PROFILE online help. Later in this chapter, you learn more about PROFILE displays and how to perform some representative tasks.

Keep in mind that changes you make to your profile using the PROFILE command are permanent.

SET Command—Change Your Profile

You can also use the SET command to change your profile. Issue the SET command at the command line with parameters to make one change at a time.

For example, you are using the ACTIVITY command display and want to set the PF6 key for that display so that it issues the CONSOLE command, type the following command on the command line:

```
SET PF6 CONSOLE
```

As with the PROFILE command, you can use the SET command both for the general profile (all displays) and for specific command profiles. To do so, you use the GENERAL or *command* parameter, respectively.

Most of the parameters that are defined in the profile can be changed with the SET command.

Access the PROFILE Command Displays

The PROFILE commands let you access the profile displays.

Review the following list of commands and their descriptions of what they display:

PROFILE

Specify this command from a menu to see the Command Selection Display, which shows all profile sections.

Specify this command on a CA SYSVIEW display to see the profile section for the active display command.

PROFILE SELECT

Displays the Command Selection display, which shows all of the profile sections.

PROFILE SELECT GENERAL or PROFILE GENERAL


Displays a selection menu showing only the general profile sections.

PROFILE SELECT *cmdname*

Displays a selection menu showing the profile sections for the command you specify.

How You Access Profile Displays

The following illustration shows how you can access PROFILE displays and how you can use them to change a profile.



Change Your Options Using the PROFILE Displays

Review the following representative list of options you can change using the PROFILE displays.

- General Profile

For all displays, you can set or change the following options:

- Default PF key designations for all commands
- Initialization and termination options
- Printing and copying options
- Special characters for commands and line commands
- Display options

- Command Profile

In most command profiles, you can set or change the following options:

- Alternate names (synonyms) for issuing the command
- PF key designations for the command (these designations override the GENERAL profile settings)
- PF key messages
- Default parameters for a command
- Command display format
- Date and time display options
- Whether to display the command-line prompt
- Initial sort parameters

Review the PROFILE Sections

You can learn about specific items that you can set or change.

Follow these steps:

1. Issue the PROFILE SELECT command at the command line.
2. Browse through the fields in the General and *command* profile sections.
3. Look at the listed items in a section by typing an **S** to the left of the item and press Enter.

For the explanations of the different options, use the PROFILE command online help.

Update Your Profile

To add a value for a field in a profile section, type it in. To change an item in the profile section list, type over the present value.

By default, your user profile is updated after you terminate your CA SYSVIEW session or switch to the profile of another user. However, you can save the change immediately by issuing the PROFILE SAVE command.

Note: You can override the default value and can specify that your changes can only be saved when you issue the PROFILE SAVE command. To do so, specify the following command at the command line:

```
SET PROFILESAVE COMMAND
```

On some profile displays, the CANCEL command can be used to cancel any changes to the current profile display.

How to Change Your Display Format

This section provides instructions on performing several representative tasks that change your display format.

You can change your display format by using either of the following methods:

- The PROFILE displays
- The SET command

You can use these tasks as a guide for changing other items in your profile. The procedure is similar.

For the details on the default display format and the names that are used for parts of the display, see the chapter "[Basic Skills](#) (see page 39)."

Change the Initial Display Format Name

The ability to customize how data is displayed makes a command easier and quicker to use and lets you tailor it for specific tasks.

Follow these steps:

Do one of the following steps:

- Go to the Formats section of the command PROFILE you want to change and specify the name of the format in the Format field.
- Specify the following command at the command line while you are on the display that you want to change:

```
SET FORMAT formatname
```

formatname

Specify either:

- The name of a format that you have created in your profile (a one- to eight-character name).
- DEFAULT to use the default format for the display.

For information about creating display formats, see [Change the Data Display Format](#) (see page 79) in this chapter.

The initial display format name is changed to the name you want to be used for a command display when the command is first entered.

Define Command Line Placement

You can define whether the command line appears at the top or bottom of your CA SYSVIEW displays.

Follow these steps:

Do one of the following steps:

- Go to the Display options area of the Miscellaneous Section of the General profile and type TOP or BOTTOM in the command-line placement field.
- Specify one of the following commands at the command line:

```
SET CMDLINE TOP  
SET CMDLINE BOTTOM
```

Note: The display is changed in several ways when you move the command line to the bottom of the display. For example, the CA SYSVIEW issued messages and the Row/Col field also move to different areas on the screen.

Change the Divider Lines Character

You can change the character that is used in the divider lines on your screen. The default character is the dash (-), but many characters are valid.

Follow these steps:

Do one of the following steps:

- Go to the Display character options area of the Miscellaneous Section of the General profile and place *x* in the Divider line character field.
- Specify the following command on the command line:

```
SET DIVCHAR x
```

The divider line character is changed to an *x*.

For more information about valid divider line characters, see the DIVCHAR character in the online help for the SET command.

Change the Row/Col Field Display

A number of settings affect the display of row and column numbers in the Row/Col field. You can elect to always display or never display the row and column counts, or you can make the display of the counts conditional. The conditional Row/Col field is on when at least one row or column is not visible on the display; otherwise, the field is off. Some commands internally suppress the display of the row and column counts (DUMP, for example), and there is no way to override this setting.

Follow these steps:

Do one of the following steps:

- Go to the Display options area in the Miscellaneous Section of the general profile and change the Display row counts and Display column counts fields to either ON, OFF, or COND.
- Use one of the following SET commands:

```
SET ROWCOUNT ON (or OFF or COND)
```

```
SET COLCOUNT ON (or OFF or COND)
```

Change the Separator Area

A number of settings affect the display in the separator area, the area that separates the header area on your display from the data area. The default is no separator area. You can change the separator to display a line.

Follow these steps:

■ Column Ruler Line

If the column ruler line is on, a horizontal column ruler is displayed. To display the column ruler line, use one of the following commands:

```
SET COLS ON  
COLS ON
```

To turn off the column ruler line, use one of these commands.

```
SET COLS OFF  
COLS OFF
```

You can also set the column ruler line on or off in some command displays. Specify ON or OFF for Column line field in the Display options area of the *command* profile Miscellaneous Section.

■ Separator Line

To specify whether the separator line is displayed, use one of the following commands:

```
SET SEPLINE ON  
SET SEPLINE OFF
```

You can also set the separator line on or off in some command displays. Specify ON or OFF for Separator line field in the Display options area of the *command* profile Miscellaneous Section.

■ Separator Character

To change the separator line character (by default, it is a blank), use the following command:

```
SET SEPCHAR x
```

x

A variable representing a valid separator line character.

For more information about valid separator line characters, see the SET SEPCHAR command explanation in the online help.

You can also change the value in the Separator line character in the Miscellaneous Section of your General profile under Display character options.

Change the PF Message Area

You can determine what is displayed in the PF message area using the PF Keys Section of your General profile. You can specify what you want displayed in two message lines. If the PF key settings are set to show, they overlay this area.

Display the PF Key Settings

You can set up CA SYSVIEW to list the settings of your PF keys on a command display.

Follow these steps:

1. Define the Message fields in the PF Keys Section of your general profile.
2. Specify YES in the PF message lines field under Display options of the Miscellaneous Section of the *command* profile.

When you are using a display, you can use the PFSHOW command to display the PF key settings.

More information

[View the PF Key Settings](#) (see page 49)

How to Change PF Key Definitions

This section provides instructions on performing several representative tasks that change your PF key definitions.

Change the setting for a PF key using either of the following methods:

- Change the value for the key in the Profile General PF Keys Section of your profile
- Use the SET command

For example, to change the setting of the PF2 key from SPLIT to RECALL, you would issue the following command:

```
SET PF2 RECALL
```

Change ISPF PF Keys

You can change your current PF key settings in your CA SYSVIEW profile without affecting the KEYS command.

Follow these steps:

1. Issue the CA SYSVIEW KEYS command.
The ISPF KEYS command is invoked and displays the PF Key Definitions and Labels panel.
2. Assign the PF keys to the ISPF commands and optionally assign labels to the function key definitions.

For more information about the ISPF KEYS command, see your IBM ISPF documentation.

Change the PF Key Values for Different Displays

You can specify different PF key definitions for each CA SYSVIEW display. For example, change your PF7 key to issue the ACTIVITY command from the CONSOLE display, and to issue the CONSOLE command from the ACTIVITY display.

Follow these steps:

1. Access the PF Keys Section of your profile.
2. Change the PF7 key definition to include the ACTIVITY and CONSOLE commands.

Your PF7 key definition has been changed for the ACTIVITY and CONSOLE commands.

Initialization Command Options in the Profile

Specifying the values for initialization options makes a command easier and quicker to use and lets you tailor it for specific tasks.

Review the following options in the Miscellaneous Section of the *command* PROFILE under Initialization options:

Default Parameters

Controls the parameters that are used with the command by default. The default parameters for the command are used whenever the command is entered without parameters. Entering the parameters with the command overrides the default parameters. To use a parameter with a command when you issue it, specify that parameter here.

Link-to Command

Specifies whether to invoke implicitly the command with the LINK command. Values are YES and NO.

The LINK command saves the current command environment, while passing control to another command. Therefore, specifying YES on this option in your profile for the ACTIVITY command, the current environment is saved when you issue the ACTIVITY command.

Change the Masking Characters

You can use masking characters when entering some values on some command parameters. The default masking characters are:

- An asterisk (*) for the fixed length masking character
- An equal sign (=) for the variable-length masking character

You can change the default masking characters.

Follow these steps:

1. Issue the PROFILE GENERAL command.
The default profile displays.
2. Select the Miscellaneous Section.
The General Section - Miscellaneous Section is displayed.
3. Find the Input character options and type in new values for the fixed length masking character and the variable-length masking character.
Press PF3 to save your changes and start using the new masking characters.

You can also use the SET command to change these variables. For example, to change the fixed length masking character or variable-length masking character, you would specify:

```
SET FLM|VLM value
```

value

Specifies the new masking character.

For more information about using masking characters when entering parameters on commands, see the chapter “Basic Skills.” For the values you can use for the FLM and VLM parameters, see the SET command online help.

How to Work with Data on a Display

You can change how data appears on your screen so that it meets your work needs. One way is by changing your data display format in your profile. However, there are other ways to affect how data is displayed without using the PROFILE or SET command.

Methods for changing the way that data appears on your displays are described in the following sections.

Change the Data Display Format

You or your security administrator can change CA SYSVIEW displays by updating the Formats Section of the *command* profile. You name these formats and use them to make your displays easy to use.

Follow these steps:

1. Issue the following command:

```
PROFILE command
```

The display shows the profile sections for that command.

2. Select the Formats Section as shown on the following display for the ACTIVITY command and press enter.

```

SYSVIEW PROFILE ----- Profile for SYSVUSER -----
Command ==>                                         Scroll *==> HALF
----- Lvl 3 Row 1-4/4
Settings for ACTIVITY
-----
Cmd Section
___ Synonyms
___ PF Keys
___ Miscellaneous
S_ Formats
===== End of Data =====
    
```

The following screen displays showing that the ACTIVITY command has one screen that is named ACTIVITY and the default format is CPU:

```

SYSVIEW PROFILE ----- Profile for SYSVUSER -----
Command ==>                                         Scroll *==> HALF
----- Lvl 4 Row 1-4/4 Col 1-79/255
Settings for ACTIVITY - Formats section
-----
Cmd Screen  Format  Description
_  ACTIVITY CPU    System activity
===== End of Data =====
    
```

3. Change the default format for a screen using either of the following methods:
 - Enter the name in the Format field
 - Create a format for a screen by entering an S in the Cmd field next to the screen and press Enter.

A screen similar to the following displays:

```

SYSVIEW PROFILE ----- Profile for SYSVUSER -----
Command ==>                                         Scroll *==> HALF
----- Lvl 4 Row 1-4/4 Col 1-79/255
Settings for ACTIVITY - Formats section for screen ACTIVITY
-----
Cmd Name    Description                               SortParms
___ DEFAULT  Select line + enter name to add             CPU%,D
___ CPU      ACTIVITY command 1 format                   CPU%,D
___ 2        ACTIVITY command 2 format                   CPU%,D
___ 3        ACTIVITY command 3 format                   CPU%,D
___ 4        ACTIVITY command 4 format                   CPU%,D
===== End of Data =====
    
```

This screen shows that the System Activity display already has five defined formats.

4. Change a format that is already defined by selecting that format with an S in the Cmd field and press Enter.
5. Add a format as follows:
 - a. Place an S in the Cmd field next to DEFAULT.
 - b. Overtyping DEFAULT with the name for the new format you are adding; then press Enter.

The data display format is changed or a new format is added when the screen refreshes.

Note: You can also specify parameters SORT and SELECT for formats on this display.

Change the Order of Fields and Exclude Fields

When you have finished changing the data display format, you can:

- Change the order of the fields on the display.
- Exclude the fields from the display.

When you press Enter from the System Activity display, you access a display similar to the following one. This display shows the profile for the ACTIVITY command in the format CPU.

```

SYSVIEW PROFILE ----- Profile for SYSUSER -----
Command ==>>>
                                           Scroll *==> ALF
----- Lvl 5 Row 1-16/45 Col 1-79/331
Settings for ACTIVITY - Screen ACTIVITY - User format CPU
-----
Cmd FieldName      AlternateName    Length DefLng DataLng Column Scroll XSys
___  ___          _____
___  Cmd           _____        4     4     3     1
___  Jobname       _____        9     9     8     5
___  Stepname      _____        9     9     8    14 SCROLL
___  Procstep      _____        9     9     8    23
___  Type          _____        5     5     4    32
___  Jobnr         _____        7     7     7    37
___  Jc            _____        3     3     1    44
___  Status        _____        8     8     6    47
___  CPU-Time      _____       10    10     8    55
___  CPU%          _____        7     7     6    65
___  Paging        _____        8     8     7    72
___  Limit         _____        6     6     5    80
___  Clocktime     _____       10    10     8    86
___  SRB-Time      _____        9     9     8    96
___  I/O-Count     _____       11    11    10   105
___  IO/Sec        _____        7     7     6   116

```

On this display, place the following values in the Cmd field to help change the order of fields or exclude them from a display.

M

Place an M next to the field to be moved.

A

Place an A next to the field after which the field marked with an M is to move.

B

Place a B next to the field before which the field marked with an M is to move.

D

Exclude this field from the display. The excluded fields appear at the bottom of the list. You can use M to move them, at which point they are “included” again.

S

Scrolling to the right begins with this field. The starting column of the field must be less than the terminal line size.

Provide an Alternate Name for a Field

To provide an alternate name for a field, type the name in the Alternate Name field next to the field name.

Use a Format for a Display

When your new display format is created, you can implement it.

Follow these steps:

1. Issue the command and, on the command line of the *command* display, type the following command:

```
SET FORMAT formatname
```

formatname

Specifies the name of the format you created.

2. To change the format name back to the default, issue this command:

```
SET FORMAT DEFAULT
```

You can also specify the format name for a display on the first Formats Section display that lists the screens for a command.

More information:

[Change the Data Display Format](#) (see page 79)

Change Parameter Values Using the Parameter Area

You can change parameters for several of the CA SYSVIEW displays by using the parameter area above the heading lines of displays.

Follow these steps:

1. Type over the current value with a new value and press Enter.

The data is redisplayed so that it reflects the new parameter value.

2. Change the value of the existing Type value by typing over the SYS value in the parameter area with another value and press Enter. For example, replace SYS with ALL.

The new display reflects this change.

Example: Activity Display

An ACTIVITY display with the Type value SYS shown in the parameter area.

```

SYSVIEW ACTIVITY ----- System Activity -----
Command ==>
                                           Scroll *==> HALF
----- Lvl 2 Row 1-16/21 Col 1-79/348
Status: NOSORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
CPU 100% LCPU 42% Paging 0   SIO 198   UIC 300   AFC 21639
-----
*
Cmd Jobname  Stepname  Procstep  Type  Jobnr  Jc  Status  CPU-Time  Limit  Clocktime
--- *MASTER*  ---      ---      ---      ---      ---  ---      ---      ---      ---
--- PCAUTH    PCAUTH    ---      SYS      ---      ---  NS      0.021     ---      5.42DAYS
--- RASP      RASP      ---      SYS      ---      ---  NS      0.008     ---      5.42DAYS
--- TRACE    TRACE     ---      SYS      ---      ---  NS      0.007     ---      5.42DAYS
--- DUMPSRV   DUMPSRV   DUMPSRV  SYS      ---      ---  NS      00:01:38  86400   5.42DAYS
--- GRS       GRS       ---      SYS      ---      ---  NS      01:10:01  ---      5.42DAYS
--- SMXC      SMXC      ---      SYS      ---      ---  NS      00:07:54  ---      5.42DAYS
--- SYSBMAS   SYSBMAS   ---      SYS      ---      ---  NS      50.963    ---      5.42DAYS
--- CONSOLE   CONSOLE   ---      SYS      ---      ---  NS      01:42:36  ---      5.42DAYS
--- WLM       WLM       IEFPROC  SYS      ---      ---  NS      00:52:30  86400   5.42DAYS
--- IEFCHAS   IEFCHAS   ---      SYS      ---      ---  NS      0.007     ---      5.42DAYS
--- IXGLOGR   IXGLOGR   IEFPROC  SYS      ---      ---  NS      0.585     86400   5.42DAYS
--- SMF       SMF       IEFPROC  SYS      ---      ---  NS      5.318     86400   5.42DAYS
--- TNF       TNF       ---      SYS      ---      ---  NS      0.008     ---      5.42DAYS

```

Change the Data Fields

You can type over some data fields on the CA SYSVIEW displays to change the information that is on the display and refresh the screen. The fields that you can overwrite are identified in the field descriptions for each display. In general, if you can tab to a data field, you can type over it.

Follow these steps:

1. Tab to a data field that you want to change.
2. Type over the data field and press Enter.
 - The commands execute.
 - The change is made.
 - The display is refreshed.

For more information about fields that you can overwrite or defining which data fields you can overwrite, contact your security administrator.

Change the Order of Data on a Display

You can use the SORT command to change the order of data as it appears in columns on your screen. The SORT command helps you to view data in the order that is most useful to you.

- According to Field

One useful way to sort data is under a column heading (field) in either ascending or descending order. This sample ACTIVITY display shows the field CPU% in ascending order.

```

SYSVIEW ACTIVITY ----- System Activity -----
Command ==>
----- Lvl 2 Row 1-17/414 Col 1-79/342
CPU 100% LCPU 35% Paging 0 SIO 76 UIC 300 AFC 21639
-----
*
ALL ALL
Cmd Jobnr Jobname Stepname Procstep Jc Type Status CPU% CPU-Time Clocktime
--- 2316 *MASTER*
--- PCAUTH PCAUTH SYS NS 0.63 00:27:22 81:21:25
--- RASP RASP SYS NS 0.00 0.009 81:21:25
--- TRACE TRACE SYS NS 0.00 0.007 81:21:25
--- DUMPSRV DUMPSRV DUMPSRV SYS NS 0.00 00:01:39 81:21:21
--- XCFAS XCFAS IEFPROC STC NS 0.44 00:49:48 81:21:16
--- GRS GRS SYS NS 0.87 00:16:12 81:21:25
--- SMXC SMXC SYS NS 0.04 00:04:34 81:21:25
--- SYSBMAS SYSBMAS SYS NS 0.00 28.487 81:21:25
--- CONSOLE CONSOLE SYS NS 1.33 00:49:08 81:21:25
--- WLM WLM IEFPROC SYS NS 0.62 00:30:02 81:21:22
--- ANTMAIN ANTMAIN IEFPROC STC NS 0.00 0.067 81:21:17
--- ANTAS000 ANTAS000 IEFPROC STC NS 0.00 0.227 81:21:11
--- OMVS OMVS OMVS STC NS 0.00 40.916 81:21:13
--- IEFCHAS IEFCHAS SYS NS 0.00 0.008 81:21:25
--- JESXCF JESXCF IEFPROC STC NS 0.00 00:01:45 81:21:13
--- ALLOCAS ALLOCAS SYS NS 0.00 0.010 81:21:25

```

To put the data in the field CPU% on this display in descending order, specify the following command on the command line:

```
SORT CPU% D
```

This command displays a screen like the following one. The D parameter caused the values in the CPU% field to be listed in descending order. Specifying A (ascending) lists the values in ascending order.

```

SYSVIEW ACTIVITY ----- System Activity -----
Command ==>                                     Scroll *==> HALF
----- Lvl 2 Row 1-17/414 Col 1-79/342 -----
CPU 100% LCPU 35% Paging 0 SIO 76 UIC 300 AFC 21639
-----
*
ALL ALL
Cmd Jobnr Jobname Stepname Procstep Jc Type Status CPU% CPU-Time Clocktime
--- 2423 CICSPROD CICSPROD CICS $ STC NS 21.55 03:10:51 81:17:59
--- 1136 IXRASUBS IXRASUBS IEFPROC $ STC NS 11.05 00:18:41 14:45:25
--- 2333 NET NET A44X $ STC NS 7.88 05:34:28 81:19:29
--- 2334 RMF RMF IEFPROC $ STC NS 4.08 00:35:23 81:19:29
--- 2586 CCITCPGW CCITCPGW CCITCPGW $ STC NS 3.18 00:33:56 81:17:07
--- 1562 KNUJ001 CATSO A55TG013 @ TSU LSW 2.30 6.346 01:27:48
--- 2362 TCP44 TCP44 TCP44 $ STC NS 2.18 00:40:23 81:18:54
--- JES JES IEFPROC STC NS 2.01 00:48:19 81:20:26
--- CONSOLE CONSOLE SYS NS 1.33 00:49:08 81:21:25
--- 2615 SYSQA02 SYSQA02 I JOB NS 1.13 00:07:10 17:50:14
--- 1281 ROSCOE ROSCOE ROSCOE $ STC NS 0.96 36.883 07:03:28
--- 2398 ENF ENF ENF $ STC NS 0.94 00:21:23 81:18:05
--- GRS GRS SYS NS 0.87 00:16:12 81:21:25
--- 1300 SYSTEM23 SYSTEM23 $$$@NX@ $ STC NS 0.80 40.133 06:13:40
--- 3938 SUP$TE10 TECHDC10 I JOB NS 0.78 00:05:36 45:21:14
--- 9073 SYSQA03 SYSQA03 I JOB NS 0.67 00:07:50 22:02:58
--- 1307 SYSTEM47 SYSTEM47 $$$@NX@ $ STC NS 0.66 41.750 06:12:48

```

■ Start and End Columns

You can also sort data using start and end column numbers to define a range of data within a display field. This data can also be put in ascending or descending order.

To sort the data between two columns on the ACTIVITY display in ascending order, specify the following command on the command line and press enter:

```
SORT 11 18 A
```

Note: To show the column ruler on your screen, specify SET COLS ON to find out the column numbers where the data begins and ends. In this example, 11 and 18.

This command displays a screen like the following one. The parameter caused the values beginning in column 11 and ending in column 18 to be listed in ascending order.

```

SYSVIEW ACTIVITY ----- System Activity -----
Command ==>                                     Scroll *==> HALF
----- Lvl 2 Row 1-15/399 Col 1-79/342
Status:  SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
CPU 100% LCPU 45% Paging 0   SIO 230   UIC 300   AFC 21639
-----
*
ALL ALL
....+....10...+....20...+....30...+....40...+....50...+....60...+....70...+...
Cmd Jobnr Jobname  Stepname Procstep Jc Type Status  CPU% CPU-Time Clocktime
----
*LOGON*      A01TD015  TSU  OUT  TI  0.00  0.014
*LOGON*      A55TG034  TSU  OUT  TI  0.00  0.012
*LOGON*      A55TG036  TSU  OUT  TI  0.00  0.012
3242 *MASTER*
3931 ADAMP1    ADADB01  $$$$@  3  JOB  NS    0.00  12.799  21:50:22
      ALLOCAS  ALLOCAS  SYS  NS    0.00  0.010  5.42DAYS
5318 ANDNI02  CATSO    A01TD003 @  TSU  OUT  TI  0.00  17.392  06:21:28
      ANTAS000  ANTAS000  IEFPROC  STC  NS    0.00  0.278  5.42DAYS
      ANTMAIN  ANTMAIN  IEFPROC  STC  NS    0.00  0.067  5.42DAYS
      APPC    APPC    APPC    STC  NS    0.00  1.852  5.42DAYS
      ASCH    ASCH    ASCH    STC  NS    0.00  00:01:03  5.42DAYS
3269 ASCHINT  ASCHINT  IEFPROC  $  INIT  OUT  LW    0.004
3270 ASCHINT  ASCHINT  IEFPROC  $  INIT  OUT  LW    0.004
3271 ASCHINT  ASCHINT  IEFPROC  $  INIT  OUT  LW    0.004
3272 ASCHINT  ASCHINT  IEFPROC  $  INIT  OUT  LW    0.004

```

- Special sort options

You can specify special options on the SORT command to either:

- Return the data to the order created by the original command
- Request that data be sorted as specified in the *command* profile Formats Section

For more on how you can change your user profile, see the sections in this chapter on the PROFILE command.

You can also specify the current SORT parameters on the command line and overtype them. For the details about using the SORT command and its parameters, see the SORT command online help.

Select Particular Rows of Data to Display

You can display particular rows of data using the SELECT command. You can select the rows according to the values that appear under the column headings. You can display all rows that have a particular field value.

Sample ACTIVITY display.

```

SYSVIEW ACTIVITY ----- System Activity -----
Command ==>                                     Scroll *==> HALF
----- Lvl 2 Row 1-16/402 Col 1-79/342
Status: NOSORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
CPU 100% LCPU 42% Paging 14 SIO 293 UIC 300 AFC 21639
-----
*
ALL ALL
Cmd Jobnr Jobname Stepname Procstep Jc Type Status CPU% CPU-Time Clocktime
--- 3242 *MASTER*
--- PCAUTH PCAUTH          SYS NS      0.00 0.021 5.42DAYS
--- RASP RASP             SYS NS      0.00 0.008 5.42DAYS
--- TRACE TRACE           SYS NS      0.00 0.007 5.42DAYS
--- DUMPSRV DUMPSRV DUMPSRV  SYS NS      0.00 00:01:38 5.42DAYS
--- XCFAS XCFAS IEFPROC   STC NS      0.14 01:18:40 5.42DAYS
--- GRS GRS              SYS NS      0.18 01:10:02 5.42DAYS
--- SMXC SMXC             SYS NS      0.11 00:07:55 5.42DAYS
--- SYSBMAS SYSBMAS     SYS NS      0.00 51.094 5.42DAYS
--- CONSOLE CONSOLE      SYS NS      0.14 01:42:47 5.42DAYS
--- WLM WLM IEFPROC     SYS NS      0.20 00:52:36 5.42DAYS
--- ANTMAIN ANTMAIN IEFPROC   STC NS      0.00 0.067 5.42DAYS
--- ANTAS000 ANTAS000 IEFPROC   STC NS      0.00 0.278 5.42DAYS
--- OMVS OMVS OMVS       STC NS      0.04 58.781 5.42DAYS
--- IEFSCHAS IEFSCHAS  SYS NS      0.00 0.007 5.42DAYS
--- JESXCF JESXCF IEFPROC   STC NS      0.00 00:03:14 5.42DAYS

```

You want the display to show only entries with a value greater than two in the CPU field. Filter the display by entering the following command on the command line:

```
SELECT CPU% > 2
```

When you press Enter, you would see the following display.

```

SYSVIEW ACTIVITY ----- System Activity -----
Command ==>                                     Scroll *==> HALF
----- Lvl 2 Row 1-5/5 Col 1-79/342
Status: NOSORT SELECT NODEST NOPREFIX NOOWNER NOUPDATE
CPU 99% LCPU 54% Paging 13 SIO 165 UIC 300 AFC 21639
-----
*
ALL ALL
Cmd Jobnr Jobname Stepname Procstep Jc Type Status CPU% CPU-Time Clocktime
--- 3258 NET NET A44X $ STC NS 4.68 08:23:00 5.42DAYS
--- 3339 CSQ1MSTR CSQ1MSTR CSQ1MSTR $ STC NS 7.58 02:30:08 5.42DAYS
--- 3340 CSQ2MSTR CSQ2MSTR CSQ2MSTR $ STC NS 3.94 01:46:34 5.42DAYS
--- 5727 OLEJU01 CATSO A55TG012 @ TSU IN 6.36 25.152 00:17:42
===== End of Data =====

```


Methods for Specifying Options on a Command

You can display specific values on a display using the following methods:

- Operators

Operators let you associate the field with the value and determine that those rows be displayed. You can use many operators:

- Greater than: > or GR
- Equal to: EQ or =
- Greater than or equal to: GE or >=
- Blank or No Blank: B or NB

You would not specify a value after the B or NB field and the operator.

- COND Keyword

You can use the condition (COND) keyword in place of a field name to specify selection for all fields that are defined as status fields on the current screen. You do not have to name them individually. Several requirements exist for specifying this keyword. To learn more about this option, see the SELECT command online help.

- Multiple Fields

You can select data to display according to more than one field by specifying parameters on the SELECT command using the *conn* parameter.

- Special Options

As with the SORT command, you can specify special options on the SELECT command to either:

- Return the data to the order created by the original command.
- Request that data be sorted as specified in the profile Formats Section.

You can also specify the current SELECT parameters on the command line and overwrite them. See the SELECT command online help.

Customize Your Display

You can customize your display by choosing the color of the fields on your display, or whether to highlight them. You can also modify the field according to its type-input or output.

Follow these steps:

1. Modify the attributes of the fields that appear on your displays using the SCREEN.

The following sample screen displays when you issue the SCREEN command:

```

SYSVIEW SCREEN ----- Screen Field Attributes -----
Command ==>                                         Scroll *==> HALF
----- Lvl 3 Row 1-17/50 -----
Status:      SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
Dev color   YES  Dev hilite  YES  Use color COND  Use hilite COND
-----
Name        Type    Intens  Color   Hilite  Description
ARrow       OUTPUT HIGH    GREEN   NONE    Arrow prompts for input fields
BARgraph    OUTPUT LOW     BLUE    REVERSE Bar graph
BARGRAPHHi  OUTPUT HIGH    YELLOW  REVERSE Hilited bar graph
BARNormal   OUTPUT LOW     GREEN   REVERSE Normal condition bar graph
BARProblem  OUTPUT HIGH    RED     REVERSE Problem condition bar graph
BARWarning  OUTPUT LOW     YELLOW  REVERSE Warning condition bar graph
COLumns     OUTPUT HIGH    BLUE    NONE    Column ruler line
CONDHi      OUTPUT HIGH    TURQUOISE REVERSE Hilited condition status field
CONDNormal  OUTPUT LOW     GREEN   REVERSE Normal condition status field
CONDProblm  OUTPUT HIGH    RED     REVERSE Problem condition status field
CONDWarnng  OUTPUT LOW     YELLOW  REVERSE Warning condition status field
DATA        OUTPUT LOW     GREEN   NONE    Data lines
DATAHi      OUTPUT HIGH    TURQUOISE NONE    Data line hilited fields
DIdiver     OUTPUT LOW     GREEN   NONE    Divider lines
DUmmy       INPUT  LOW     YELLOW  NONE    Dummy data input fields
DUMMYHi     INPUT  HIGH    TURQUOISE NONE    Hilited dummy data input fields
Eodata      OUTPUT LOW     GREEN   NONE    End of data line
    
```

The Fields are listed in the first column.

2. Change the attributes of the field using one of the following methods:
 - Overtyping the attribute values for them.
 - Specifying the SCREEN command with parameters, indicating the field and how you would like it to be changed.

For example, to make all input fields on your displays white, either overtype the value for the field in the Color column, or specify:

```
SCREEN INPUT WHITE
```

For attribute values you can specify for the field, and for other details about the SCREEN command, see the SCREEN command online help.

Print a Display

You can print a display using the PRINT command. The printed output for the display can be sent to a printer or placed in a data set.

Follow these steps:

- To print the whole display, issue the following command:

```
PRINT ALL
```

- To print what is on the screen, issue the following command:

```
PRINT SCREEN
```

- To print specified lines on the display. For example, to print lines 5 through 20 on a display, issue the following command:

```
PRINT FROM 5 TO 20
```

Once you issue a PRINT command, all output from subsequent PRINT commands goes to the same file until you issue a PRINT CLOSE command.

Note: For other printing options you can use, see the online help for information about the PRINT command.

Chapter 4: MVS Displays

This section contains the following topics:

[About the MVS Displays](#) (see page 93)

[DASD Units Display](#) (see page 93)

[MVS Exception Alerts Display](#) (see page 95)

[Console Display](#) (see page 97)

[Processor Information Display](#) (see page 98)

[Access the APF List Display](#) (see page 99)

[Access the LINKLIST Libraries Display](#) (see page 100)

[Subsystem Detail Display](#) (see page 102)

About the MVS Displays

This chapter describes some representative MVS resource displays and some tasks you can perform on them.

In addition to the displays described in this chapter, you can use many other displays to view MVS resource displays. To see menus of the commands you can use, specify **MENU MVS** on the command line. This menu contains other menus that let you view different types of information, including status, storage, devices, data sets, and so on.

DASD Units Display

You can use the DASD Units display to view the status of DASD devices in the system. This display shows you information about a device, limited by volume, unit type, usage type, and current status.

To access the display, issue the DASD command.

The sample DASD Units display:

```

SYSVIEW DASD ----- DASD Units -----
Command ==>                                     Scroll *==> HALF
----- Lvl 2 Row 1-17/1097 Col 1-79/252
Interval 2.1
-----
  *      ONLINE *      *      ALL
Cmd Volser Status Devn Unit  Usage  Shr  Jobname  ASID AM  IORt  IOct
--- ACFOA1 ONLINE 2E26 3390-3 PRIVATE SHR
--- ACF001 ALLOC 054F 3390-3 PRIVATE SHR JAC$1215 0091 1432
--- ACUT05 ALLOC 2E40 3390-3 PRIVATE SHR IXRASUBS 0197 9613
--- ACUT06 ALLOC 2E45 3390-3 PRIVATE SHR ASTEX 022D 30112
--- ACUT07 ALLOC 2120 3390-3 PRIVATE SHR ASTEX 022D 38187
--- ADBA01 ALLOC 2D20 3390-3 PRIVATE SHR WILDI04S 016A 50231
--- ADBA02 ALLOC 2D21 3390-3 PRIVATE SHR STAD00NL 0085 52931
--- ADBA03 ALLOC 2D22 3390-3 PRIVATE SHR WILDI04S 016A 6407
--- ADBA04 ALLOC 2D23 3390-3 PRIVATE SHR ASTEX 022D 57649
--- ADBA05 ALLOC 2D24 3390-3 PRIVATE SHR WILDI04S 016A 26237
--- ADBA06 ALLOC 2D25 3390-3 PRIVATE SHR WILDI04S 016A 25392
--- ADBA07 ALLOC 2D26 3390-3 PRIVATE SHR ASTEX 022D 63687
--- ADBA08 ALLOC 2D27 3390-3 PRIVATE SHR WILDI04S 016A 41642
--- ADBA09 ALLOC 2D28 3390-3 PRIVATE SHR WILDI04S 016A 1205
--- ADBA10 ALLOC 2D29 3390-3 PRIVATE SHR INIT 00EE 40368
--- ADBA11 ALLOC 2D2A 3390-3 PRIVATE SHR WILDI04S 016A 40306
--- ADBA12 ALLOC 2D2B 3390-3 PRIVATE SHR STAD002P 001E 30384
    
```

Tasks Performed from the DASD Units Display

You can perform the following line commands from this display. You only must specify the uppercase portion of the line command.

To issue these commands, place your cursor in the Command input area to the left of the variable you would like to affect.

Space

Display allocated free DASD space for the selected volser.

Link-to Command: SPACE

Vtoc

Display data sets for the selected volser.

Link-to Command: VTOC

DSinfo

Display information about the DASD volume.

Link-to Command: DSINFO VTOC

Output

Display the output of the job that last allocated the unit.

Link-to Command: OUTPUT

Plot, PLt

Display a plot selection list for the selected volser.

Link-to Command: PLOTLIST DEVICE

MVS Exception Alerts Display

You can use the MVS Exception Alerts display to view exception alerts for thresholds that have been defined to the MVS data collector. If the current value exceeds a threshold definition, the data collection value is displayed. You can display alerts for both problem and warning thresholds.

To access the display, issue the ALERTS command.

Note: The THRESH command displays thresholds that have been defined.

The sample MVS Exception Alerts display:

```

SYSVIEW ALERTS ----- MVS Exception Alerts -----
Command ==>
                                           Scroll *==> HALF
----- Lvl 2 Row 1-15/15 Col 1-79/211
Cmd  Name      Argument Alias      Value  Status  Description
----  -
CPU%  ALL          100%   PROBLEM CPU usage percentage
.     0000         100%   PROBLEM CPU usage percentage
.     0001         100%   PROBLEM CPU usage percentage
.     0002         100%   PROBLEM CPU usage percentage
.     0003         100%   PROBLEM CPU usage percentage
JOBECSA NET      0032    5.22M  PROBLEM E-CSA storage allocated
JOBSTG  *MASTER* 0001    56.4M  PROBLEM Real storage
STGESQA% 110%   PROBLEM E-SQA storage allocated pct
STGESQAF 48.2K  PROBLEM E-SQA storage free
STGSQAF 355K   WARNING SQA storage free
JOB      D51JMSTR  0      INACTIVE Job required to be active
.       D51JMSTR  0      INACTIVE Job required to be active
.       NETVIEW   0      INACTIVE Job required to be active
.       NETWSSI   0      INACTIVE Job required to be active
.       SYSVCPAS  0      INACTIVE Job required to be active
===== End of Data =====

```

Tasks Performed from the MVS Exception Alerts Display

You can perform the following line commands from this display. You only must specify the uppercase portion of the line command.

To issue these commands, place your cursor in the Command input area to the left of the variable you would like to affect.

Select

Dynamically provide more information about the selected data element using the PLOT or CLIST command. If a member for this variable has been defined in the CLISTLIB, the CLIST command is executed. If a member name does not exist, the PLOT command is executed.

Link-to Command: PLOT or CLIST

Plot

Display a graph of performance data for the selected data element.

Link-to Command: PLOT

CLIST

Issue the CLIST command for the selected data element.

The following CLIST command is issued:

```
CLIST member ,, argument alias
```

member - Variable name. If the variable name contains the percent character (%), this character translates to the letter "P" to generate a valid member name.

argument - Passed as parameter 1

alias - Passed as parameter 2

Thresh

Display threshold information for the selected variable name.

Link-to Command: THRESH

Variable

Display a variable definition for the selected variable name.

Link-to Command: VARS

Console Display

Use the Console display to view the currently displayed messages on any active console. You can use the console facilities without having to go to the computer room.

To access the Console display, issue the CONSOLE command.

To view messages for a console, specify the console ID on the CONSOLE command. The default ID is the ID of the master console.

Note: Another console command is the XCONSOLE command, which establishes an MVS extended console session, where the user can both issue commands and receive responses. For more information, see the XCONSOLE command online help.

The sample Console display:

```

SYSVIEW CONSOLE ----- Console -----
Command ==>>>                               Scroll *==>> HALF
----- Lvl 2 Row 21-39/39 Col 1-79/191
Id=20 Devn=0902 Mode=R Backlog=1   Name=ALTIXE44 Sys=XE44   Cmdsys=XE44
-----
- 09.25.33 JOB00485 $HASP375 DOROL01D ESTIMATE EXCEEDED BY          260,
- 000 LINES 1 % SPOOL
 09.25.36 JOB01504 $HASP308 G325EXEC ESTIMATED TIME EXCEEDED BY 110
MINUTES
 09.25.37 STC03697 CAS9899E - Error: Invalid CTH header received
 09.25.37 STC03697 CAS9890E - Vers: 6 Cpu: 7
*09.25.38          *$HASP050 JES RESOURCE SHORTAGE OF TGS - 85%
* UTILIZATION REACHED
 09.25.39          $HASP893 VOLUME(SPL04A)                          C
$HASP893 VOLUME(SPL04A) STATUS=ACTIVE,TGNUM=16500,
$HASP893          TGINUSE=14044,TRKPERTGB=3,PERCENT=85
 09.25.39          $HASP646 85.1151 PERCENT SPOOL UTILIZATION
 09.25.40 JOB01523 $HASP308 PC3AEXEC ESTIMATED TIME EXCEEDED BY 100
MINUTES
 09.25.40 JOB01697 $HASP100 DBDRIUTL ON INTRDR      IVEDA01
FROM STC01281 ROSCOE
 09.25.40 JOB01503 $HASP308 G315EXEC ESTIMATED TIME EXCEEDED BY 110
MINUTES
- 09.25.40 JOB01697 TSS7053I Default ACID <BATCHDEF> Assigned
    
```

Tasks Performed from the Console Display

You can perform the following line command from this display. You only specify the uppercase portion of the line command.

To issue these commands, place your cursor in the Command input area to the left of the variable you would like to affect.

Delete

Delete the message from the MVS console screen. The message is marked as a candidate for deletion. When space is required on the screen, the message is physically deleted.

Processor Information Display

The Processor Information display lets you view information about processors. You can view the busy percentage, mode, job name, and ASID.

To access the display, issue the CPU command.

Tasks Performed from the Processor Information Display

You can perform the following line commands from this display. You only specify the uppercase portion of the line command.

To issue these commands, place your cursor in the Command input area to the left of the variable you would like to affect.

Select

Display job output for the job active on the selected processor.

Link-to Command: OUTPUT

Plot

Display a plot of the CPU busy percentage for the selected processor.

Link-to Command: PLOT

Access the APF List Display

The APF List display shows you data set information in the authorized program facility (APF) list. Use line commands and subcommands to alter dynamically this list.

To access the display, issue the APFLIST command.

The sample APF List display:

```

SYSVIEW APFLIST ----- APF List -----
Command ==>                                     Scroll *==> HALF
                                                Lvl 2 Row 1-17/451
Status:   SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
APFLIST format is DYNAMIC
-----
Cmd  Dataset-Name                               Volser  Status
---  -
ADD .APFLIST.DATASET.NAME                     ADDVOL
ANF .SANFLOAD                                  MVR25A
AOP .SAOPLOAD                                  MVR25A
APC .DEVCA7 .CL233 .LOADLIB                    APCD06
APC .DEVCA7 .L230 .CALLIB                      APCD98
APC .DEVCA7 .SECLIB                            APCD06
APC .DEVCA7 .TS04 .LOADLIB                    APCD98
APC .DEVCA7 .TS04 .TESTLIB                    APCD98
APC .DEVCA7 .TS044 .CAILIB                   APCD98
APC .DEVL232 .CAILIB                          APCD10
APC .LV1CA7 .L29302 .LOADLIB                  APCD98
APC .LV1JT .V3R3 .P9504 .TRACLINK            APCD10
APC .LV2CA7 .TEST .CAILIB                    APCD09
APC .LV2CA7 .TEST4 .CAILIB                   APCD08
APCDAL .L233X .CAILIB                        APCD06
APCMTL .CU1B .CHQA .SESFLNK                  APCM06
APCMTL .DS60P .DS9710 .CAILIB                APCM07

```

Tasks Performed from the APF List Display

To verify that the data sets listed exist on the specified volumes, use the VERIFY subcommand on the APF List command.

The example of an APF List display after the VERIFY subcommand has been issued.

```

SYSVIEW APFLIST ----- APF List -----
Command ==>                               Scroll *==> HALF
APFL004I VERIFY complete - 82 errors detected ----- Lvl 2 Row 1-17/451
Status:   SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
APFLIST format is DYNAMIC
-----
Cmd  Dataset-Name                               Volser  Status
---  -
ADD.APFLIST.DATASET.NAME                     ADDVOL
ANF.SANFLOAD                                  MVR25A  FOUND
AOP.SAOPLOAD                                  MVR25A  FOUND
APC.DEVCA7.CL233.LOADLIB                      APCD06  FOUND
APC.DEVCA7.L230.CALLIB                        APCD98  FOUND
APC.DEVCA7.SECLIB                             APCD06  FOUND
APC.DEVCA7.TS04.LOADLIB                      APCD98  FOUND
APC.DEVCA7.TS04.TESTLIB                     APCD98  FOUND
APC.DEVCA7.TS044.CAILIB                     APCD98  FOUND
APC.DEVL232.CAILIB                           APCD10  FOUND
APC.LV1CA7.L29302.LOADLIB                    APCD98  NOT_FOUND
APC.LV1JT.V3R3.P9504.TRACLINK                APCD10  NOT_FOUND
APC.LV2CA7.TEST.CAILIB                      APCD09  NOT_FOUND
APC.LV2CA7.TEST4.CAILIB                    APCD08  NOT_FOUND
APCDAL.L233X.CAILIB                          APCD06  FOUND
APCMTL.CU1B.CHQA.SESFLNK                    APCM06  FOUND

```

Access the LINKLIST Libraries Display

The LINKLIST Libraries display shows you the linklist data sets. Use this information to:

- Identify linklist data sets that have gone into extra extents after the last IPL.
- Identify which linklist data sets are APF-authorized.
- Identify which linklist data sets contain a specific load module.
- Display all duplicated members in more than one linklist data set by using the DUPLICAT command.

To access the display, issue the LINKLIST command.

The sample LINKLIST Libraries display:

```

SYSVIEW LINKLIST ----- LINKLIST Libraries -----
Command ==>                                         Scroll *==> HALF
-----
Jobname SYSVIEW  ASID 007B  Jobid STC02423
Setname LNKLS00      Status CURRENT IPL CHK  Allocations ACTIVE
LLA search available  Extents 168
Libraries 73 Alloc  0 Open  0
-----
Cmd  Dataset-Name                               Xtn Volser APF
----  -----
----  SYS1.LINKLIB                               6 MVR25A APF
----  SYS1.MIGLIB                                5 MVR25A APF
----  SYS1.CSSLIB                                 1 MVR25A APF
----  SYS2.XE44.LINK250                           1 MVCA44 APF
----  SYS2.COMMON.LINK250                         1 MVSP2  APF
----  SYS2.XE44.LINKLIB                           1 MVCA44 APF
----  ISP.SISPLoad                                1 MVR25A APF
----  ISF.SISFLOAD                               12 MVR25A APF
----  SYS1.CMDLIB                                 3 MVR25A APF
----  SYS1.V2R5M0.SHASLINK                       9 MVR25A APF
----  SYS1.V2R5M0.SHASMIG                        2 MVR25A APF
----  NETVIEW.V3R1M0.CNMLINK                     3 MVR25A APF
----  SYS2.OPERA30.P9602                          1 MVSP1  APF
----  SYS2.OP542.P9808B                          5 MVSP2  APF
----  SYS2.TSS50.P9808D.XE44                     1 MVCA44 APF

```

Tasks Performed from the LINKLIST Libraries Display

You can perform the following subcommands from this display. Use of these commands could have dependencies on LLA.

ADD

Add a data set to LINKLIST.

DELETE

Delete a data set from LINKLIST.

REBUILD

Rebuild the linklist DEB (data extended block).

WHERE

Search for a module in the LINKLIST libraries.

Examples: ADD and WHERE Subcommands

1. The ADD subcommand

To add a cataloged data set to the end of the list of LINKLIST data sets, issue this subcommand:

```
ADD dsname
```

dsname

Specifies the name of the data set.

2. The WHERE subcommand

To locate all instances of a module on the LINKLIST Libraries display, issue the following command:

```
WHERE modulename
```

modulename

Specifies the name of the module to locate.

Subsystem Detail Display

The Subsystem display lets you view information about subsystems. You can use this display to determine which subsystems handle certain functions and the entry point address of the module that handles that function.

To access the display, issue the SUBSYS command. You can specify a summary display or a detail display.

The sample Subsystem Detail display:

```

SYSVIEW SUBSYS ----- Subsystem Detail -----
Command ==>>>                               Scroll *==>> HALF
----- Lvl 2 Row 477-493/538 Col 1-79/112
Status:   SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
Subsystems Defined  161 Actual  161
-----
Name SSCT      SSVT      User-1  User-2  Code EPAddr  Region  Module  Offset
SLS0 00C47ECC 0AC180F0 08A39000 20179B2F  4 89A9C4A0 E-CSA   ***NA***
.    .          .          .          .          8 892780F0 E-CSA   ***NA***
.    .          .          .          .          9 88A23028 E-CSA   ***NA***
.    .          .          .          .          10 89026038 E-CSA   ***NA***
.    .          .          .          .          50 89684078 E-CSA   ***NA***
.    .          .          .          .          58 89A9C768 E-CSA   ***NA***
SMS  00C491B0 00C48048 00000000 00000000  8 842E2248 E-PLPA  CMPSTSGI 075248
.    .          .          .          .          15 842E2248 E-PLPA  CMPSTSGI 075248
.    .          .          .          .          16 84444D58 E-PLPA  IGG500PN 00AD58
.    .          .          .          .          17 84441700 E-PLPA  IGG500PN 007700
.    .          .          .          .          55 842E2248 E-PLPA  CMPSTSGI 075248
SPVT 00C495F8 00000000 00000000 00000000
SSTB 00A76178 00000000 09DF7160 00000000
STRB 00C35028 0868F340 0868F000 00000000
SVDM 00C445E4 00000000 00ADA520 00000000
SVPM 00C4462C 00000000 00ADA020 00000000
SYST 00C4459C 00000000 00FA3480 00000000

```

Tasks Performed from the Subsystem Display

You can perform the following subcommands from this display. For detailed information about parameters, see the online help.

ADD

Add a subsystem entry to z/OS.

DELETE

Delete a subsystem entry from z/OS.

Example: Add a Subsystem Entry

To add a subsystem entry, issue the following subcommand:

```
ADD name
```

name

Specifies the subsystem name.

Chapter 5: Job and Output Management

This section contains the following topics:

[About the Job and Output Management Displays](#) (see page 105)

[Job and Output System Activity Display](#) (see page 105)

[Job Summary Display](#) (see page 107)

[Job Queues Display](#) (see page 108)

[Printers Display](#) (see page 110)

[System Log Display](#) (see page 111)

About the Job and Output Management Displays

This chapter describes how you perform some tasks using CA SYSVIEW job and output management displays.

In addition to the displays described in this chapter, you can use many others to do the following tasks:

- View information about jobs
- Perform job management tasks
- Perform output-related tasks

To see a menu of the commands you can use, specify **MENU JES** on the command line.

Note: You can use CA SYSVIEW line commands to perform many tasks on these displays. To see the valid line commands for a display, place your cursor in the line command input area and press the Help PF key.

Job and Output System Activity Display

To access the System Activity display, issue the ACTIVITY command.

This display shows status information about jobs executing on the system. The jobs can be started tasks, TSO users, or batch jobs. The displayed information lets you determine:

- Whether a job is swapped out and why
- The amount of real storage the job is using

- The dispatching priority of a job relative to other jobs
- Whether a job is in a loop

The sample System Activity display:

```

SYSVIEW ACTIVITY ----- System Activity ----- 10:25:20
Command ==>>>                                     Scroll *==>> HALF
-----
(r)  CP% IFA% Pct% ...50..100 -Condition- ---Ready--- --Paging-- -Storage-
CPU  35%  0%  28%             ENQ NoSMF ASIDs  3  Slots 41% ECSA  87%
LCPU 35%  0%  28%             RES NoWTO Tasks  3  Rate  3  ESQA  95%
                                   NoDMP  TAP  ---I/O--- AFQA 10649 SQA  97%
Spool                51%                Rate 27113 UICA 2540 CSA  64%
-----
Formats DEFAULT CPU CPU1 PERF STORAGE
Status  SORT
XSStat  Data NO  Group ALL  MsgLvl ERROR  Limit NONE  RemDup NO  Type SYST
-----
*                ALL                ALL
Cmd Jobname  Stepname Procstep Type  Jobnr Jc Status CPU-Time Limit Clocktime
--- BLADA08  CATSO    A55TG129 TSU   62337 @ LSW   8.985128 3600 01:04:18
--- BLX1PROC  BLX1PROC BLXSPCAS STC   17660 $ NS    0.109452 86400 85:03:33
    
```

Tasks Performed from the System Activity Display

To perform line commands from the System Activity Display, place your cursor in the command input area to the left of the variable.

The following line commands are valid:

C

Cancel a job.

S

Display the job output.

Link-to Command: OUTPUT

L

List the job output files.

Link-to Command: LISTFILE

T

Display tasks for the job.

Link-to Command: TASK

M

Invoke the MENU ADDRSP command.

Link-to Command: MENU

Job Summary Display

To access the Job Summary display, issue the JOBSUM command.

The Job Summary display shows a summary of information about jobs on the JES job queues. This display tells you the type, queue, status, job input class, and spool volume.

The sample Job Summary display:

```

SYSVIEW JOBSUM ----- Job Summary -----
Command ==>                               Scroll *==> HALF
----- Lvl 2 Row 1-16/1998 Col 1-79/328
Status:  SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
Spool space used - 62.95%  Maximum jobs allowed - 5000
-----
*      ALL      ALL  ALL  ALL
Cmd Jobname  Type Jobnr Queue Stat Jobc Prty Posi Spool% Tot-Lines Ccode
___ CHH$IPC9  JOB   2475  OUTP  HLDC M      1      2.37  1456782  0
___ SYSTEM74  JOB   4137  OUTP  HLDC I      1      2.21  847380  U3334
___ QA90MUF4  JOB   3673  OUTP  HLDC D      1      2.19  905079  0
___ GLOED02F  JOB   4663  OUTP  HLDC A      1      2.18  811295  16
___ NETSPY52  JOB   5712  OUTP      M      1      2.13  858767  S222
___ ONETH01E  JOB   5406  OUTP  HLDC B      1      2.12  793355  16
___ FONCR01C  JOB    588  OUTP  HLDC A      1      1.69  629805  S222
___ A021BKWD  JOB   4643  OUTP  HLDC Y      1      1.64  778816  S222
___ QADRAS60  JOB   2133  OUTP  HLDC 3      1      1.42  541641  S222
___ SYSTEM11  STC   3741  OUTP  HLDC $      1      1.33  501196  S978
___ SYSTEM11  STC    120  OUTP  HLDC $      1      1.19  446748  S978
___ SYSTEM07  STC   5025  OUTP  HLDC $      1      1.17  513076  S222
___ SYSTEM11  STC   2990  OUTP  HLDC $      1      1.13  423551  S978
___ NETSPY52  JOB   4536  OUTP      M      1      1.07  417642  0
___ NETSPY52  JOB    784  OUTP      M      1      1.05  417375  0
___ SYSTEM11  STC   1868  OUTP  HLDC $      1      1.03  387792  S978

```

Tasks Performed from the Job Summary Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid:

D

Delete a job.

S

Display the job output.

Link-to Command: OUTPUT

SS

Display information about steps for a job.

Link-to Command: STEPSUM

R

Release a job.

H

Hold a job.

Job Queues Display

To access the Job Queues display, issue the JJOBQUE command.

This display shows information about jobs on the JES job queues.

This display is probably the most comprehensive CA SYSVIEW display for jobs on job queues. The Output Queue display and the Held Output Queue display are less comprehensive, but useful. These displays are, basically, subsets of the Job Queues display. Issue the JOUTQUE and JHELDQUE commands, respectively, to access these displays.

The sample Job Queues display:

```

SYSVIEW JJOBQUE ----- Job Queues -----
Command ==>>>                               Scroll *==>> HALF
----- Lvl 2 Row 12-27/2190 Col 1-79/413
Status:  SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
Total Lines 20,440,040      Total Pages 0
-----

```

Cmd	St-Date	St-Time	Jobnr	Jobname	Queue	Type	Jobc	Prty	Tot-Lines	Outc	Opri
---	11Mar2008	15:36:27	4709	ACOBAA01S	OUTP	JOB	A	1	1967	X	144
---	11Mar2008	13:50:25	4356	ACOBAA01S	OUTP	JOB	A	1	1981	X	144
---	11Mar2008	13:22:07	4255	ACOBAA01S	OUTP	JOB	A	1	1970	X	144
---	11Mar2008	11:10:11	3931	ADAMP1	EXEC	JOB	3	11			
---	11Mar2008	10:22:36	3665	AJNL0027	OUTP	JOB	Y	1	145	Y	144
---	10Mar2008	19:44:57	1154	AJNL0074	OUTP	JOB	Y	1	133	X	144
---	09Mar2008	10:45:06	738	AJNL0105	OUTP	JOB	Y	1	157	A	144
---	09Mar2008	10:15:01	654	AJNL0105	OUTP	JOB	Y	1	158	A	144
---			2207	ALEDA01B	INP	JOB	X	11			
---	12Mar2008	02:39:04	5318	ANDNI02	EXEC	TSU	@	15			
---	12Mar2008	02:39:04	5318	.	OUTP	TSU	@	15	40279	D	96
---	11Mar2008	16:28:30	4884	ANDNI02D	OUTP	JOB	A	1	76	X	144
---	11Mar2008	16:28:30	4884	.	OUTP	JOB	A	1	3	Y	144
---	11Mar2008	16:05:52	4816	ANDNI02D	OUTP	JOB	A	1	76	X	144
---	11Mar2008	16:05:52	4816	.	OUTP	JOB	A	1	3	Y	144
---	11Mar2008	15:23:00	4668	ANDNI02D	OUTP	JOB	A	1	76	X	144

Tasks Performed from the Job Queues Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid:

D

Delete output.

S

Display output.

Link-to Command: OUTPUT

L

List output files.

Link-to Command: LISTFILE

R

Release output or a job.

Printers Display

To access the Printers display, issue the PRINTER command.

This display shows the status of local and remote JES printers. If a job is printing, the Printers display also shows information about the job.

The sample Printers display:

```

SYSVIEW PRINTER ----- Printers -----
Command ==>                               Scroll *==> HALF
----- Lvl 2 Row 1-17/20 Col 1-79/577
Status:  SORT NOSELECT NODEST NOPREFIX NOOWNER NOUPDATE
-----
      *      ALL
Cmd  Device  Status  Devn Jobname  Jobnr Programmer Lines-Prt Tot-Lines Fcnt
----  -----  -----  ----  -
PRT1  DRAINED  001E
PRT10 DRAINED  FSS
PRT2  DRAINED  FSS
PRT33 DRAINED  FSS
PRT66 DRAINED  FSS
PRT67 DRAINED  FSS
PRT76 DRAINED  FSS
PRT77 DRAINED  FSS
PRT88 DRAINED  FSS
PRT90 DRAINED  FSS
PRT91 DRAINED  FSS
PRT92 DRAINED  FSS
PRT93 DRAINED  FSS
PRT94 DRAINED  FSS
PRT95 DRAINED  FSS
PRT96 DRAINED  FSS
PRT97 DRAINED  FSS

```

Tasks Performed from the Printers Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid:

C

Cancel the output.

S

Start the printer.

P

Stop the printer.

System Log Display

To access the System Log display, issue the SYSLOG command.

This display shows the MVS system log data set. This display takes all SYSLOG output files on the JES spool and logically combines them. To view a system log, specify the JES system ID of the SYSLOG you want to display on the SYSLOG command. By default, the current system log is displayed.

The sample System Log display:

```

SYSVIEW SYSLOG ----- System Log for XE44 -----
Command ==>                                     Scroll *==> HALF
----- Lvl 2 Row 76234-76252/76289 Col 37-115/126
Date 12Mar2008 Time 09:12:49
-----
          00000214 IEA989I SLIP TRAP ID=X33E MATCHED. JOBNAME=*UNAVAIL, ASID=
          00000010 TSS7100E 009 J=HARCA06 A=HARCA06 T=A01TD023 F=TSO - Incorre
STC05315 00000010 R05120I: LINE 015 ONCHI01                A55TG010 <SIGNOFF>
STC05315 00000010 RCS012I: ROSCOE /A55TG010: SUCCESSFUL DISCONNECT <VTAM>
TSU05502 00000210 IEA630I OPERATOR SOUAY01 NOW ACTIVE,  SYSTEM=XE44    , L
SOUAY01  00000210 $TOJ5744,OUTGRP=1.1.1,C=6683,T=GT15
JOB00922 00000010 $HASP308 CICS4IDS ESTIMATED TIME EXCEEDED BY 2280 MINUTES
JOB05744 00000010 $HASP686 OUTPUT(SOUAY01B) 992
          992 00000010 $HASP686 OUTPUT(SOUAY01B)  OUTGRP=1.1.1,BURST=NO,FCB=6683,
          992 00000010 $HASP686                    FLASH=***,FORMS=STD,HOLD=(NONE)
          992 00000010 $HASP686                    OUTDISP=WRITE,PRIORITY=128,
          992 00000010 $HASP686                    PRMODE=LINE,QUEUE=A,
          992 00000010 $HASP686                    RECORDS=(2866 OF 2866),
          992 00000010 $HASP686                    ROUTECDE=LOCAL,SECLABEL=,TSOAVAI
          992 00000010 $HASP686                    UCS=GT15,USERID=SOUAY01,WRITER=
STC03491 00000010 CAS9899W - USILEP05 (141.202.133.43:1721) not available...w
JOB05781 00000010 @48 REPLY WITH REQUEST TO IDMS V74
JOB00789 00000010 *42 REPLY WITH REQUEST TO DS60 V1
JOB05728 00000010 @41 REPLY WITH REQUEST TO IDMS V71

```

Tasks Performed from the System Log Display

The System Log display lets you locate a time, date, or both in the log. To do so, issue the LOCATE subcommand in the following format:

```
LOCATE [hh:mm:ss] [,<date>]
```

hh:mm:ss

This variable specifies the time to locate in *hh:mm:ss* format.

***hh* (optional)**

Values are 00-23.

***mm* (optional)**

Values are 00-59.

ss

Values are 00-59.

The default is 00:00:00.

Note: You can use a period instead of a colon to separate the *hh*, *mm*, and *ss* values.

<date>

This variable specifies the date to locate in the user date format. The default is the current displayed date. Because the user date format can vary widely, the full date must be entered.

For example, to locate ten a.m. on March 17 2013, and the user date format is set to mm/dd/yy, issue the following command:

```
LOCATE 10 03/18/13
```


Chapter 6: System Overview Displays

This section contains the following topics:

[About the System Overview Displays](#) (see page 113)

[Accessing and Controlling the Displays](#) (see page 113)

[System Overview Data](#) (see page 118)

About the System Overview Displays

This chapter describes some representative displays for the System Overview component. The information section of a CA SYSVIEW command or menu can display an overview of a select group of metrics and conditions of your system.

Accessing and Controlling the Displays

You can access the System Overview Menu from the Primary Option Menu or by typing the command Menu Overview from any SYSVIEW menu or command.

System Overview Menu

The following sample menu demonstrates the information section in full format displaying real-time data and a few available options:

Equation 1: This sample menu shows the full System Overview information section.

```

TPX55
File Edit View Communication Actions Window Help

SYSVIEW MENU ----- System Overview Menu ----- 11:00:54
Option ==>>> |
                                           Scroll *==> HALF
                                           Lvl 2 Row 1-14/22
-----
(r)  CP%  IFA%  Pct%  . . 50 . 100  -Condition-  ---Ready---  --Paging--  -Storage-
CPU  100%  3%   81%  [ ]          ENQ  NoSMF  ASIDs  6     Slots  43%  ECSA  87%
LCPU 94%   2%   75%  [ ]          RES  NoWTO  Tasks  10    Rate   94   ESQA  95%
                                           NoDMP  TAP    -----I/O-----
                                           Rate  16472  AFQA  37144  SQA   97%
                                           UICA  1387   CSA   64%
-----
Option Description
- 1  Menu - System status
- 2  Menu - Job resource usage overview
- 3  Menu - Operations
- 4  Menu - Overview resource plots
- 5  Menu - DISPLAY commands

- 6  System Condition Monitor
- 7  Multi system resource overview
- 8  MVS exception alerts
- 9  Job activity summary
- 10 Jobs exceeding resource usage thresholds
- 11 CPU usage by job
- 12 I/O usage by job
- 13 Job degradation delay analysis
    
```

Displaying the Information Lines

Using the commands PROFILE or SET, users can control the following System Overview options and characteristics for each command:

- Whether the information area is displayed
- Whether the format of the information area is displayed in a full or short format
- Whether the type of information is real time or interval

SET Keywords

The following available SET keywords let you control the display of the information lines:

OVERView

Controls the display of the system overview information lines.

Valid Values: YES or ON and NO or OFF.

Default: NO or OFF

For example:

```
set overview yes
```

If you turn the SET command parameter IMPLICITSET to yes, you can switch the OVERVIEW between yes and no.

```
set implicitset yes
```

OVERVIEWFmt or OVERFmt

Controls the format of the system overview information lines when the Overview option is set to Yes.

Valid Values: LONG or SHORT. FULL can also be specified and is a synonym for LONG.

Default: LONG

OVERVIEWType or OVERType

Controls the type of displayed data in the system overview information lines when the Overview option is set to Yes.

Valid Values: REALTIME or INTERVAL.

Default: REALTIME

OVERVIEWDivl or OVERDivline

Controls the display of a divider line following the system overview information lines when the Overview option is set to Yes.

Valid Values: Yes or On and No or Off.

Default: Yes

Sample Displays

The following screens show the information area in both the long format and the short format of the Activity command display.

- Short Format

The following sample display shows the short format of the information area, which displays when you specify SET OVERVIEWFMT SHORT:


```

TPX55
File Edit View Communication Actions Window Help

SYSVIEW ACTIVITY ----- System Activity ----- 11:02:00
Command =====> |
                                           Scroll *==> HALF
----- Lvl 3 Row 13-24/787 Col 1-79/484
CPU LCPU ASIDs Tasks IORate Spool Slots Page AFQA UICA CSA ECSA SQA ESQA
80% 68% 19 26 1797 51% 43% 19 33925 1600 64% 87% 97% 95%
-----
Formats DEFAULT CPU CPU1 PERF STORAGE
Status SORT
XSStat Data NO Group ALL MsgLvl ERROR Limit NONE RemDup NO Type SYST
-----
*
ALL ALL
Cmd Jobname Stepname Procstep Type Jobnr Jc Status CPU-Time Limit Clocktime
___ ADAMI03 CATSO A55TG128 TSU 62320 @ LSW 2.051983 3600 01:42:00
___ ADAMP76 DBID076 $$$$$$@ JOB 26301 D NS 1.398799 86400 54:30:49
___ ADKSTA1 CATSO A55TG020 TSU 60805 @ LSW 6.149453 3600 03:38:31
___ ADKST01 CATSO A55TG056 TSU 60825 @ LSW 8.103516 3600 03:36:01
___ AD11STRT $$$@NX@ JOB 43916 C NS 00:01:13 86400 26:27:05
___ ALLOCAS ALLOCAS SYS NS 5.843304 85:45:14
___ ANTAS000 ANTAS000 IEFPROC STC NS 10.46084 86400 85:45:07
___ ANTMAIN ANTMAIN IEFPROC SYS NS 2.560511 86400 85:45:12
___ APCSRV22 APCSRV22 APCSRVR STC 62687 $ LSW 0.380367 86400 01:21:07
___ APCSRV22 APCSRV22 APCSRVR STC 18128 $ IN 21.38245 86400 82:51:43
___ APCSRV22 APCSRV22 APCSRVR STC 46842 $ LSW 7.904607 86400 23:52:23
___ APPC APPC APPC STC NS 14.39662 86400 85:39:34
    
```

- Long Format

The following sample display shows the information area set back to the long format, which displays when you specify SET OVERVIEWFMT LONG:



Screen Attributes

Users can define and control their screen color, reverse video, highlighting, and so on. To display and set these screen attributes, use the SCREEN command.

Review the following areas of the screen attribute of the OVERVIEW information section:

Headers

The screen attribute name is HEADER.

Text

The screen attribute name is INFO.

Conditions

Specifies the screen attribute that is based on the status of the condition, as follows:

- Condition is false - INFO
- Condition is true - CONDHI

Bar graphs

Specifies an attribute that is based on the threshold definition (if any), as follows:

- BARGRAPH - No threshold defined
- BARNORMAL - Evaluated status - NORMAL
- BARWARNING - Evaluated status - WARNING
- BARPROBLEM - Evaluated status - PROBLEM

Metrics and Values

Specifies the metric and value attributes that are based on the threshold definition (if any), as follows:

- INFO - No threshold defined
- CONDNORMAL - Evaluated status - NORMAL
- CONDWARNING - Evaluated status - WARNING
- CONDPROBLEM - Evaluated status - PROBLEM

System Overview Data

The System Overview data is displayed in fields that are associated with the following information areas:

- Graph
- Condition
- Ready
- I/O
- Paging
- Common

These information areas and their fields are described in the following sections.

Graph Fields

The following fields show the usage percentage of your system:

(r)

Indicates that the information is being displayed in real-time mode.

(i)

Indicates that the information is being displayed using collected interval data.

CPU

Specifies the processor busy percentage from the operating system point of view.

LCPU

Specifies the processor busy percentage from the LPAR point of view.

Spool

Indicates the percentage of spool space used. This percentage is in relation to the total number of spool track groups that are defined to JES.

Condition Fields

The following fields display the condition of your system:

ENQ|NoENQ

Indicates whether enqueue conflicts currently exist.

RES|NoRES

Indicates whether enqueue reserves currently exist.

DMP|NoDMP

Indicates whether a dump data set is in use.

SMF|NoSMF

Indicates whether a potential problem with SMF exists, such as:

- SMF not active
- SMF data lost
- SMF buffering records
- Dump required for one or more SMF data sets

WTO|NoWTO

Indicates whether a potential WTO problem exists, such as:

- A message backlog exists
- WTO buffer shortage

TAP|NoTAP

Indicates whether a tape mount is pending.

Ready Fields

The following fields display the number of jobs that are ready to be dispatched:

ASIDs

Specifies the number of address spaces that have one or more tasks ready to be dispatched.

Tasks

Specifies the number of tasks ready to be dispatched.

I/O Fields

This field displays the I/O rates:

Rate

Specifies the overall start I/O rate for the system, expressed as the number of start I/Os per second.

Paging Fields

The following fields display the paging information:

Slots

Specifies the percent of local page data set slots in use.

Rate

Specifies the overall paging rate for the system, expressed as the number of pages per second.

AFQA

Specifies the available frame queue average.

UICA

Specifies the unreferenced interval count average.

Common Fields

The following fields display the percentage of used common storage and queue areas:

ECSA

Displays the percentage of currently used Extended Common Storage Area.

ESQA

Displays the percentage of currently used Extended System Queue Area.

SQA

Displays the percentage of currently used System Queue Area.

CSA

Displays the percentage of currently used Common Storage Area.

Chapter 7: UNIX System Services Displays

This section contains the following topics:

- [About the USS Displays](#) (see page 123)
- [USS Address Space List Display](#) (see page 123)
- [USS Mounted File Systems Display](#) (see page 125)
- [System Configuration Options Display](#) (see page 126)

About the USS Displays

This chapter describes representative UNIX System Services displays and some tasks you can perform on them.

In addition to the displays described in this chapter, there are many other USS resource displays. To see a menu of the commands you can use, specify MENU USS on the command line. You can use these commands to monitor and manage USS resources.

Note: You can use CA SYSVIEW line commands to perform many tasks on these displays. To see the valid line commands for a display, place your cursor in the line command input area and press the Help PF key.

USS Address Space List Display

To access the USS Address Space List display, issue the USSLIST command.

This display shows you information about address spaces that contain USS processes.

The following display is a sample USS Address Space List.

```
SYSVIEW USSLIST ----- USS Address Space List -----
Command ==>                                     Scroll *==> HALF
----- Lvl 3 Row 1-18/67 Col 1-79/219
Jobname SYSVIEW  ASID 0078  Jobid STC01358
-----
Cmd           Jobnr Jobname  Stepname Procstep Type Jc Status  PrcCt ThrCt
-----
1270 AOPD     STEP1           OTX $  NS      1    5
1279 FTPD441  STEP1           OTX $  OUT DW   1    1
1271 INETD8   STEP1           OTX $  OUT DW   1    1
           OPSUSS  OPSP002B OPSP   STC   OUT DW   1    1
           OPSUSS  OPSP002C OPSP   STC   OUT DW   1    1
1269 OPSUSS1  STEP1           OTX $  OUT DW   1    1
```

This second screen shows the fields that you see when you scroll to the right:

```

SYSVIEW USSLIST ----- USS Address Space List -----
Command ==>                                         Scroll *==> HALF
----- Lvl 3 Row 1-18/67 Col 1-32&84-130/219
Jobname SYSVIEW  ASID 0078  Jobid STC01358
-----
Cmd           Jobnr Jobname |UserTime  SysTime  TotlTime  SysCl  FilRd  FilWr
-----
1270 AOPD      0.200    0.060    0.260    289   446    1
1279 FTPD441   0.220    0.070    0.290    181   12     1
1271 INETD8    0.020    0.000    0.020    28    4     1
          OPSUSS  0.030    0.010    0.040    8
          OPSUSS  0.030    0.010    0.040    8
1269 OPSUSS1   0.030    0.010    0.040    16   31
  
```

Tasks Performed from the USS Address Space List Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Select

Switch to the selected ASID.

Link-to Command: USS

Process or UProcess

Display the processes for the selected address space.

Link-to Command: UPROCESS

Threads or UThreads

Display the threads for the selected address space.

Link-to Command: UTHREADS

Files or UFiles

Display the open USS files for the selected address space.

Link-to Command: UFILES

USS Mounted File Systems Display

The USS Mounted File System display shows you information about mounted USS file systems.

To access this display, Issue the UFILESYS command.

The sample USS Mounted File Systems display:

```

SYSVIEW 12.0b CA31 ----- UFILESYS, USS Mounted File Systems ----- 2008/06/12 07:11:08
Command =====>                                           Scroll *====> PAGE
----- Lvl 3 Row 1-4/4 Col 1-54&100-176/388
Formats DEFAULT ZFS
Status NoSRT NoLIM  SEL NoDST NoPFX NoOWN NoUPD NoPRT NoCAP
-----
Cmd      AggregateName                |Type   Status  Mode ISUId   BpSec DevNo PDevN   Blocks Used  ....+....5.
-----
OMVS.OMLVL2.CA31.ZFS                ZFS    ACTIVE  R/W    0        0   35    8       3600 33%
OMVSSYS.WAS61.CONFIG.B61A.ZFS      ZFS    ACTIVE  R/W    0        0  121    7      302400 48%
OMVSSYS.WAS61.CONFIG.B61B.ZFS      ZFS    ACTIVE  R/W    0        0  119    7      302400 47%
OMVSSYS.WAS61.CONFIG.B61G.ZFS      ZFS    ACTIVE  R/W    0        0  124    7      328320 48%
***** End of Data *****

```

Tasks Performed from the USS Mounted File Systems Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Select

Select the file system detail display.

ULISTDir, ULS, Ls, or Ld

List the mount point directory of the file system.

Link-to Command: ULISTDIR

UDIRTree, DIRTree, or DT

Display the mount point of the selected file system using the FILESYS keyword.

Link-to Command: UDIRTREE

Dsinfo or Info

Display the file system name.

Link-to Command: DSINFO

LISTCat or LCat

Display the file system name.

Link-to Command: LISTCAT

System Configuration Options Display

To access the System Configuration Options display, issue the USYSCONF command.

The following sample System Configuration Options display shows you USS system configuration options:

```

SYSVIEW USYSCONF----- USS System Configuration Options -----
Command ==>                                         Scroll *==> HALF
----- Lvl 3 Row 1-18/29
Parmlib member BPXPRM00
-----
Description          Parameter          Value
Storage copy option on fork call FORKCOPY          COPY
Max message queues   IPCMSGNIDS        500
Max message queue bytes IPCMSGQBYTES      262144
Max messages per queue IPCMSGQNUM        10000
Max semaphore sets   IPCSEMNIDS        500
Max operations per semaphore cal IPCSEMNOPS        25
Max semaphores per semaphore set IPCSEMNSEMS       25
Max pages for one shared mem seg IPCSHMMPAGES      256
Max shared memory segments IPCSHMNIDS        500
Max shared mem seg per addrspc IPCSHMNSEGS       10
Max pages for all shared mem seg IPCSHMSPAGES      262144
Max address space region size MAXASSIZE         41943040
Max core dump file size MAXCORESIZE       4194304
Max cpu time in seconds MAXCPUIME         1000
Max files per process MAXFILEPROC       256
Max file size        MAXFILESIZE       NOLIMIT
Max memory mapped file pages MAXMMAPAREA       4096
Max processes in the system MAXPROCSYS        125
    
```

Chapter 8: CICS Displays

This section contains the following topics:

[About the CICS Displays](#) (see page 127)

[CICS System Activity Display](#) (see page 127)

[CICS Active Tasks Display](#) (see page 129)

[CICS Dynamic Storage Areas Display](#) (see page 130)

[Transaction Log Display](#) (see page 132)

[CICS Degradation Analysis Display](#) (see page 133)

About the CICS Displays

This chapter describes some representative CICS resource displays and some tasks you can perform on them.

In addition to the displays described in this chapter, you can use many others to view CICS resource displays. To see menus of the commands you can use, specify MENU CICS on the command line. This menu contains other menus that let you view different types of information, such as:

- Status
- Storage
- Subsystems
- Transactions
- Domains
- Journals

CICS System Activity Display

To access the CICS System Activity display, issue the CICSLIST command.

This display shows you information about CICS address spaces that are currently being monitored. You also see CICS address spaces that are currently inactive but have been monitored during the current IPL.

The sample CICS System Activity display:

```

SYSVIEW  -----CICSLIST, CICS System Activity -----
Command ==>>>                                     Scroll *==>>> PAGE
----- Lvl 2 Row 1-5/5 Col 1-79/192
Jobname SYSVIEW  ASID 0051  Jobid STC01321  CICS n/a  SSID GSVX
-----
Cmd  Name      Status  JobStat  Job-CPU  RealStg  Trans  IOReqs  CPUtime  Lifetime
-----
_____ CACTUSA  ACTIVE  NS       00:14:49  1.51M  4094  58261  0.055  0.611
_____ CICSPMP6  ACTIVE  IN       00:38:16  11.5M  23646  143k   0.001  3.481
_____ CICSPMP9  ACTIVE  IN       00:37:35  14.8M  11919  71772  0.001  15.740
_____ CICSPQA5  ACTIVE  IN       00:09:44  2.74M  7586  30704  0.001  10.619
_____ PAQMC520  ACTIVE  IN       00:03:01  2.14M  8480  89475  0.006  0.050
===== End of Data =====

```

Tasks Performed from the CICS System Activity Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

DSAs

Display a list of the Dynamic Storage Areas in use.

Link-to Command: CDSAS

LISTFILE and LF

List spool files for the selected CICS job name.

Link-to Command: LISTFILE

LOGs

List history data collection logs for the selected job name and SSID.

Link-to Command: LGLOGS

REVIEW

Display an hourly breakdown of transaction activity.

Link-to Command: CREVIEW

Select

Select the CICS address space for future use in displays. The currently selected address space is displayed in the information section.

Example:

Jobname CICSPROD ASID 0039

Link-to Command: ASID

Tasks

List the active and suspended transactions.

Link-to Command: CTASKS

CICS Active Tasks Display

To access the CICS Active Tasks display, issue the CTASKS command.

This display provides information about CICS active and suspended tasks, for the current address space or for all CICS address spaces currently being monitored.

The sample CICS Active Tasks display:

```

SYSVIEW CTASKS ----- CICS Active Tasks -----
Command ==>
                                           Scroll *==> HALF
----- Lvl 2 Row 1-13/13 Col 1-79/398
Jobname SYSVC530 ASID 01A0 Jobid STC04215 CICS TS3.2 Mode LOCAL SSID GSVX
           Current High Limit AtLimit           CPU Paging IORate TranRate
Max Tasks           4   4   32   0 Job  0.13% 0.133 3.067 1.433
                               MVS   11%   19   335
-----
Cmd A Tran  Task# Program  Term WaitType WaitName           CPUTime Lifetime
----  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -  -
----  CSHQ   22 DFHSHSY   SHSYSTEM           0.090
----  CSSY    6 DFHAPATT  ICEXPIRY DFHAPTIX         0.004
----  CSTP    8 DFHZCSTP  TCP_NORM DFHZDSP         2.148
----  CSOL    3 DFHSOL   SODOMAIN SO_NOWORK  0.018
----  CSNE   23 DFHZNAC   ZC DFHZNAC1         0.007
----  CEMT   222 DFHEMTD  U015 ZCIOWAIT DFHZARQ1           00:05:34
----  > SYSV  375 GSVXCICS U036 EKWAIT  SINGLE           0.001 0.003
----  CEBR   225 DFHEDFBR U037 ZCIOWAIT DFHZARQ1           00:05:27
----  XPFI   25 XC53INIT  XPFC REQUESTS         0.238
----  CFQR   20 DFHFCQT   FCCFQR           0.001
----  CSNC   21 DFHCRNP   CSNC MROQUEUE         0.003
----  CFQS   19 DFHFCQT   FCCFQS           0.007

```

Tasks Performed from the CICS Active Tasks Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Cancel

 Cancels the selected transaction.

Enqueue and NQ

 Displays the enqueues that the selected transaction owns or is waiting on.

Link-to Command: CENQUEUE

Kill

 Kills (cancels) the selected looping transaction.

Select

 Displays detailed transaction information.

SUBpools

 Displays the CSUBPOOL command. The subpools that the selected task owns are displayed.

Link-to Command: CSUBPOOL

CICS Dynamic Storage Areas Display

To access the CICS Dynamic Storage Areas display, issue the CDSAS command.

This display shows you information about each Dynamic Storage Area that CICS defined.

The sample CICS Dynamic Storage Areas display:

```

SYSVIEW CDSAS ----- CICS Dynamic Storage Areas -----
Command ==>                                         Scroll *==> PAGE
----- Lvl 2 Row 1-8/8 Col 1-79/241
Jobname PAQMC520 ASID 00DE Jobid JOB06244 CICS TS3.2
Storage protection is INACTIVE
Region  User  Sys Alloc Free  PctS  Size  PctL Limit High  SOS
DSA          820K 716K  53%  1.5M  16%   5M  1.5M
EDSA         6.64M 2.36M  74%   9M   33%  20M   9M
PVT          5.36M 400K 5.75M 720K  64% 8.98M 88% 6.06M
E-PVT        23.4M 9.61M  33M 104M   2% 1.84G  18% 128M
-----
Cmd DSAname  Size Alloc  Free MFree  SOS Queued Used  ...20...40...60...80...100
--- UDSA      256K  488K  256K  256K      0%
--- CDSA      512K  488K   24K   8K      95%
--- SDSA      256K   16K  240K  240K     6%
--- RDSA      512K  316K  196K  124K    62%
--- ECDSA      3M  2.2M  820K  788K    73%
--- EUDSA      1M           1M   1M     0%
--- ESDSA      1M           1M   1M     0%
--- ERDSA      5M  4.44M  576K  500K    89%

```

Tasks Performed from the CICS Dynamic Storage Areas Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Elements

Display a list of allocated storage blocks.

Link-to Command: CELEMENT

Plot

Display the DSA percentage full.

Link-to Command: PLOT

PRograms

Display a list of programs that are loaded in the selected DSA.

Link-to Command: CPROGRAM

Subpools

Display a list of allocated subpools.

Link-to Command: CSUBPOOL

Xtents

Display the Dynamic Storage Area Extents.

Link-to Command: CDSAX

Transaction Log Display

To access the Transaction Log display, issue the CTRANLOG command.

This display shows you CICS transaction records.

The sample Transaction Log display:

```

SYSVIEW CA31 ----- CTRANLOG, Transaction Log ----- 03/20/08 15:22:32
Command ==>
----- Lvl 2 Row 4987-4999/5000 Col 1-79/226
Status NoSRT NoLIM NoSEL NoDST NoPFX NoOWN NoUPD NoPRT NoCAP
LogStream SYSVIEW.CICSLOGR.TRAN.XX99 Retention 2 days
Available 22:21:02 01/06/08 to 15:09:19 03/20/08
Displayed 12:09:47 02/27/08 to 15:09:19 03/20/08
-----
Cmd Jobname Date Time Tran Task# Term Userid Lifetime CPUTime
A44ICCS8 03/20/08 11:42:18 CWBG 68 CICSUSER 0.893456 0.000576
A44ICB18 03/20/08 12:00:34 CSOL 3 CICSUSER 00:31:27 0.000720
A44ICB18 03/20/08 12:32:01 CSOL 3 CICSUSER 00:31:27 0.000480
A44ICB18 03/20/08 12:42:18 CWBG 74 CICSUSER 0.960104 0.000672
A44ICCS8 03/20/08 12:42:20 CWBG 69 CICSUSER 0.986021 0.000688
A44ICB18 03/20/08 13:03:29 CSOL 3 CICSUSER 00:31:27 0.000720
A44ICB18 03/20/08 13:34:56 CSOL 3 CICSUSER 00:31:27 0.000624
A44ICB18 03/20/08 13:42:19 CWBG 75 CICSUSER 0.789768 0.000624
A44ICCS8 03/20/08 13:42:20 CWBG 70 CICSUSER 0.865847 0.000624
A44ICB18 03/20/08 14:06:24 CSOL 3 CICSUSER 00:31:27 0.000432
A44ICB18 03/20/08 14:37:51 CSOL 3 CICSUSER 00:31:27 0.000624
A44ICB18 03/20/08 14:42:20 CWBG 76 CICSUSER 0.806204 0.000624
A44ICCS8 03/20/08 14:42:22 CWBG 71 CICSUSER 0.852687 0.000624

```

Tasks Performed from the Transaction Log Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Select

Display the detail screen for a record.

CICS Degradation Analysis Display

To access the CICS Degradation Analysis display, issue the CWAITS command.

This display shows you a degradation analysis graph that summarizes the time CICS spent on various resources.

The sample CICS Degradation Analysis display:

```

SYSVIEW CWAITS ----- CICS Degradation Analysis -----
Command ==>                                                    Scroll *==> PAGE
----- Lvl 2 Row 1-11/11
Jobname PAQMC520  ASID 00DE  Jobid JOB06244  CICS TS3.2
      CPU Paging IORate TranRate Transactions
Job   0.03%      0.533   0.067      8,529
MVS   94%       2    1350
-----
Resource                Total  Average Pct% ...20...40...60...80..100
Transaction life time    00:07:10  0.050 100% *****
Dispatch time           00:01:30  0.011 21% *****
CPU time                 50.364  0.006 12% ***
Program control load wait 1.470    <1%
Suspend time            00:05:38  0.040 79% *****
Dispatch delay           10.160  0.001 2% *
File control wait        00:05:26  0.038 76% *****
Lock manager delay time  0.888    <1%
Syncpoint time           1.998    <1%
Waiting to run           00:01:27  0.010 20% *****
I/O count                87875    10

```


Chapter 9: WebSphere MQ Displays

This section contains the following topics:

- [About the MQ Displays](#) (see page 135)
- [MQ Subsystem List Display](#) (see page 135)
- [MQ Exception Alerts Display](#) (see page 137)
- [MQ Channel Status Display](#) (see page 138)
- [MQ Local Queues Display](#) (see page 139)
- [MQ Queue Manager Display](#) (see page 141)

About the MQ Displays

This chapter describes some representative WebSphere MQ resource displays and some tasks you can perform on them.

In addition to the displays described in this chapter, there are many other MQ resource displays. To see menus of the commands you can use, specify MENU MQSERIES on the command line. This menu contains other menus that let you view different types of information, such as:

- MQ queue managers
- Queues
- Channels
- Processes
- Page sets

MQ Subsystem List Display

To access the MQ Subsystem List display, issue the MQLIST command.

This display shows you information about defined MQ subsystems.

The sample MQ Subsystem List display:

```

SYSVIEW ----- MQLIST, MQ Subsystem List -----
Command ==>                                     Scroll *==> PAGE
----- Lvl 2 Row 1-3/3 Col 1-79/251
Jobname CSQ5MSTR  ASID 0284  Jobid STC61678  MQ 6.0   Qmgr CSQ5
-----
Cmd          Qmgr Status  ChInit  Mon  Job-CPU RealStg IOReqs Clocktime
-----
          CSQ3 ACTIVE  ACTIVE   2.533079  45.6M  2712  00:02:27
          CSQ4 ACTIVE  ACTIVE   1.692717  14.9M  1605  00:02:44
          CSQ5 ACTIVE  ACTIVE   5.068565  4.86M  5146  05:08:20
  
```

Tasks Performed from the MQ Subsystem List Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Output

Displays the output for the selected queue manager.

Link-to Command: OUTPUT

Select

Sets the selected queue manager as target MQ queue manager.

Link-to Command: MQSERIES

STArt *kwd*

Issues the START command indicated by the keyword specified.

Valid Keyword:

- **Chinit** - Issues the START CHINIT command

If the keyword is omitted, a START QMGR command is issued.

STOp *kwd*

Issues the STOP command indicated by the keyword specified.

Valid Keywords:

- **Quiesce** - Issues the STOP QMGR MODE(QUIESCE) command
- **Force** - Issues the STOP QMGR MODE(FORCE) command
- **Restart** - Issues the STOP QMGR MODE(RESTART) command
- **Chinit** - Issues the STOP CHINIT command

If the keyword is omitted, a STOP QMGR command is issued.

MQ Exception Alerts Display

To access the MQ Exception Alerts display, issue the MQALERTS command.

This display shows you information about MQ data collection exception alerts. If the current value exceeds a threshold definition, the data collection value is displayed. You can display alerts for both problem and warning thresholds.

The sample MQ Exception Alerts display:

```

SYSVIEW MQALERTS ----- MQ Exception Alerts -----
Command ==>                               Scroll *==> HALF
----- Lvl 2 Row 1-5/5 Col 1-79/252 -----
Cmd Name   QMgr  Argument                               Value  Status
--- MQQDEPTH CSQ1  CSQ1.GSVSMQSR.B1F406759B47D800        2403  PROBLEM
--- .        CSQ1  CSQ1.GSVSMQSR.B1F414871FA9DA00        1528  PROBLEM
--- .        CSQ1  SYSTEM.ADMIN.QMGR.FWD                 344   PROBLEM
--- .        CSQ2  SYSTEM.ADMIN.CHANNEL.FWD              295   PROBLEM
--- .        CSQ2  SYSTEM.ADMIN.QMGR.FWD                 373   PROBLEM

```

Tasks Performed from the MQ Exception Alerts Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Select

Dynamically provide more information about the selected data element using the PLOT or CLIST command. If a member for this variable has been defined in the CLISTLIB, the CLIST command is executed. If a member name does not exist, the PLOT command is executed.

Link-to Command: PLOT or CLIST

Plot

Display a graph of performance data for the selected data element.

Link-to Command: PLOT

CList

Issue the CLIST command for the selected data element.

Link-to Command: CLIST

Thresh

Display threshold information for the selected variable name.

Link-to Command: MQTHRESH

Variable

Display a variable definition for the selected variable name.

Link-to Command: MQVARS

MQ Channel Status Display

To access the MQ Channel Status display, issue the MQCHSTAT command.

This display provides you with the status of MQ channels.

The sample MQ Channel Status display:

```

SYSVIEW ----- MQCHSTAT, MQ Channel Status -----
Command ==>>>                                     Scroll *==>>> PAGE
----- Lvl 2 Row 17-33/33 Col 1-79/767
Formats DEFAULT COMMON COMPRESS CONNECT MONITOR SSL STATUS
Jobname CSQ5MSTR ASID 0284 Jobid STC61678 MQ 6.0 Qmgr CSQ5
-----
Cmd      Channel          ChlType  Status   SubState  ConName
-----
_____ CSQ5.TO.CSQ4          SDR      INACTIVE
_____ CSQ5.TO.S31Q         SDR      INACTIVE
_____ MQECOLL.CSQ5         RCVR     INACTIVE
_____ MQSRV2.CSQ5         RCVR     INACTIVE
_____ SYSTEM.ADMIN.SVRCONN SVRCONN  INACTIVE
_____ SYSTEM.AUTO.RECEIVER RCVR     INACTIVE
_____ SYSTEM.AUTO.SVRCONN SVRCONN  INACTIVE
_____ SYSTEM.DEF.CLUSRCVR CLUSRCVR INACTIVE
_____ SYSTEM.DEF.CLUSSDR CLUSSDR  INACTIVE
_____ SYSTEM.DEF.RECEIVER RCVR     INACTIVE
_____ SYSTEM.DEF.REQUESTER RQSTR   INACTIVE
_____ SYSTEM.DEF.SENDER   SDR      INACTIVE
_____ SYSTEM.DEF.SERVER   SVR      INACTIVE
_____ SYSTEM.DEF.SVRCONN  SVRCONN  RUNNING  RECEIVE   ::ffff:168.192.0
_____ S31Q.TO.CSQ5         RCVR     INACTIVE
_____ TO.CSQ3.CLUSTERS    CLUSSDR  RETRYING OTHER      168.192.0.100(44
_____ TO.CSQ5.CLUSTERS    CLUSRCVR RUNNING  RECEIVE   ::ffff:168.192.0

```

Tasks Performed from the MQ Channel Status Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

List

Invoke the appropriate MQCHxxxx command to list the details of all channels of the selected channel type.

Link-to Command: MQCHxxxx

RESet

Issue a RESET CHANNEL command for the channel.

Select or Alter

Invoke the MQALTER command to display and alter the attributes of the selected channel.

Link-to Command: MQALTER

STArt

Issue a START CHANNEL command to start the channel.

STOp

Issue a STOP CHANNEL command to stop the channel.

MQ Local Queues Display

To access the MQ Local Queues display, issue the MQQLocal command.

This display shows you information about MQ local queues.

The sample MQ Local Queues display:

```

SYSVIEW ----- MQLOCAL, MQ Local Queues -----
Command ==>                                     Scroll *==> PAGE
SET$009I MQLOCAL FORMATLINE set to NO ----- Lvl 2 Row 1-15/15 Col 1-79/849
Jobname CSQ5MSTR ASID 0284 Jobid STC61678 MQ 6.0 Qmgr CSQ5
Interval 53.0
-----
Cmd      Queue                                     Depth  QHWM IProc OProc Puts PutsD
-----
AMQ.C0634EF6AD4CDFEB                               1
CSQ5.GSVMSQSR.C0635C8468ED38CB                       1
IMSS.OTMA.QUEUE                                     200  250  1
SYSTEM.ADMIN.CHANNEL.EVENT                          20
SYSTEM.ADMIN.CONFIG.EVENT                          10
SYSTEM.ADMIN.PERFM.EVENT                          124
SYSTEM.ADMIN.QMGR.EVENT                            44
SYSTEM.CHANNEL.INITQ                                1
SYSTEM.CHANNEL.SYNCQ                                6
SYSTEM.CLUSTER.COMMAND.QUEUE                       1
SYSTEM.CLUSTER.REPOSITORY.QUEUE                   11
SYSTEM.CLUSTER.TRANSMIT.QUEUE                     1
SYSTEM.COMMAND.INPUT                               1
SYSTEM.PENDING.DATA.QUEUE                          1
TPTPTP.GSVMSQSR.C0635CC6B8D8EE0C                   1
    
```

Tasks Performed from the MQ Local Queues Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

DElete

Issue a DELETE QLOCAL for the queue.

PLot

Invoke a PLOTLIST MQQUEUE command to display a plot selection list for the selected local queue.

PLOTLIST MQQUEUE

Select or Alter

Invoke the MQALTER command to display and alter the attributes of the selected queue.

Link-to Command: MQALTER

MQ Queue Manager Display

To access the MQ Queue Manager display, issue the MQMGR command.

This display shows you information about the currently selected target MQ queue manager. For information about displaying potential target MQ queue managers, see the online help for the MQLIST command. For information about setting the target MQ queue manager, see the online help for the MQSERIES command.

The sample MQ Queue Manager display:

```

SYSVIEW ----- MQMGR, MQ Queue Manager -----
Command ==>                                     Scroll *==> PAGE
----- Lvl 2 Row 1-18/79 Col 1-79/100
Jobname CSQ5MSTR ASID 0284 Jobid STC61678 MQ 6.0 Qmgr CSQ5
-----
Description      Field      Value
Queue manager    QMName    CSQ5
Queue manager id QMID      CSQ5.C044F70A629CA54B
Description      Descr     CSQ5, IBM WebSphere MQ for z/OS V6.0.0
Accounting for queues AcctQ     OFF
Active channels  ActChl    200
Activity reports ActivRec  MSG
Adoption check   AdoptChk  ALL
Adoption MCA restart AdoptMCA  NO
Alteration date  AltDate   04/02/07
Alteration time  AltTime   09:27:51
Authority events AuthorEv   DISABLED
Bridge events    BridgeEv  DISABLED
Coded char set id CCSID      500
Channel auto-def exit ChAExit
Channel init adaptors ChIAdaps  8
Channel init dispatchers ChIDisps  5
Channel init service prm ChIServP  000000000000000000000000000000
Channel events   ChLEv     DISABLED

```


Chapter 10: IMS Displays

This section contains the following topics:

- [About IMS Displays](#) (see page 143)
- [IMS Subsystem List Display](#) (see page 143)
- [IMS Exception Alerts Display](#) (see page 144)
- [IMS Pools Display](#) (see page 145)
- [IMS Dependent Region List Display](#) (see page 146)
- [IMS Common Queue Subtask](#) (see page 146)

About IMS Displays

This chapter describes some representative IMS displays and some tasks you can perform on them.

In addition to the displays described in this chapter, there are many other IMS resource displays. To see menus and commands you can use, specify MENU IMS on the command line.

Note: You can use CA SYSVIEW line commands to perform many tasks on these displays. To see the valid line commands for a display, place your cursor in the line command input area and press the Help PF key.

IMS Subsystem List Display

The IMS Subsystem List display shows you information about IMS control regions. Both active and inactive control regions are displayed. To access the IMS Subsystem List display, issue the IMSLIST command.

The following screen is a sample IMS Subsystem List display.

```
SYSVIEW IMSLIST ----- IMS Subsystem List -----
Command ==>                                         Scroll *==> PAGE
----- Lvl 3 Row 1-6/6 Col 1-79/146
Jobname SVD61IM1  ASID 0081  Jobid STC01952  IMS 10.0 Id SVP1
-----
Cmd  Jobname  Status   Id  Region  Job-CPU R-Stg I/O-Req Clocktime Xrf
-----
----- SVD51IMS INACTIVE  IMSV
----- OPS51IMS INACTIVE  IMS1
----- OPS69IMS INACTIVE  IMS9
----- SVD61IM1 ACTIVE    SVP1 DB/DC   51.185  876K   2524  26:07:29 XRF
----- SVD61IM2 INACTIVE  SVP2
----- SVD61IM3 ACTIVE    SVP3 DB/DC   28.735  816K   2292  26:06:30
```

This second screen displays the fields that you see when you scroll to the right:

```

SYSVIEW IMSLIST ----- IMS Subsystem List -----
Command ==>                                     Scroll *==> PAGE
----- Lvl 3 Row 1-6/6 Col 1-18&81-141/146
Jobname SVD61IM1 ASID 0081 Jobid STC01952 IMS 10.0 Id SVP1
-----
Cmd  Jobname |Jobnr ASID Type Description                CC Ver SCD
-----
SVD71IMS                SYSVIEW DB/DC Test Region
OPS71IMS                OPS/MVS DB/DC Test Region
OPS69IMS                OPS/MVS DBCTL Coldstart 1
SVD61IM1  1952 0081 STC  SYSVIEW DB/DC XRF IRLM                10.0 00C7AEE8
SVD61IM2                SYSVIEW DB/DC XRF IRLM
SVD61IM3  1958 0086 STC  SYSVIEW DB/DC IRLM                10.0 00B3AEE8
    
```

Tasks Performed from the IMS Subsystem List Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Select

Select the active IMS control region for subsequent commands.

CHEckpt

Issue the IMS command CHE to take a simple checkpoint for the control region.

COLDSYS

Issue the IMS command ERE COLDBASE OVERRIDE to perform a cold start on both the database and communications components.

DUMPQ

Issue the IMS command CHE DUMPQ. This command causes IMS to take a DUMPQ checkpoint and shut down the control region.

EREstart

Issue the IMS command ERE. This command causes an emergency restart for the control region.

IMS Exception Alerts Display

To access the IMS Exception Alerts display, issue the IMSALERT command. This display shows you information about IMS data collection exception alerts. Data collection values are displayed if the current value exceeds a threshold definition.

The sample IMS Exception Alerts display:

```

SYSVIEW IMSALERT ----- IMS Exception Alerts -----
Command ==>                                         Scroll *==> PAGE
----- Lvl 3 Row 20-32/32 Col 1-79/226
Cmd Name      ID      Argument      Value      Status      Description
----
IMPLSIZE     SVP3     TTAB          256K      PROBLEM     Current pool size
IMPLMAX      SVP1     BXQE          96K       WARNING     Maximum pool size
IMPLMAX      SVP1     LGWA          116K      WARNING     Maximum pool size
IMPLMAX      SVP3     BXQE          96K       WARNING     Maximum pool size
IMPLMAX      SVP3     LGWA          116K      WARNING     Maximum pool size
IMPLSIZE     SVP1     STTR          56K       WARNING     Current pool size
IMPLSIZE     SVP1     XMCI          56K       WARNING     Current pool size
IMPLSIZE     SVP3     STTR          56K       WARNING     Current pool size
IMPLSIZE     SVP3     XMCI          52K       WARNING     Current pool size
IMSSTAT      IMSV          INACTIVE     INACTIVE   IMS ID status
IMSSTAT      IMS1          INACTIVE     INACTIVE   IMS ID status
IMSSTAT      IMS9          INACTIVE     INACTIVE   IMS ID status
IMSSTAT      SVP2          INACTIVE     INACTIVE   IMS ID status

```

IMS Pools Display

To access the IMS Pools display, issue the IMSPOOLS command. This display shows you a list of CBT pools that have been defined to the IMS control region. Current storage information for each pool is also available.

The sample IMS Pools display:

```

SYSVIEW IMSPOOLS ----- IMS Pools -----
Command ==>                                         Scroll *==> HALF
----- Lvl 4 Row 1-17/120
Jobname SVD61IM1 ASID 0081 Jobid STC01952 IMS 10.0 Id SVP1
Global 1.17M Local 496K
-----
Cmd      Pool  SP  Current Maximum  Gets  Frees  CSA  Pct%  ...25...50...75..100
-----
LSAV     0    160K 164K    40      1      CSA  32%
TTAB    231  256K 256K    64      1      CSA  21%
LQMW     0    92K  92K    23      1      CSA  19%
LCLL     0    88K  88K    22      1      CSA  18%
LGWA    231  112K 116K    42      14     CSA  9%
BXQE    231  96K  96K    12      14     CSA  8%
CLLE    231  80K  80K    20      14     CSA  7%
PST     231  76K  80K    33      14     CSA  6%
SVPL     0    32K  32K     8      14     CSA  6%
TIB     251  28K  28K     1      14     CSA  6%
STTR    231  56K  60K    28      14     CSA  5%
XMCI    241  56K  56K    14      14     CSA  5%
RECA     0    21.2K 21.2K  1      14     CSA  4%
DMHR    228  32K  32K     8      14     CSA  3%
EPST    231  36K  40K    10      14     CSA  3%
GQMW    231  36K  36K     9      14     CSA  3%
IRLM    231  32K  32K     8      14     CSA  3%

```

IMS Dependent Region List Display

To access the IMS Dependent Region List display, issue the IMSREGNS command. This display shows you information about dependent regions for the active IMS control region.

The sample IMS Dependent Region List Display:

```

SYSVIEW IMSREGNS ----- IMS Dependent Region List -----
Command ==>                                                    Scroll *==> PAGE
----- Lvl 4 Row 1-6/6 Col 1-79/122
Jobname SVD61IM1  ASID 0081  Jobid STC01952  IMS 10.0 Id SVP1
-----
Cmd      Jobname  Type  Id Status          Class      Program  Tran/Step
-----
          SVD61DL1 DLI   ACTIVE
          SVD61F11 FPM   1 ACTIVE          DFSIVP4
          SVD61F12 FPM   2 ACTIVE          DFSIVP5
          SVD61F13 FPM   3 ACTIVE          DBFSAMP3
          SVD61M11 TP    4 WAITING         1
          SVD61RC1 DBRC  ACTIVE
  
```

IMS Common Queue Subtask

The IMS Common Queue Server subtask (IMSCQS) is the interface between the z/OS Common Queue Server and CA SYSVIEW.

Display IMS Subsystem Shared Queues Group Information

You can obtain information about the IMS subsystems that participate in a shared queues group.

Follow these steps:

1. Issue the IMSLIST command.

The IMS Control Regions display shows the shared Q group name, CQS SSN, and the primary overflow message structure names.

2. Issue the IMSQTRAN, IMSQSTAT, or the IMSTRANS command.

IMSQTRAN shows the message counts for transactions queued to various queue types in the shared message queue.

IMSQSTAT shows the status of the CQS address space and the Coupling Facility structures that support the shared messaging environment used by the target IMS subsystem.

Use the IMS SPOC to Issue IMS Commands

You can use the CA SYSVIEW IMS single point of control (SPOC) to issue IMS type 1 and type 2 commands in an IMSPLEX. Type 1 commands must be preceded with a forward slash (/) character.

To use the SYSVIEW IMS SPOC, configure and implement:

- CA SYSVIEW Option for IMS
- An IMSPLEX
- IMS Common Services Layer
- IMS Structured Call Interface
- IMS Operations Manager

To issue IMS Commands

1. Issue the IMSSPOC command

The IMS SPOC screen displays as a console interface, which lets CA SYSVIEW communicate with the IMS subsystems participating in the IMSPLEX.

2. Change the IMSPLEX and Route fields using either of the following methods:

- Overtyping the data in the information area of the display
- Specifying the IMSPLEX and the Route parameters on the command line

IMSPLEX

Provides the current target IMSPLEX name.

Route

Provides the current route options that specify which IMSPLEX members the command is routed to. Asterisk (*) routes the command to all members.

The screen refreshes and displays the new data.

Chapter 11: CA Datacom Displays

This section contains the following topics:

[About the DATACOM Displays](#) (see page 149)

[DATACOM System Activity Display](#) (see page 149)

[DATACOM Directory Areas Display](#) (see page 150)

[DATACOM Directory Databases Display](#) (see page 152)

[DATACOM MUF Identity Display](#) (see page 153)

[DATACOM MUF Active Tasks Display](#) (see page 153)

About the DATACOM Displays

This chapter describes some representative CA Datacom resource displays and some tasks you can perform on them.

In addition to the displays described in this chapter, there are many other CA Datacom resource displays. To see menus of the commands you can use, specify MENU DATACOM on the command line.

This menu contains other menus that let you view different types of information, such as: CA Datacom directories, elements, keys, and so on, and CA Datacom MUF displays.

DATACOM System Activity Display

To access the DATACOM System Activity display, issue the DCLIST command.

This display shows you information about CA Datacom address spaces. The PARMLIB member DATACOM defines the list of job names to monitor; however, this information can also be obtained dynamically. For more on defining this list, see the *Administration Guide*.

The sample DATACOM System Activity display:

```

SYSVIEW ----- DCLIST, DATACOM System Activity -----
Command ==>                                         Scroll *==> PAGE
----- Lvl 2 Row 1-13/13 Col 1-79/184
Jobname SYSV31UR  ASID 0050  Jobid JOB19593  DATACOM n/a
-----
Cmd Name      JobStat  Job-CPU  RealStg  IOReqs  Clocktime  Jobnr  Stepname  Procname
DBDVM631  IN      0.051   1.13M    10      00:56:01   2713  $$$$$@
EDBC10MF  LSW     1.824   20M     1648    23:38:45  19383  DB10STRT  DBMUF
I0D0STRT  NS      1.494   15.8M   1634    15:37:01  27261  AD10STRT  DBMUF
MMIMDB31  IN      1.286   10.7M   2163    01:19:22   2363  DB11STRT  DBMUF
QAMUF11G  NS      7.366   1.84M   3120    23:08:11  20095  QAMUF11G  $$$@NX@
QAMUF11M  NS     10.112   7.13M   5934    23:08:36  20076  QAMUF11M  $$$@NX@
QAMUF11W  NS      1.737   2.24M   1786    23:08:24  20087  QAMUF11W  $$$@NX@
QAMUF11Z  NS      2.174    28M    2164    23:08:05  20099  QAMUF11Z  $$$@NX@
QAMUF111  NS      2.700   3.47M   2151    23:08:26  20085  QAMUF111  $$$@NX@
SCDP1MUF  NS      4.487   544K    1340    23:39:21  19266  SCDP1MUF  DBMUF
SCHDMUF   NS      4.233   588K    653     23:40:21  19152  SCHDMUF   DBMUF
SQL2MUFA
SQL2MUFB  LSW      0.973   14.3M   1749    19:41:14  24871  DBMUF
***** End of Data *****

```

Tasks Performed from the DATACOM System Activity Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

JJobque

Lists the jobs for a selected job name.

Link-to Command: JJOBQUE

Select

Selects the address space for use in future displays. The currently selected address space is displayed in the information section.

Example:

```
Jobname  DATACOM  ASID  0039
```

Link-to Command: ASID

DATACOM Directory Areas Display

To access the DATACOM Directory Areas display, issue the DCAREAS command.

This display shows you an entry for each area in the Directory (CXX).

The sample DATACOM Directory Areas display:

```

SYSVIEW DCAREAS ----- DATACOM Directory Areas -----
Command ==>                                         Scroll *==> HALF
----- Lvl 2 Row 1-18/55 Col 1-79/177
Jobname SYSVDCOM  ASID 017E  Jobid STC03610  DBID *
-----
Cmd DBID Area Occurrence                Inserts HiURI Moved Tracks Slack
---- 1 DEM DEMO-DEM                        17                0
---- . PAY PAYROLL                          200               0
---- . PMF PERSONNEL                         200               0
---- 2 AGR AGGREGATE                          69 225           5   10   0
---- . ALS ALIAS                            109 1032          10   0
---- . ARA AREA                              11 71             10   0
---- . ATZ AUTHORIZATION                      1 8               10   0
---- . BAS DATABASE                          5 16              10   0
---- . DWV DATAVIEW                          37               10   0
---- . ELM ELEMENT                           72 381            10   0
---- . FIL FILE                               80               10   0
---- . FLD FIELD                             2671 8550         163  20   0
---- . HSD DD-HSD-FILE                       172 344           10   0
---- . JOB JOB                                10               10   0
---- . KEY KEY                                70 296            10   0
---- . KWC DESCRIPTOR                        30               10   0
---- . LIB LIBRARY                            10               10   0
---- . MEM MEMBER                             10               10   0

```

Tasks Performed from the DATACOM Directory Areas Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Select

Displays information for every table in the current area.

Link-to Command: DCTABLES

DSets

Displays information about the data set in the current area.

Link-to Command: DCDSETS

IO

Displays read and write statistics for the current area.

Link-to Command: DCAREAIO

Tables

Displays information for every table in the current area.

Link-to Command: DCTABLES

DATAKOM Directory Databases Display

To access the DATAKOM Directory Databases display, issue the DCDBASES command.

This display shows you one entry for each database in the directory.

The sample DATAKOM Directory Databases display:

```

SYSVIEW DCDBASES ----- DATAKOM Directory Databases -----
Command ==>                                         Scroll *==> PAGE
----- Lvl 2 Row 1-11/11 Col 1-79/172
Jobname SYSVDCOM ASID 017E Jobid STC03610 DBID *
-----
Cmd DBID Occurrence                               Tracks Index Part Extend Read Rep SQL
---  ---  ---
1 HUMAN-RESOURCE                                15     1     1  EXTEND
2 DATA-DICT                                    20     2     1  EXTEND
4 PRM-ACT-DB                                    5      1     1  EXTEND  READ
5 SAMP-ACT-DB                                   20     1     1  EXTEND
6 CBS-DB                                        1
10 ORDER-ENTRY                                 1
15 DDD-DATABASE                                20     1     1  EXTEND
16 CASQLDEFAULT                                1
17 TTM-DATABASE                                1
400 B400-DATABASE                              1
1000 CASYSTEMTABLES                            1                                     READ
    
```

Tasks Performed from the DATAKOM Directory Databases Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Select or Areas

Displays the areas for the selected database.

Link-to Command: DCAREAS

DSets

Displays data sets for the selected database.

Link-to Command: DCDSETS

IO

Displays read and write statistics for the selected database.

Link-to Command: DCAREAIO

Tables

Displays the tables for the selected database.

Link-to Command: DCTABLES

DATACOM MUF Identity Display

To access the DATACOM MUF Identity display, issue the DCMUFS command.

This display shows you multi-user facility system information for CA Datacom address spaces.

The sample DATACOM MUF Identity display:

```

SYSVIEW DCMUFS ----- DATACOM MUF Identity -----
Command ==>                                         Scroll *==> PAGE
----- Lvl 2 Row 1-1/1 Col 1-79/90
Jobname SYSVDCOM  ASID 017E  Jobid STC03610
-----
Cmd MUFname  Dirname  Nodename SubID  SVC Release SP  GenLvl RAAT-Sec  SQL-Sec  D
___ SYSVDCOM DCOM90              0 213  11.0              NONE    NONE    I
    
```

DATACOM MUF Active Tasks Display

To access the DATACOM MUF Active Tasks display, issue the DCTASKS command.

This display shows information about CA Datacom tasks.

The sample DATACOM MUF Active Tasks display:

```

SYSVIEW DCTASKS ----- DATACOM MUF Active Tasks -----
Command ==>                                         Scroll *==> PAGE
----- Lvl 2 Row 1-4/4 Col 1-79/142
Jobname QA90MUF1  ASID 00A7  Jobid JOB01430
-----
Cmd Jobname  Task#  Owner  Excps  RunUnit  SeqNum  Command  Status  Duration
___ B310EXEC   4          48585  128783  REDKY   NOT ACTIVE  000:00
___ G315EXEC   13         48594  128781  UPDAT   NOT ACTIVE  000:00
___ H316EXEC   14         48595  128778  ADDIT   NOT ACTIVE  000:00
___ I317EXEC   1          48581  128782  ADDIT   NOT ACTIVE  000:00
    
```


Chapter 12: TCP/IP Displays

This section contains the following topics:

[About the TCP/IP Displays](#) (see page 155)

[Access the TCP/IP Stacks Display](#) (see page 155)

[Access the IP Users Display](#) (see page 157)

[Access the TCP/IP Connections Display](#) (see page 158)

[Access the IP Devices Display](#) (see page 160)

About the TCP/IP Displays

This chapter describes some representative TCP/IP resource displays and some tasks you can perform on them.

To see menus of the commands you can use, specify MENU TCP on the command line. This menu contains other menus that let you view different types of information, such as:

- Configuration
- Statistics
- UDP connections

Access the TCP/IP Stacks Display

The TCP/IP Stacks display provides information about active or stopped TCP/IP stacks. Use these steps for accessing and using the TCP/IP Stacks display.

Follow these steps:

1. Issue the TCPLIST command
The TCP/IP Stacks display is accessed.
2. Enter the appropriate line command against the stack you are working with.

The sample TCP/IP Stacks display:

```
SYSVIEW ----- TCPLIST, TCP/IP Stacks -----
Command ==>>>                               Scroll *==>> PAGE
----- Lvl 3 Row 1-3/3 Col 1-79/197
TCP Jobname TCPIP31 (DEFAULT)
Jobname SYSTCPD
USER01 VTAM.TCPIP.TCPIP.DATA
SYSVIEW VTAM.TCPIP.TCPIP.DATA
-----
Cmd  Jobname  Status  Hostname IPV6  ClockTime  CPUtime  RealStg  IOCount
----  -
TCPIP31  ACTIVE  TCPIP31  ENABLED  41:48:13  00:05:15  8.91M  117565
TCPIP31V ACTIVE  TCPIP31V ENABLED  41:48:06  00:01:25  4.8M   15429
TCPIP99  ACTIVE  TCPIP99  ENABLED  41:48:07  00:01:21  3.46M   5518
```

Tasks Performed from the TCP/IP Stacks Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Activity

Display the system activity for the selected TCP/IP stack jobname.

Link-to Command: ACTIVITY

Ping

Ping the hostname for the TCP/IP stack.

Link-to Command: PING

Mib2

Browse the MIB2 MIB for the TCP/IP stack.

Link-to Command: MIBBROWS

Select

Set the selected TCP/IP stack as the target stack.

Link-to Command: TCPOPTS

Access the IP Users Display

The IP users display provides information about the jobs that use the selected TCP stack.

Follow these steps:

1. Issue the IPUSERS command to access the display.
2. Enter the appropriate line command against the jobs you are working with.

The sample IP Users display:

```

SYSVIEW ----- IPUSERS, IP Users -----
Command ==>                                     Scroll *==> PAGE
-----
TCP Jobname TCP/IP31 (DEFAULT)
Interval      2.0
-----

```

Cmd	Jobname	ASID	TCP	UDP	Lsn	InBytes	OutBytes	InD	OutD	InR	OutR
---	AW31RSTR	01FD	1	2		1036691	10763020				
---	CCISLW	00AD	38		1	254448500	206748814	45301	27864	22651	13932
---	CCITCPG2	00AB	13		1	45272259	73088976	1494	1235	747.0	617.5
---	CSQ5CHIN	02EE	2		1	4373020	16574571				
---	DENMX2JV	005A	1		1	3837337	183287				
---	DENMX3JV	01CC	1		1	447155	20667				
---	DENMX5JV	01D1	1		1	3353301	158976				
---	DFSKERN	011D		2	1	445416	1170114				
---	D81ADIST	0140	39		2	20257129	21561306	2188	3321	1094	1661
---	MVSNFSC	001E	3	7		246202332	116054888	2440	1256	1220	628.0
---	OSNMPD	0138		1	1	45941137	48208110				
---	SYSQA09	007D	3		3	442352444	442352696				
---	SYSQA10	0082	3		2	442351720	442352444				
---	TCP/IP31	00E7	13		6	3045080	34987667	86	1634	43.00	817.0

Tasks Performed from the IP Users Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Lsn

Drill down to show details about each listener socket the job has opened.

Link-to Command: IPLISTEN

Tcp

Drill down to show details about each TCP socket the job has opened.

Link-to Command: IPTCONN

Udp

Drill down to show details about each UDP socket the job has opened.

Link-to Command: IPUCONN

Access the TCP/IP Connections Display

The TCP/IP connections display provides information about each TCP socket connection for each job using the TCP stack.

Follow these steps:

1. Issue the IPTCONN command
The TCP/IP Connections display is accessed.
2. Enter the appropriate line command against the connection you are working with.

You can now use the TCP/IP Connections display.

The sample TCP/IP Connections display:

```

SYSVIEW ----- IPTCONN, TCP/IP Connections -----
Command ==>                                         Scroll *==> CSR
----- Lvl 3 Row 129-144/189 Col 1-79/615
Formats DEFAULT PERFORM SECURITY SOCKOPTS STATE TEST
TCP Jobname TCPIP31 (DEFAULT)
Interval TOTAL
-----
Cmd  Jobname  ASID  Subtask  State      Port  PortName      RAddr
----  -
___  D81ADIST  0140  007B1CF0 ESTABLISHED 5141      192.168.31.215
___  .          .      .          ESTABLISHED .          192.168.31.88
___  EDCQAM01  0099  007F90C8 ESTABLISHED 3011      192.168.65.31
___  .          .      007A1378 ESTABLISHED 3015      192.168.65.31
___  JCKTE#G2  0192  007CAD90 ESTABLISHED 3689      ::FFFF:192.168.65
___  .          .      00000000 ESTABLISHED 24233     ::FFFF:192.168.65
___  LABD0023  0205  007FF708 ESTABLISHED 1831      192.168.201.201
___  LABD0024  01F2  007FF210 ESTABLISHED 1832      192.168.201.201
___  LABD0025  020F  007FF708 ESTABLISHED 1830      192.168.201.201
___  LABD0028  0234  007FF290 ESTABLISHED 3608      192.168.27.141
___  MVSNFSC   001E  007C8718 ESTABLISHED 1753      ::FFFF:192.168.27
___  .          .      007C8400 ESTABLISHED 1975      ::FFFF:192.168.27
___  .          .      007C8268 ESTABLISHED 3321      ::FFFF:192.168.27
___  M81ADIST  00F3  007B0658 ESTABLISHED 5151      192.168.10.26

```

Tasks Performed from the TCP/IP Connections Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

DROP

Issue the following command for the selected connection:

```
VARY TCPIP, ,DROP
```

Link-to Command: XMVS

Intf

Drill down to show details about the device and interface that the connection uses.

Link-to Command: IPDEVICE

Ping

Ping the remote address for the connection.

Link-to Command: PING

Access the IP Devices Display

The IP Devices display provides information about the devices, links, and interfaces that are defined for the TCP/IP stack.

Follow these steps:

1. Issue the IPDEVICE command.
The IP Devices display is accessed.
2. Enter the appropriate line command against the device, link, or interface you are working with.

The sample IP Devices display:

```

SYSVIEW ----- IPDEVICE, TCP Devices/Links/Interfaces -----
Command ==>                                           Scroll *==> PAGE
----- Lvl 2 Row 1-4/4 Col 1-79/195
TCP Jobname TCPIP31 (DEFAULT)
-----
Cmd  DevName      DevType  DevStatus  Name      Type      Status
----  -
----  LOOPBACK      LOOPBACK  READY      LOOPBACK  LOOPBACK  READY
----  .              .          .          LOOPBACK6 LOOPBACK6  READY
----  OSD12         MPCIPA    READY      OSA       IPAQENET  READY
----  IUTIQDFF     MPCIPA    READY      HIPERLFF  IPAQIDIO  READY
----  OSD53        MPCIPA    READY      OSA53LNK IPAQENET  READY
----  .            .          .          OSAQDI026 IPAQENET6  READY
  
```

Tasks Performed from the IP Devices Display

To perform line commands from this display, place your cursor in the command input area to the left of the variable.

The following line commands are valid, only the uppercase portion of the line command is necessary for you to specify:

Ping

Ping the device address.

Link-to Command: PING

Select

Display detail information about the device and link or interface.

Link-to Command: XTSO

STArt

Issue the following command for the device or interface:

```
VARY TCPIP,START
```

Link-to Command: XMVS

STOp

Issue the following command for the device or interface:

```
VARY TCPIP,STOP
```

Link-to Command: XMVS

Chapter 13: System Condition Monitor Displays

This section contains the following topics:

[How the System Condition Monitor Works](#) (see page 163)

How the System Condition Monitor Works

The System Condition Monitor (SCM) displays tell you at a glance where the problems are. This display eliminates the need to search multiple areas to find the problem sources.

The SCM provides a color-coded, high-level summary of resources that are currently being monitored.

Access the SCM Display

The SCM display lets you obtain threshold information, as follows:

- According to the type of data, including MVS, CICS, USS, IMS, TCP/IP, or WebSphere MQ system entries
- According to the system name of the desired MVS system
- Data for all connected systems or only the current system

Follow these steps:

1. Issue the SCMSYS command

The sample System Condition Monitor display:

```

SYSVIEW ----- SCMSYS, System Condition Monitor -----
Command ==>                                     Scroll *==> PAGE
----- Lvl 2 Row 1-17/22 Col 1-79/126
(r) Pct% ..25..50..75.100 -Condition- ---Ready--- ---Paging--- --Common--
CPU 100%                    ENQ NoSMF ASIDs 24 Slots 39% ECSA 75%
LCPU 45%                    RES NoWTO Tasks 24 Rate 1 ESQA 94%
                               NoDMP NoTAP ----I/O---- AFQA 33543 SQA 91%
Spool 81%                    Rate 5394 UICA 2540 CSA 76%
-----
Jobname GREZZ99 ASID 02E8 Jobid TSU29348
ISERVE ISRV      Name *      Type *
-----
Cmd Name      Description                Norm Warn Prob Status System
FILESYS      USS File systems              11 16 PROBLEM ZZ99
JOBS         Job resource alerts           3 13 PROBLEM .
WLM          Workload Manager              11 2 PROBLEM .
STORAGE      Common storage usage          1 PROBLEM .
OPERATOR     Operations overview           25 5 ACTION .
JES2OUT     JES2 output                   20 1 WARNING .
PAGING       Paging alerts and datasets     2 1 WARNING .
DEVICES      Devices and connections        3 NORMAL .
ENQUEUES     Enqueue Conflicts             1 NORMAL .
PRINTERS     Printer devices                1 NORMAL .
SMS          SMS storage groups            1 NORMAL .
    
```

- 2. Place an S in the command area to the left of the OPERATOR entry.

The resulting detailed display for the OPERATOR entry:

```
SYSVIEW SCMENTRY ----- System Condition Monitor Detail -----
Command ==>                                                    Scroll *==> HALF
----- Lvl 3 Row 1-10/10 Col 1-79/186
System  Type   Name      Status
XE44    MVS     OPERATOR ACTION REDQ
-----
Cmd Description                                                    Status
___ Intervention required on 2 TAPE devices.                       ACTION
___ WTOs requiring replies is 42                                   ACTION
___ Enqueue conflicts are causing 1 jobs to wait.                  WARNING
___ The JES2 input queue has 3 jobs held due to duplicate jobnames. WARNING
___ There are 4 jobs waiting for classes X,S.                     WARNING
___ WTO buffers are queued on 6 EXTENDED CONSOLES.                WARNING
___ No PRINT devices require attention.                            NORMAL
___ Spool volume SPL44A extension 0 is 54.4% full.                 NORMAL
___ Spool volume SPL44B extension 1 is 52.6% full.                 NORMAL
___ SMF recording 35% used. Dsn=SYS1.MAN1                          NORMAL
```


Chapter 14: Cross-System Resource Monitoring Displays

This section contains the following topics:

[Cross-System Resource Monitoring](#) (see page 167)

Cross-System Resource Monitoring

The Cross-System Resource Monitoring feature lets you remotely display, monitor, and manage information from:

- A current system
- All connected systems
- A subset of connected systems

You perform these tasks from one interface without using a session manager. This feature uses the CA Common Communications Interface (CAICCI) component of CA Common Services (CCS) to implement the cross-system communication.

When the available sessions that are cross-system capable are displayed, you can use the screens to do the following tasks:

- Jump to any of those active sessions, including sessions that are running under different CA SYSVIEW releases, and monitor the information.
- Use the cross-system mode of multiple systems. This mode lets you gather and display data from all of the active cross-system capable sessions running under the same CA SYSVIEW release.

Note: The cross-system mode of multiple systems cannot gather data from sessions that are running under different releases of CA SYSVIEW.

Display the Cross-System Connections

The following two sample displays show the cross-system servers and statistics.

Follow these steps:

1. Issue the XSLIST command.

The XSystem Servers panel containing a list of available cross-system connections displays.

From this panel, you can select and switch to a remote system using the XSCONN command or by selecting a system from the menu.

For information about these commands or any other CA SYSVIEW commands, select the Menu Help option on the Primary Option Menu and review the materials.

```

SYSVIEW XSLIST ----- XSystem Servers -----
Command ==>                                     Scroll *==> HALF
-----
Cmd   System  Status  Type  Description  Lvl 2 Row 1-13/13 Col 1-79/377
-----
      DEVA    ACTIVE  DATA Development system A  GSVX SYSVIEW
      .      ACTIVE  SESS  .                GSVX SYSVUSER
      DEVB    INACTIVE      Development system B
      DEVC    INACTIVE      Development system C
      MAINTA  INACTIV      Maintenance system A
      MAINTB  INACTIVE      Maintenance system B
      PROD    ACTIVE  DATA Production system      GSVX SYSVIEW
      .      ACTIVE  SESS  .                GSVX SYSVUSER
      SYSTEM1 INACTIVE      Production system 1
      SYSTEM2 ACTIVE  DATA Production system 2      GSVX SYSVIEW
      .      ACTIVE  SESS  .                GSVX SYSVUSE
      TEST    ACTIVE  DATA Test system        GSVX SYSVIEW
      .      ACTIVE  SESS  .                GSVX SYSVUSER
    
```

2. Select the PROD system from the menu.

The XSYS PROD displays. The interface type of XSYS on the title line indicates that you are viewing statistics from a cross-system session. PROD indicates that the system activity statistics are from the production system.

```

SYSVIEW XSYS PROD ----- ACTIVITY, System Activity -----
Command ==>                                     Scroll *==> PAGE
-----
Hop 1 Lvl 3 Row 1-14/435 Col 1-79/439
CPU 17% LCPU 17% Paging 3 SIO 972 UIC 2540 AFC 1857
-----
=
Cmd Jobname Stepname Procstep Type Jobnr Jc Status CPU-Time Limit Clocktime
___ *MASTER*          SYS 1234 $ NS 00:04:47 86400 59:51:59
    
```

Selected product commands can display gathered data from remote systems. Gathering data from a remote system requires:

- An active product data server on the remote system
- A reachable system through the CAICCI communication network

Control the Display of Cross-System Data

The following list summarizes the SET keywords. These keywords control the display of cross-system data and only apply to commands that are defined as cross-system data capable. For a list of commands that have this attribute, issue the XSCMDS command.

XSData

Controls whether the cross-system data is gathered and displayed. The values are YES and NO.

Default: NO

XSGroup

Controls which system gathers and displays the cross-system data. Values are the keywords:

- ALL
- NONE
- Group name (as defined by the GROUPS PARMLIB member or the GROUPS command) or a specific system name or alias

The group must be defined as the type XSSYSTEM and the members are the names of the systems from which data is displayed. The group member names cannot be aliases.

Default: ALL

Note: The XSGROUP NONE is not the same as XSDATA NO. With XSGROUP NONE and XSDATA YES, the screen displays the cross-system fields but does not display data from any remote systems.

XSLimit

Sets a limit on the number of command data records that are returned from a remote system. The value must be a number from 0 to 99999 or the keyword NONE. A value of 0, or the equivalent NONE keyword means that there is no limit on the number of returned records from a remote system.

Default: NONE (or 0)

XSMsglvl

Controls the display of data lines for systems from which data could not be obtained. The message data line displays the system name and message in a field named XSMsg.

The values are NONE, INFO, WARN, and ERROR.

Default: ERROR

XSRemdup

Controls the removal of duplicate systems from any hardware, sysplex, or node base cross-system data. The values are:

NO

No duplicate systems are removed from any hardware, sysplex, or node base cross-system data.

AUTO

Automatically removes the duplicate systems from any hardware, sysplex, or node base cross-system data. Only the first system (taken in alphabetical order) within like-named hardware, sysplex, or node (JES MAS) configurations are displayed.

PREF

A system preference order is used to remove the duplicate systems. A group name the same as the hardware, sysplex, or node configuration defines the order with a group type of XSHDWR, XSPLEX, or XSNODE.

The order of the group members (system names) in the group defines the preferred order. The first available system, if any, is used. If no matching system names are found, then the systems are considered in alphabetical order (the same as AUTO).

Default: NO

The AUTO and PREF options only apply when the XSGROUP name is ALL and only when cross-system data type is HARDWARE, SYSPLEX, or NODE. In all other cases, AUTO and PREF are ignored.

Duplicate data resulting from more than one cross-system data server active on a system is automatically removed.

XSStatusline

Controls the display of the cross-system status line in the screen info line area. The values are:

YES

Always display the cross-system status line.

NO

Never display the cross-system status line.

COND

Only display the cross-system status line when XSDATA is YES.

Default: NO

XSCMDS Command Display

The XSCMDS command displays all cross-system capable commands and the set status for each command. This display lets you easily control the cross-system data for a command by simply changing the command values in the data fields.

The following example XSCMDS command display shows:

- A few cross-system capable commands and their default values
- The changed default ACTIVITY data field values for Data, Limit, and Stat

```

SYSVIEW VTAM ----- XSCMDS, XSystem Data Commands -----
Command ==>>>
-----
Cmd      Name      Description      Data Group  MsgLvl Limit Stat RemDup Type
-----
ACTIVITY System activity  YES  ALL    ERROR  500 YES  NO  System
ALERTs   MVS exception alerts  NO  ALL    ERROR  NONE NO  NO  System
.
.
.
.
PARTinfo Partition information  NO  ALL    ERROR  NONE NO  NO  HARDWARE
PLEXSys  Sysplex systems      NO  ALL    ERROR  NONE NO  NO  SYSPLEX
WTOR     WTO reply required messages  NO  ALL    ERROR  NONE NO  NO  SYSPLEX

```


Chapter 15: Using SDSFMIGRATE to Migrate from SDSF

This section contains the following topics:

[How to Activate the SDSFMIGRATE Option](#) (see page 173)

[Masking Characters for the SDSFMIGRATE Option](#) (see page 174)

How to Activate the SDSFMIGRATE Option

CA SYSVIEW provides the SDSFMIGRATE option to help you migrate from the IBM SDSF product to CA SYSVIEW.

The SDSFMIGRATE option lets you:

- Work in an environment similar to SDSF while becoming accustomed to the CA SYSVIEW environment and command structure
- Enter most SDSF primary commands
- Enter most SDSF line commands

To activate and use this option, do the following steps:

1. Enter the SET SDSFMIGRATE ON command or have the CA SYSVIEW administrator change the DEFAULT profile when the product is first installed.

Note: For more information about the DEFAULT profile, see the *Administration Guide*.

2. Compare the SDSF commands with the CA SYSVIEW commands by entering the following command:

```
MENU SDSF
```

3. After you become used to CA SYSVIEW and want to experience the full potential and flexibility of its environment, issue the following SET command:

```
SET SDSFMIGRATE OFF
```

The option is turned off.

Masking Characters for the SDSFMIGRATE Option

When the SDSFMIGRATE option is turned on:

- The fixed-length masking character is set to a percent sign (%)
- The variable-length masking character is set to an asterisk (*).

When you turn off the option, these settings remain the same; they are not reset to the CA SYSVIEW defaults.

Chapter 16: Create Reports Using the CA Easytrieve Reporting Service

This section contains the following topics:

- [About CA Easytrieve](#) (see page 175)
- [Planning Reports](#) (see page 175)
- [Generating Canned Reports](#) (see page 176)
- [Sample Output from Canned Reports](#) (see page 178)
- [Report Structure](#) (see page 194)
- [Macros](#) (see page 195)
- [SMF Record Descriptions](#) (see page 202)

About CA Easytrieve

This chapter explains how to use CA Easytrieve Common Reporting Service (CA Easytrieve) to create CA SYSVIEW historical reports.

CA Easytrieve is an information retrieval and data management language that produces tabular reports by retrieving data from:

- SMF records produced by CA SYSVIEW
- Various MVS and RMF components

Note: CA Easytrieve Common Reporting Service is a subset of CA Easytrieve. If you already have CA Easytrieve installed at your site, you can use its full reporting capability. For a detailed description of the CA Easytrieve language, see the *CA Easytrieve Report Generator Reference Guide* available on CA Support Online at <https://support.ca.com>.

Planning Reports

With CA Easytrieve, you can follow these basic steps when programming reports:

- Define the files and working storage variables
- Extract a subset of records from an input file
- Order the records by some key; for example, by timestamp and data set name
- Accumulate counters and calculate averages, rates, and so on
- Format the output report

Generating Canned Reports

A canned report is a report for which commands are already written for you. All of the canned reports that are shipped with CA SYSVIEW are distributed as CA Easytrieve macros in the sysview.CNM4ZMAC data set. These macros simplify common actions, for example, the selection by time, record type, and so on.

Sample JCL

Use the following sample JCL as a guide for writing your own reports:

```
// JOBCARD
// SET PROGRAM=GSVUEZTR
// SET EZTLOAD=      dsname for Easytrieve program library
// SET EZTMAC=      dsname for Sysview Easytrieve macros
// SET SYSVLOAD=    dsname for Sysview program library
// SET SMFIN=      dsname for input SMF data
// SET WRKSPACE=20  space, in cylinders, for temporary work files
// SET WRKUNIT=VIO  unit name for temporary workfiles
//EXECEZTR EXEC PGM=&PROGRAM
//STEPLIB DD DSN=&EZTLOAD,DISP=SHR
//          DD DSN=&SYSVLOAD,DISP=SHR
//PANDD   DD DSN=&EZTMAC,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSUDUMP DD SYSOUT=*
//SYSOUT  DD SYSOUT=*
//SMFIN   DD DISP=SHR,DSN=&SMFIN
//EZTVFM  DD UNIT=&WRKUNIT,SPACE=(CYL,(&WRKSPACE,&WRKSPACE))
//ERRORS  DD SYSOUT=*
//REPORTS DD SYSOUT=*
//SYSIN   DD *
LIST ON NOMACRO
%DISKSTAT TOP 20
```


Canned Report Keywords

All canned reports that are shipped with CA SYSVIEW support the following keyword parameters:

EACH

Determines the length of each reporting interval, which can be one of the following values:

- *n* DAY determines that the reporting interval is *n* days.
- MONTH determines that the reporting interval is one month.
- *n* HOUR determines that the reporting interval is *n* hours.
- *n* MIN determines that the reporting interval is *n* minutes.
- RECORD determines that the TSTAMP value for each SMF record should be set to the actual timestamp, without adjustment.

Default: DAY

FROM

Determines the starting timestamp for SMF record selection. The SELECT-PROC subroutine uses FROM to exclude SMF records that have timestamps earlier than the provided value. The timestamp is specified as YYYY/MM/DD-HH:MM.

Default: ALL, which allows all records to be selected.

SHIFT

Determines the time range for selecting data. The SELECT-PROC subroutine uses this range to exclude SMF records which do not fall within the specified time range. The range is specified as h1:m1 h2:m2.

- h1:m1 specifies the starting time for the shift
- h2:m2 specifies the ending time for the shift

If h1:m1 is greater than h2:m2, then two time ranges are assumed: h2:m2 24:00 and 00:00 h1:m1.

Default: 00:00 24:00

TO

Determines the ending timestamp for SMF record selection. The SELECT-PROC subroutine uses TO to exclude SMF records that have timestamps later than the provided value. The timestamp is specified as YYYY/MM/DD-HH:MM.

Default: ALL, which allows all records to be selected.

Sample Output from Canned Reports

The CICS, MVS, and WebSphere MQ sample canned reports that are discussed in this section are shipped with CA SYSVIEW.

CICS Canned Reports

This section shows the CICS sample reports and the code to produce them.

Note: The CICS canned reports require CA SYSVIEW Option for CICS collected data.

ABEND Summary

This report shows the CICS program ABEND summary. In addition to the standard parameters, the following keyword parameter is supported:

RECTYPE

Record type containing the SYSVIEW SMF data.

Default: 255

To create a CICS ABEND Summary report, use this ABENDSUM code:

```
LIST OFF
%ABENDSUM
```

The sample CICS ABEND Summary report:

TRAN	PROGRAM	ABEND CODE	COUNT
2008/05/20 08:07	CA SYSVIEW CICS Program	ABEND Summary	PAGE 1
From:	2008/03/04 08:57	Each:	DAY
To:	2008/03/05 07:32	Shift:	00:00 24:00
Interval Start:	2008/03/04 00:00		
	CICS		
TRAN	PROGRAM	ABEND CODE	COUNT
-----	-----	-----	-----
CSMI	DFHMIRS	ASRA	10
CSMI	PGDS	ASRA	10
CWXN	DFHWBXN	AWB2	2
DQIN	VPEHJE62	ATNI	1
MP30	PR3MAINI	ASRA	1
MP30	PR3SREMS	ASRA	1
TRLC	PGLC	ASRA	1
TRLC	PGLC	CAC1	1
TRME	PGME	ASRA	1
TR64	PGB5	CAC1	2
TR64	PGB5	NPRM	2
TR65	PG51	ASRA	1
TR65	PG51	CAC1	1
TR80	PG80	????	3
TR80	PG80	ASRA	4
TWBA	LKMK	ASRA	79
TWBA	LKMX	ASRA	29

Program Usage Summary

This report shows the CICS program usage statistics. In addition to standard parameters, the following keyword parameters are supported:

RECTYPE

Specifies the record type containing the SYSVIEW SMF data.

Default: 255

ORDERBY

Specifies the variables that are used to sort for the final report, which can be any combination of PROGRAM, USAGE, PERCENT, AVG_TIME, and AVG_CPU.

Default: USAGE D

TOP

Restricts the number of lines of output for each time interval.

Default: 99999999

NAME

Filters by the program name. The default is * (an asterisk), which selects all program names.

To create the CICS Program Usage Summary report, use this PROGUSE code:

%PROGUSE

The sample CICS Program Usage Summary report:

Name	Use Count	% of All	AVG Time	AVG CPU
XMLDOC	271,528	59.1	0.116	0.000
SQLDYN	41,175	9.0	3.232	0.227
@IAESYNC	38,927	8.5	3.301	0.129
IN25TDAT	16,013	3.5	0.059	0.000
DFHCCNV	10,158	2.2	443.281	0.121
IN25SGET	9,211	2.0	6.450	1.191
IN25MSG5	7,703	1.7	0.095	0.000
IN25PGMS	6,116	1.3	1104.373	0.712
VPEHJE62	5,680	1.2	174.713	11.013
DFHUCNV	5,274	1.1	0.038	0.000
IN25LGTE	4,169	0.9	7.852	1.365
SC00DISP	4,152	0.9	1.008	1.250
IN25MSGP	3,616	0.8	0.297	0.000
IN25AKRE	3,368	0.7	0.136	0.000
DFHMIRS	2,663	0.6	2.576	1.067
PR3MAINI	2,061	0.4	3.795	4.936
MP3SMGRI	1,964	0.4	72.566	10.444
IN25SER1	1,812	0.4	63.625	0.669
IN25AKCO	1,684	0.4	283.718	24.308
IN25AKEP	1,684	0.4	0.991	0.026
IN25SCORE	1,683	0.4	2.123	1.254
DQ0NLPR	1,380	0.3	7.620	1.091
IN25AKBE	1,349	0.3	0.149	0.000
SPOLFAX	1,091	0.2	0.847	0.097
DFHWBA	1,080	0.2	60.095	37.901
DFHWBBLI	1,080	0.2	4.968	0.124
DFHWBXN	946	0.2	16.214	0.263

Statistics Summary

This report shows the CICS Statistics. In addition to standard parameters, the following keyword parameters are supported:

RECTYPE

The record type containing the SYSVIEW SMF data.

Default: 255

ORDERBY

The variables that are used to sort for the final report, which can be any combination of JOBNAME, TRANUSE, TRANTIME, TRANRATE, TRANCPU, and TRANIO.

Default: TRANUSE D

TOP

Used to restrict the number of lines of output for each time interval.

Default: 99999999

To create the CICS Statistics Summary report, use this CICSSTAT code:

```
LIST OFF
%CICSSTAT
```

The sample CICS Statistics Summary report:

2008/05/20 08:07 CA SYSVIEW CICS Statistics Summary									
From: 2008/03/04 08:57 Each: DAY									
To: 2008/03/05 07:32 Shift: 00:00 24:00									
Interval Start: 2008/03/04 00:00 Order by: TRANUSE D									
CICS JOBNAME	TRAN USE	TRAN TIME	TRAN RATE	TRAN MAX TIME	TRAN CPU	TRAN I/O	FILE USE	FILE I/O	FILE TIME
TOPCDEVL	4772	8.274	0.05	2087.73	0.027	0.034	155,665	0.034	
A02ICSTT	4739	5.343	0.05	1887.50	0.014	0.045	117,779	0.045	
TOPCQAQA	4727	6.677	0.05	1962.96	0.015	0.017	70,086	0.017	
TOPCDEV3	2391	11.962	0.02	1887.44	0.020	0.114	166,995	0.114	
CACTAPG	1243	19.909	0.01	1887.47	0.014	0.005	4,022	0.005	
A02ICST2	1100	23.588	0.01	1887.44	0.200	0.059	34,529	0.059	
CACTUSA	1042	23.675	0.01	1887.54	0.016	0.002	1,610	0.002	
TOPSTEST	329	75.068	0.00	1887.44	0.007	0.000	0	0.000	
TOPCMIN	146	168.606	0.00	1887.45	0.007	0.000	0	0.000	
A02ICST3	64	383.456	0.00	1887.44	0.013	0.000	0	0.000	
TOPCDEM	43	570.890	0.00	1887.47	0.006	0.000	0	0.000	
CACTUSA2	33	744.517	0.00	1887.61	0.016	0.003	6	0.003	
TOPCDEV2	33	744.228	0.00	1887.44	0.003	0.000	0	0.000	
TOPCDEV4	31	791.670	0.00	1887.44	0.001	0.000	0	0.000	
CACMPQA	22	1115.366	0.00	1887.54	0.000	0.000	0	0.000	

Statistics Summary of File Usage

This report shows the CICS file usage statistics. In addition to standard parameters, the following keyword parameters are supported:

RECTYPE

The record type containing the SYSVIEW SMF data.

Default: 255

ORDERBY

Used to sort for the final report, which can be any combination of ID, USE, UPDATES, READNUPD, READUPDT, DELETES, ADDS, BROWSE, SPLITS, and TIME.

Default: USE D

TOP

Used to restrict the number of lines of output for each time interval.

Default: 99999999

DSNAME

Used to filter by data set name.

Default: * (an asterisk), which selects all data sets.

To create the CICS Statistics Summary report of file usage, use this FILESTAT code.

```
%FILESTAT
```

The sample CICS Statistics Summary report of file usage:

FILE ID	FILE USE	FILE UPDATES	FILE READNUPD	FILE READUPDT	FILE DELETES	FILE ADDS	FILE BROWSE	FILE SPLITS	FILE I/O TIME
PROTSYM	392,746	0	392,746	0	0	0	0	0	0.09
IDSTA0BJ	66,530	0	55,500	0	0	11,030	0	0	0.18
IDSTASRC	55,473	0	44,846	0	0	10,627	0	0	0.03
ADROUT	12,964	0	4,855	0	0	8,109	0	0	0.13
ADRLIB	5,961	0	5,961	0	0	0	0	0	0.17
IDDVW	4,474	0	4,342	0	0	132	0	0	0.38
IDDAT	4,367	0	3,514	0	0	853	0	0	0.01
ENMAP30	3,539	0	1,010	0	0	0	509	0	0.02
ADRPNL	1,273	0	1,273	0	0	0	0	0	0.01
IDSTAPNL	1,187	0	1,052	0	0	135	0	0	0.02
IDSASOBJ	62	0	62	0	0	0	0	0	0.04
MP3TMP1	55	0	3	0	42	10	0	0	0.00
IDSASPNL	17	0	17	0	0	0	0	0	0.02
MP3TMP3	13	0	0	0	12	1	0	0	0.02
MP3TMP2	11	0	0	0	11	0	0	0	0.01

Transaction Range Summary

This report shows the CICS transaction usage by lifetime. In addition to standard parameters, the following keyword parameter is supported:

RECTYPE

The record type containing the SYSVIEW SMF data.

Default: 255

To create the CICS Transaction Range report, use this TRANRANG code:

```
LIST OFF
```

```
%TRANRANG EACH HOUR
```

The sample CICS Transaction Range report:

2008/05/20 08:08 CA SYSVIEW CICS Transaction Range Summary													PAGE 1	
From: 2008/03/04 08:57 Each: HOUR														
To: 2008/03/05 07:32 Shift: 00:00 24:00														
DATE	TIME	TRAN USE	TRAN RATE	TRAN USE 0-1 SEC	% USE 0-1	TRAN USE 1-3 SEC	% USE 1-3	TRAN USE 3-5 SEC	% USE 3-5	TRAN USE 5-10 SEC	% USE 5-10	TRAN USE 10+ SEC	% USE 10+	
2008/03/04	09:00	136	.03	100	73.5	27	19.8	0	0.0	2	1.4	7	5.1	
2008/03/04	10:00	2,581	.71	2,217	85.8	227	8.7	37	1.4	28	1.0	72	2.7	
2008/03/04	11:00	3,786	1.05	3,140	82.9	383	10.1	71	1.8	59	1.5	133	3.5	
2008/03/04	12:00	1,720	.47	1,479	85.9	111	6.4	30	1.7	40	2.3	60	3.4	
2008/03/04	13:00	2,747	.76	2,316	84.3	231	8.4	58	2.1	64	2.3	78	2.8	
2008/03/04	14:00	3,184	.88	2,898	91.0	149	4.6	25	0.7	45	1.4	67	2.1	
2008/03/04	15:00	5,224	1.45	4,669	89.3	271	5.1	69	1.3	101	1.9	114	2.1	
2008/03/04	16:00	1,337	.37	1,123	83.9	143	10.6	12	0.8	19	1.4	40	2.9	

User Summary

This report shows the CICS user summary report. In addition to standard parameters, the following keyword parameter is supported:

RECTYPE

The record type containing the SYSVIEW SMF data.

Default: 255

To create the CICS User Summary report, use this USERSTAT code:

```
LIST OFF
%USERSTAT
```

The sample CICS User Summary report:

USER ID	TRAN COUNT	TRAN ID	TRAN MAX LIFE	TRAN AVG LIFE	TRAN AVG CPU
2008/05/20 08:08 CA SYSVIEW CICS User Summary Report PAGE 1					
From: 2008/03/04 08:57 Each: DAY					
To: 2008/03/05 07:32 Shift: 00:00 24:00					
Interval Start: 2008/03/04 00:00					
ACCTCONN	404	TWBA	1238.391	4.181	0.049
	429	VTAT	0.002	0.000	0.000
	833			2.028	0.024
ADHPU01	1	IS31	0.152	0.152	0.015
	55	IS91	0.331	0.023	0.003
	2	SCFD	0.300	0.151	0.010
	25	S041	0.408	0.046	0.004
	1	STAR	0.872	0.872	0.058
	84			0.044	0.004
ADROPS	1	IDLX	0.136	0.136	0.010
	3	SCFD	0.279	0.137	0.018
	4			0.137	0.016
ALLTR01	1	CESF	0.382	0.382	0.002
	18	DQIN	0.677	0.153	0.006
	1	DQRY	0.119	0.119	0.003
	3	IDLX	1.180	0.464	0.021
	5	SAST	14.347	10.221	1.211
	902	SCFD	3.784	0.043	0.004
	930			0.101	0.011

IMS Canned Reports

This section shows the IMS sample reports and the code that was used to produce them.

Note: The IMS canned reports require CA SYSVIEW Option for IMS collected data.

Transaction Summary

This report shows the IMS transaction usage by program. In addition to standard parameters, the following keyword parameter is supported:

IMSID

The target IMS subsystem.

To create the IMS Transaction Summary report, use this IMSMRA02 code:

```
LIST OFF
%IMSMRA02 IMSID=SVP9
```

The sample IMS Transaction Summary report:

ADMINISTRATOR APPLICATION	TRANSACTION CODES	PROGRAM NAME	TRANSACTION COUNT	AVG D.B. CALLS PER TRANSACTION	TOTAL TRANSACTION D.B. CALLS	AVG. MRR SECONDS PER TRANSACTION	AVG. CPU SECONDS
AD	ADDPART	DFSSAM04	1	2	2	0.077733	0.002369
AD	***		1	2	2	0.077733	0.002369
IV	IVTNV	DFSIVP2	87		83	48.550905	0.000505
IV	***		87		83	48.550905	0.000505
PA	PART	DFSSAM02	11	1	13	0.261262	0.008001
PA	***		11	1	13	0.261262	0.008001
	TOTAL		99		98	42.695761	0.001357

MVS Reports

This section shows the MVS sample reports and the code to produce them.

Address Space Statistics

This report shows the MVS Address Space Performance report. This report requires SMF 70 records.

To create the Address Space Statistics report, use this ASCBSTAT code:

```
LIST OFF
%ASCBSTAT EACH HOUR
```

The sample Address Space Statistics report:

2008/05/20 08:08 CA SYSVIEW Address Space Statistics												PAGE 1	
From:		2008/03/25 06:23		Each:		HOUR							
To:		2008/03/29 09:57		Shift:		00:00 24:00							
Interval	AVG READY	MAX READY	AVG IN	MAX IN	AVG OUT	MAX OUT	AVG WAIT	MAX WAIT	AVG BATCH	AVG STC	AVG TSO	MAX TSO	
2008/03/25 06:00	19.1	143	253.6	267	0.0	2	38.6	41	84.1	252.2	26.1	28	
2008/03/25 07:00	36.9	179	263.4	281	0.0	3	35.7	37	89.8	248.8	32.3	36	
2008/03/29 08:00	1.7	18	109.7	127	0.0		0.0		7.4	255.6	19.9	36	
2008/03/29 09:00	1.7	26	140.0	154	0.0	3	0.0		14.6	270.3	54.0	68	

Device Activity

This report shows the Device Activity statistics. This report requires SMF 74 records. In addition to standard parameters, the following keyword parameters are supported:

ORDERBY

Orders the variables for sorting for the final report, which can be any combination of DEVNUM, SSCH.

Default: SSCH D

TOP

Restricts the number of lines of output for each time interval.

Default: 99999999

To create the Device Activity report, use this DEVSTAT code:

```
LIST OFF
%DEVSTAT TOP 30
```

The sample Device Activity report:

DEVICE ID	DEVICE SSCH	SSCH RATE	DEVICE SERVTIME	DEVICE CONNECT	DEVICE PENDING	DEVICE DISC	DEVICE %BUSY	DB DELAY
A010	588,583	6.81	0.88	0.12	0.13	0.63	0.60	0.00
2679	567,973	6.57	1.13	0.65	0.45	0.03	0.75	0.00
2365	402,651	4.66	1.52	1.21	0.22	0.10	0.71	0.00
211A	309,333	3.58	0.79	0.51	0.25	0.04	0.28	0.00
2E32	230,613	2.67	2.27	2.00	0.19	0.08	0.61	0.01
2136	222,787	2.58	1.42	1.16	0.21	0.05	0.37	0.00
23D7	191,446	2.22	2.27	2.02	0.21	0.04	0.50	0.00
90D2	108,141	1.25	49.34	0.02	0.51	48.80	6.18	0.00
90D3	108,003	1.25	0.83	0.18	0.50	0.15	0.10	0.00
9031	88,287	1.02	1.71	0.26	0.48	0.97	0.18	0.00
23ED	85,647	0.99	3.43	3.13	0.21	0.09	0.34	0.00
2E4F	79,565	0.92	1.03	0.70	0.17	0.17	0.10	0.00
2366	77,257	0.89	1.84	1.56	0.20	0.08	0.16	0.00
2447	74,320	0.86	2.44	1.97	0.39	0.08	0.21	0.05
A011	70,286	0.81	1.88	0.37	0.34	1.18	0.15	0.00
2E1E	63,606	0.74	1.90	1.60	0.20	0.10	0.14	0.01
28C1	44,182	0.51	1.82	0.70	0.27	0.85	0.09	0.00
200E	43,367	0.50	1.21	0.43	0.76	0.02	0.06	0.01
2E30	35,428	0.41	0.53	0.26	0.23	0.04	0.02	0.03
2105	31,546	0.37	1.40	0.91	0.21	0.27	0.05	0.00
3400	27,140	0.31	0.55	0.00	0.55	0.00	0.02	0.00
3425	27,140	0.31	0.49	0.00	0.49	0.00	0.02	0.00
24AC	24,079	0.28	1.09	0.54	0.22	0.33	0.03	0.00
26C0	22,031	0.25	1.57	0.84	0.45	0.28	0.04	0.00
2D83	21,677	0.25	0.57	0.29	0.26	0.03	0.01	0.00
2054	21,616	0.25	5.05	4.75	0.24	0.07	0.13	0.00
2363	20,955	0.24	0.88	0.65	0.19	0.03	0.02	0.00
2808	19,495	0.23	1.28	0.76	0.26	0.27	0.03	0.00
23F6	19,414	0.22	5.91	5.52	0.21	0.17	0.13	0.01
2E8D	19,183	0.22	1.09	0.80	0.24	0.05	0.02	0.01

Disk Device Activity

This report shows the disk device activity statistics and requires SMF 74 records. Both standard and the following keyword parameters are supported:

ORDERBY

Orders the variables for sorting for the final report, which can be any combination of VOLSER, SSCH.

Default: SSCH D

TOP

Restricts the number of lines of output for each time interval.

Default: 99999999

VOLSER

Filters by volume.

Default: * (an asterisk), which selects all volumes.

To create the Disk Device Activity report, use this DISKSTAT code:

```
LIST OFF
%DISKSTAT TOP 30
```

The sample Disk Device Activity report:

2008/05/17 11:28 CA SYSVIEW Disk Device Activity									
From: 2008/03/25 06:23 Each: DAY									
To: 2008/03/29 09:57 Shift: 00:00 24:00									
Interval: 2008/03/25 00:00									
PAGE 1									
VOLSER	DEVICE	SSCH	SSCH	RATE	DEVICE	DEVICE	DEVICE	DEVICE	DB
ID	SSCH	RATE	SERVTIME	CONNECT	PENDING	DISC	%BUSY	DELAY	
DCMQAD	567,973	6.57	1.13	0.65	0.45	0.03	0.75	0.00	
DCMQAA	402,651	4.66	1.52	1.21	0.22	0.10	0.71	0.00	
MVCA44	309,333	3.58	0.79	0.51	0.25	0.04	0.28	0.00	
RTM002	230,613	2.67	2.27	2.00	0.19	0.08	0.61	0.01	
DCMQAC	222,787	2.58	1.42	1.16	0.21	0.05	0.37	0.00	
LOAN02	191,446	2.22	2.27	2.02	0.21	0.04	0.50	0.00	
LOAN04	85,647	0.99	3.43	3.13	0.21	0.09	0.34	0.00	
S16DB2	79,565	0.92	1.03	0.70	0.17	0.17	0.10	0.00	
DCMQAB	77,257	0.89	1.84	1.56	0.20	0.08	0.16	0.00	
MVR14A	74,320	0.86	2.44	1.97	0.39	0.08	0.21	0.05	
MVS010	63,606	0.74	1.90	1.60	0.20	0.10	0.14	0.01	
SPL44D	44,182	0.51	1.82	0.70	0.27	0.85	0.09	0.00	
CTL022	43,367	0.50	1.21	0.43	0.76	0.02	0.06	0.01	
RTM001	35,428	0.41	0.53	0.26	0.23	0.04	0.02	0.03	
SPL44T	31,546	0.37	1.40	0.91	0.21	0.27	0.05	0.00	
NMD031	24,079	0.28	1.09	0.54	0.22	0.33	0.03	0.00	
SPL44C	22,031	0.25	1.57	0.84	0.45	0.28	0.04	0.00	
CAT036	21,677	0.25	0.57	0.29	0.26	0.03	0.01	0.00	
LOAN37	21,616	0.25	5.05	4.75	0.24	0.07	0.13	0.00	
DCMSPD	20,955	0.24	0.88	0.65	0.19	0.03	0.02	0.00	
SPL44B	19,495	0.23	1.28	0.76	0.26	0.27	0.03	0.00	
LOAN05	19,414	0.22	5.91	5.52	0.21	0.17	0.13	0.01	
APCM06	19,183	0.22	1.09	0.80	0.24	0.05	0.02	0.01	
DCMSPA	18,945	0.22	0.57	0.31	0.24	0.03	0.01	0.00	
APCD08	15,756	0.18	2.23	1.95	0.21	0.07	0.04	0.00	
LOAN10	12,626	0.15	5.75	5.07	0.64	0.04	0.08	0.00	
AUTM04	10,952	0.13	1.60	1.06	0.19	0.34	0.02	0.00	
APCM04	10,442	0.12	1.73	0.89	0.18	0.66	0.02	0.00	
JESCK5	10,071	0.12	2.16	1.88	0.25	0.03	0.03	0.00	
APCM03	9,871	0.11	0.86	0.53	0.20	0.13	0.01	0.00	

Non-VSAM Data Set Activity

This report shows the MVS data set activity and requires SMF 14 records. Both standard and the following keyword parameters are supported:

ORDERBY

Orders the variables for sorting for the final report, which can be any combination of DSNNAME, EXCP, INPUT, or OUTPUT.

Default: EXCP D

TOP

Restricts the number of lines of output for each time interval.

Default: 99999999

DSNAME

Filters by data set name.

Default: * (an asterisk), which selects all data sets.

To create the Non-VSAM Data Set Activity report, use this DSNSTAT code:

```
%DSNSTAT TOP 30
```

The sample report:

Dataset Name	Total EXCP	Input EXCP	Output EXCP
APCDAL.BMS.CKPT	34,405,362	34,403,742	1,620
SYSPROG.OPSMVS.USER.REXX	1,359,545	1,359,545	0
DCMQA.QAMUFM.A01797	482,262	0	482,262
DCMQA.STEPLIB.CAILIB	158,702	158,702	0
DIST.CAGJG0.SRCLIB	155,920	155,920	0
DCMQA.QAMUFM.LXX	104,537	0	104,537
DCMQA.PROCLIB	86,130	86,130	0
MEN.C5100.DOMCA01.P3300445.SVCDUMP	59,499	59,140	359
DCMQA.QAMUFM.IXX797	50,234	0	50,234
RTM.QA.SYSV771.PARMLIB	45,278	45,278	0
APCMTL.JSKVIEW.SARDBASE.D0000001	33,875	0	33,875
SYS1.SMFDATA.MS032504.T0624A1	27,073	0	27,073
SYS1.SMFDATA.MS032504.T0624P1	27,073	0	27,073
RTM.QA.SYSV771.PROFILE	26,053	26,053	0
DCMQA.QAMUFM.IXX796	23,519	0	23,519
OPSQL.OPST.CPM.REXX	21,603	21,603	0
DCMQA.QAMUFM.IXX795	18,654	0	18,654
BST.SASCDEV.LINKLIB	14,415	14,415	0
APCMTL.SITA.FOPS.VPS2SP10.CNTL	13,999	13,999	0
DCMQA.QAMUFM.IXX794	13,294	0	13,294
DCMQA.QA10.CICSTEST.JCL	11,226	5,932	5,294
DCMQA.QAMUFM.CXX	10,471	0	10,471

Paging Statistics

This report shows the MVS paging statistics. This report requires SMF 71 records.

To create the Paging Statistics report, use this PAGESTAT code:

```
%PAGESTAT EACH HOUR
```

The sample Paging Statistics report:

2008/05/20 08:15 CA SYSVIEW Paging Statistics												PAGE	1
From:		2008/03/25 06:23		Each:		HOUR							
To:		2008/03/29 09:57		Shift:		00:00 24:00							
Interval	PAGE IN	PAGE OUT	PAGE RECLM	VIO IN	VIO OUT	SWAP IN	SWAP OUT	PAGE MOVE	PAGE MOVEX	MIN UIC	MAX UIC	AVG UIC	
2008/03/25 06:00	1.08	21.50	0.00	0.00	0.00	0.08	0.00	13.66	0.00	2030	2540	1886.1	
2008/03/25 07:00	2.82	2.88	0.00	0.00	0.00	0.08	0.00	26.23	0.00	2540	2540	1903.6	
2008/03/29 08:00	1.40	0.00	0.00	0.00	0.00	0.00	0.00	10.94	0.00	320	1970	528.5	
2008/03/29 09:00	1.79	37.00	0.00	0.00	0.00	0.55	0.55	37.92	0.00	1970	2540	1855.3	

Swap Statistics

This report shows the MVS paging statistics. This report requires SMF 71 records.

To create the Swap Statistics report, use this SWAPSTAT code:

```
LIST OFF
%SWAPSTAT
```

The sample Swap Statistics report:

2008/05/20 08:09 CA SYSVIEW Swap Statistics								PAGE	1
From:		2008/03/25 06:23		Each:		DAY			
To:		2008/03/29 09:57		Shift:		00:00 24:00			
Interval Start: 2008/03/25 00:00									
Swap Reason	Swap Count	Swap Rate	Swap P-AUX	Swap L-AUX	Swap P-EXT	Swap L-EXT	Swap Migrate		
TERMINAL OUTPUT WAIT	196	0.00	0	0	0	0	0		
TERMINAL INPUT WAIT	5,660	0.07	0	0	0	0	0		
LONG WAIT	654	0.01	0	0	0	0	0		
DETECTED WAIT	2,104	0.02	0	0	0	0	0		
EXCHANGE ON RECOMMENDATION VAL	1	0.00	0	0	0	0	0		
UNILATERAL	29	0.00	0	0	0	0	0		
TRANSITION TO NON-SWAPPABLE	341	0.00	0	0	0	0	0		

WebSphere MQ Reports

This section shows the WebSphere MQ sample reports and the code to produce them.

Buffer Manager Statistics

This report shows the WebSphere MQ buffer pool usage statistics. This report requires SMF 115 records. In addition to the standard parameters, the following keyword parameter is supported:

SUBSYS

Specifies a target queue manager. The default is CSQ1.

To create the WebSphere MQ Buffer Pool Usage report, use this WMQBUFFU code:

```
LIST OFF
%WMQBUFFU
```

The sample WebSphere MQ Buffer Pool Usage report:

Buffer Pool Usage Report								PAGE	1
Buffer Pool	Interval Start Date	Interval Start Time	Buffer Util %	Total Buffers	Lowest Available	No Buffers Available	Stealable Buffers	Dasd Writes	Dasd Reads
0	2008/04/14	08:15:07		50000	49961		49963	8	
	2008/04/14	08:45:11		50000	49963		49963		
1	2008/04/14	08:15:07	11	1050	719		932	59	
	2008/04/14	08:45:11	12	1050	915		915		11
2	2008/04/14	08:15:07		1050	1049		1049	1	
	2008/04/14	08:45:11		1050	1049		1049		
3	2008/04/14	08:15:07		1050	1049		1049	1	
	2008/04/14	08:45:11		1050	1049		1049		

Log Manager Statistics

This report shows the WebSphere MQ log manager statistics. This report requires SMF 115 records. In addition to the standard parameters, the following keyword parameter is supported:

SUBSYS

Specifies a target queue manager.

Default: CSQ1

To create the WebSphere MQ Log Manager report, use this WMQLOGR code:

```
LIST OFF
%WMQLOGR
```


The sample Log Manager report:

Log Manager Report							PAGE	1
Interval Date	Interval Time	Suspend Count	Read Hits	Read Actives	Read Archives	Write Page-Ins	MAXRTU Delayed	LOGLOAD Checkpoint
2008/04/14	08:15:07	1	123	5	0	0	0	1
2008/04/14	08:45:11	0	34	1	0	0	0	0
2008/04/14	09:00:07	0	154	1	0	0	0	0
2008/04/14	09:15:11	2	24	0	0	5	0	0

Report Structure

The following example code for the ABENDSUM canned report is based on the provided macros and shows the structure of a CA Easytrieve program. Most of the comments in this example were removed for brevity.

Note: The line numbers that are shown on some lines match the explanation section, but are not part of the program.

```

1  MACRO @ EACH 'DAY'          +
      SHIFT '00:00 24:00'    +
      FROM 'ALL'             +
      TO 'ALL'               +
      RECTYPE 255
2  %SYSVDEFINE RECTYPE &RECTYPE +
      EACH '&EACH'           +
      FROM '&FROM'           +
      TO '&TO'               +
      SHIFT '&SHIFT'         +
      SEGMENT EXPCRABS
3  JOB INPUT SMFIN START SET-PARMS
4  PERFORM SELECT-REC.
      IF SELECTED = 'T'
5  %SYSVFOR EXPCRABS ABENDS
      END-IF
6  %SYSVPROC. *Common subroutines

7  REPORT ABENDS PRINTER REPORTS SUMMARY SUMCTL DTLCOPYALL +
      SPACE 2 NOADJUST LONGDATE
      SEQUENCE TITLE-TSTAMP MNS_TRAN ABS_ABNDPGM ABS_ABNDCODE
      CONTROL FINAL NOPRINT TITLE-TSTAMP NEWPAGE NOPRINT MNS_TRAN NOPRINT +
      ABS_ABNDPGM NOPRINT ABS_ABNDCODE
      TITLE 1 '          Sysview CICS Program ABEND Summary'
      TITLE 2 'From:          ' LOW-STAMP ' Each:      &EACH'
      TITLE 3 'To:          ' HIGH-STAMP ' Shift:    &SHIFT'
      TITLE 4 'Interval Start:' TITLE-TSTAMP
      HEADING MNS_TRAN ('TRAN' '----')
      HEADING ABS_ABNDPGM ('PROGRAM' '-----')
      HEADING ABS_ABNDCODE ('CICS' 'ABEND CODE' '-----')
      HEADING ABS_ABNDCOD ('SYSTEM' 'ABEND CODE' '-----')
      HEADING TALLY ('COUNT' '-----')
      LINE MNS_TRAN ABS_ABNDPGM ABS_ABNDCODE TALLY

```

The following explanations correspond to the line numbers in the preceding example:

1. This section of the code defines the ABENDSUM program as a macro so that parameters can be specified easily when the program is run. This example has no positional parameters, and five keyword parameters (EACH, SHIFT, FROM, TO, and RECTYPE), each with a default value.

The following examples show how to invoke this macro:

```
%ABENDSUM
%ABENDSUM EACH HOUR
```

2. This section invokes the SYSVCDEF macro. This macro:

- Includes the definitions of:
 - All the CA SYSVIEW SMF record types
 - Some related MVS and RMF record types
- Sets global variables that are referenced in the common subroutines.

The SEGMENT parameter identifies the primary data segment to use for the report.

3. This line begins the extraction section. The JOB statement defines and initiates processing activities as follows:

INPUT SMFIN

The INPUT parameter identifies the SMFIN input file.

START SET-PARMS

The START parameter runs the SET-PARMS subroutine, which initializes the selection criteria.

4. This PERFORM statement runs the SELECT-REC subroutine for each record in the input file. This subroutine performs common selection and filtering. If you want to process the record, set the variable SELECTED to T (true); otherwise it is set to F (false).
5. This line issues a PRINT statement for each EXPCRABS segment in the current record.
6. This line includes common subroutine definitions.
7. This section defines the output report.

Macros

The canned reports are constructed from several macros that provide common functionality. These macros help you eliminate duplicated effort and are described in the following sections.

SYSVCDEF Macro

The SYSVCDEF macro provides common definitions for global variables that various utility macros and subroutines use. SYSVCDEF includes the SMF record definitions that the canned reports require. Invoke it as the first noncomment statement in the CA Easytrieve program.

The SYSVCDEF macro supports the following keyword parameters:

EACH

Determines the length of each reporting interval. The SELECT-BY-TIME subroutine of the SYSVPROC macro uses this parameter to set the TSTAMP value for each SMF record. For most reports, SMF data is aggregated for each reporting interval. Specify one of the following values:

***n* DAY**

Reporting interval is *n* days.

MONTH

Reporting interval is one month.

***n* HOUR**

Reporting interval is *n* hours.

***n* MIN**

Reporting interval is *n* minutes.

RECORD

Set the TSTAMP value for each SMF record set to the actual timestamp, without adjustment. In practice, this value prevents data aggregation.

Default: DAY

FROM

Determines the starting timestamp for SMF record selection. The SELECT-PROC subroutine uses this value to exclude SMF records which have timestamps earlier than the provided value. The timestamp is specified as YYYY/MM/DD-HH:MM.

Default: ALL, which allows all records to be selected.

PRODUCT

Indicates the name of the product that produced the SMF records. This name is used to filter the SMF records. Typically, the SEGMENT specification automatically sets this value.

Default: Null string, ""

RECSTYPE

Specifies the SMF record subtype that contains the desired data. Typically, the SEGMENT specification automatically sets this value.

Default: 0

RECTYPE

Specifies the SMF record type for the SYSVIEW IMS records. The SEGMENT specification automatically sets this value when SEGMENT is the name of a section in a standard MVS or RMF record.

Default: 255

SEGMENT

Indicates the name of the primary data segment type to extract. SEGMENT is used to:

- Determine RECTYPE and RECSTYPE when appropriate
- Set up variables that can be used for stepping through the segments with the SYSVFOR macro

Default: Null string, "

SHIFT

Determines the time range for selecting data. The SELECT-PROC subroutine uses SHIFT to exclude SMF records that do not fall within the specified time range. The range is specified as h1:m1 h2:m2.

- h1:m1 is the starting time for the shift.
- h2:m2 is the ending time for the shift.
- If h1:m1 is greater than h2:m2, then two time ranges are assumed: h2:m2 24:00, and 00:00 h1:m1.

Default: 00:00 24:00

SUBSYS

Indicates the name of the subsystem that produced the SMF records. SUBSYS is used to filter the SMF records. Typically, SUBSYS is set automatically from the SEGMENT specification.

Default: Null string, "

TO

Determines the ending timestamp for SMF record selection. The SELECT-PROC subroutine uses TO to exclude SMF records that have timestamps later than the provided value. The timestamp is specified as YYYY/MM/DD-HH:MM.

Default: ALL, which allows all records to be selected.

SYSVPROC Macro

The SYSVPROC macro defines common subroutines for selecting and filtering records and data segments. Invoke SYSVPROC after the first JOB statement, and before the first REPORT statement. The following subroutines are provided:

SELECT-BY-TIME

Filters the SMF records by the record timestamp. Any record that does not satisfy the FROM, TO, and SHIFT parameters is rejected by setting the SELECT variable to F.

SELECT-REC

Performs the standard record selection by using the values set previously through the SYSVDEF macro and the SET-PARMS subroutine. Upon return from the routine, the SELECT variable has a value of T if the record passes all filtering criteria, otherwise the value is F.

Specifically, the routine verifies that SMFRTYP, SMFRSTYP, SMFHSSI, and SMFHPROD match the corresponding values for RECTYPE, RECSTYPE, SUBSYS, and PRODUCT.

The routine also calls SELECT-BY-TIME to verify that the record timestamp is within the time ranges specified in the FROM, TO, and SHIFT parameters.

SET-OFFSETS

Sets the addressability to the various record definitions, which are based on RECTYPE, RECSTYPE, SMFRTYP, SMFRSTYP, and SEGMENT.

SELECT-BY-TIME calls SET-OFFSETS, and is not typically named directly from a user program.

SET-PARMS

Decodes the standard parameters that are specified on the SYSVDEF macro. The values are then inserted into global variables that are accessible to the various filtering and selection routines and macros.

SET-PARMS is typically invoked as the START procedure on a JOB statement, but can also be invoked directly at any time using a PERFORM statement.

SET-SMFTIME

Examines the SMF record timestamps to determine the lowest and highest timestamp found in the data.

Because SET-SMFTIME is an internal subroutine, it typically is not invoked directly from a user program.

SPLIT-PARM

Splits a parameter into two parts, delimited by the first blank.

Because SPLIT-PARM is an internal subroutine, it typically is not invoked directly from a user program.

FILTERID Macro

The FILTERID macro filters on an alphanumeric field.

This macro supports the following three positional parameters:

FAIL

Specifies the name of a label for branching to when PAT is not matched.

PAT

Specifies the pattern for matching. The pattern is a text string to match against the content of VAR. Each position of VAR is matched against PAT, until a mismatch is found, or until a blank is found in VAR.

- The asterisk (*) in PAT matches the rest of VAR.
- The question mark (?) matches any single character.

VAR

Specifies the name of the field or variable to filter.

Example: FILTERID Macro

In this example, all remaining processing in the current JOB is skipped if the value of SMF74SER does not begin with TSO.

```
%FILTERID SMF74SER 'TSO*' JOB
```

In this example, processing jumps to the SKIPIT label if the value of SMF74SER does not end in 01.

```
%FILTERID SMF74SER '????01' SKIPIT
```

SMFDATE Macro

The SMFDATE macro converts a binary 8-byte SMF timestamp into a numeric date using the YYYYMMDD format.

This macro supports two positional parameters:

DATEOUT

8-byte numeric, typically defined as follows:

```
8 N MASK(9999/99/99)
```

SMFTOD

SMF timestamp, usually SMFHTOD

SMFTIME Macro

The SMFTIME macro converts a binary 8-byte SMF timestamp into a numeric time using the HHMMSS format.

This macro supports two positional parameters:

SMFTOD

SMF timestamp, typically SMFHTOD

TIMEOUT

8-byte numeric, typically defined as follows:

8 N MASK(99:99:99)

STCKCONV Macro

The STCKCONV macro converts data between a binary STCK timestamp and its 19-byte character representation as YYYY/MM/DD HH:MM:SS.

This macro supports three parameters:

BINSTAMP

Name of the BIN variable, which is defined as 8 A.

CHARSTAMP

Name of the CHAR variable, which is defined as 19 A.

FORMAT

Type of conversion desired:

B

Convert from CHAR to BINARY

C

Convert from BINARY to CHAR

SYSVFOR Macro

The SYSVFOR macro generates a report line for each instance of a segment type within the current SMF record.

This macro supports two explicit arguments:

SEGN

Name of the desired segment

RPTN

Name of the report to generate

Before you invoke this SYSVFOR macro, set the following global variables in the SET-OFFSETS subroutine, which are invoked internally through the SELECT-REC and SELECT-BY-TIME subroutines.

SEG_COUNT

Sets the number of segments in the record.

SEG_LEN

Sets the length of the segment type.

SEG_OFFSET

Sets the offset within the SMF record to the first byte of the first segment. Calculate the offset from SMFHSI, which is the first byte following the RDW.

For SMF records, such as SYSVIEW CMCR that provides “triplets” containing offsets relative to the RDW, set the SEG_OFFSET to four less than the provided value. The SELECT-REC subroutine code in macro SYSVPROC does this set for each of the segment types defined in any of the provided SMF record types.

This following macro steps through all of the SMF74B segments and issues PRINT EXTRACT for each such segment found.

```
%SYSVFOR SMF74B EXTRACT
```

TOP Macro

The TOP macro restricts report output to the first *n* lines in each control-break. Use it in any report that does not already have a REPORT-INPUT procedure.

This macro supports two positional parameters:

FIELD

Name of the control-break field, which is typically the timestamp for interval reporting and typically named T_TSTAMP.

The maximum length of the field is 44.

TOP

Number of lines to include in each control group.

Example: TOP Macro:

```
%TOP TSTAMP 20
```

SMF Record Descriptions

The following macros contain CA Easytrieve definitions of SMF record types:

SMFHDR

Common record header

SMFR14

Data set activity (types 14 and 15)

SMFR30

Job/step termination

SMFR64

VSAM data set activity

SMFR70

RMF type 70

SMFR71

RMF type 71

SMFR74

RMF type 74

IMSIMTR

The IMS Transaction record

IMSIMRA

The IMS Region Accounting record

CSMF027

SYSVIEW CICS Transaction Detail

CSMF008

SYSVIEW CICS Thresholds

CSMF025

SYSVIEW CICS Transaction Summary

CSMF028

SYSVIEW CICS System Interval Data

CSMF009

SYSVIEW CICS State Thresholds

CSMF024

CICS Exceptions

ZSMF003

SYSVIEW Threshold Exception Records

ZSMF004

SYSVIEW State Exception Records

Chapter 17: Creating Command Displays

This section contains the following topics:

[User-Defined Displays](#) (see page 205)

[How to Create Displays](#) (see page 206)

User-Defined Displays

CA SYSVIEW lets you create your own command displays that look-and-feel like any other CA SYSVIEW display. You can tailor the displays to the needs of your site. They can contain rows of text data, or can be formatted using extended attributes.

For more information, see the CA SYSVIEW online help topic [User Displays - RXDISP Formatting Extensions](#).

How to Create Displays

CA SYSVIEW lets users create their own CA SYSVIEW command displays. The display can be simple rows of text data, or can be formatted using extended attributes.

The user display supports:

- Extended attributes
- Help
- Line commands
- Selection
- Sorting

To create your displays, do the following steps:

1. Use REXX for building your new user command.
2. Use the control statement for letting the REXX EXEC embed statements to define a title, info lines, header lines, link fields, and so on.
3. Use the data queued to the REXX stack for creating the display.
4. Use the RXDISP command for invoking a REXX EXEC and display any returned output on the stack on a CA SYSVIEW screen.

Example: REXX EXEC Samples

The REXXLIB data set, SYSVIEW.CNM4BREX, contains the following REXX EXEC samples:

FILELIST

Provides a sample REXX EXEC for creating a display that contains a directory listing of multiple data sets.

LOAN

Provides a sample REXX EXEC for calculating loan payments.

Index

A

- access and control the displays • 113
- accessing profile displays • 69
- ACTIVITY command • 105
- adding a cataloged data set to the end of the list of LINKLIST data sets • 101
- ALERTS command • 95
- APF List display • 99
- APFLIST command • 99

B

- base components • 20
- busy percentage, for processor • 98

C

- CA Datacom • 31
- CA Datacom Option
 - performance statistics • 31
 - Toolkit and Utilities • 32
- CA Easytrieve Common Reporting Service
 - canned reports • 194
 - description • 175
- CA MIM component • 34
- CA Roscoe • 36
- canned reports
 - distribution of • 176
 - example • 194
 - keywords • 176, 177
 - sample output • 178
- CDSAS command • 130
- changing a display format • 79, 81
- channels, MQ • 138
- CICS
 - Active Tasks display • 129
 - address spaces currently being monitored • 127
 - administrative options • 27
 - CICS resources • 26
 - Degradation Analysis display • 133
 - Dynamic Storage Areas display • 130
 - historical data • 26
 - status information • 26
 - storage information • 26
 - System Activity display • 127
 - Transaction Log Summary display • 132

- CICSLIST command • 127
- column ruler line • 75
- columns, in display format • 74
- command facility • 18
- command line of a display
 - changing the placement of • 73
 - default format • 43
- commands
 - entering • 49
 - executed in the current ASID • 55
 - how long in effect • 55
- commas, separating parameters • 50
- components • 34
 - base • 20
 - CA MIM • 34
 - USS • 34
 - workload manager • 35
- CONSOLE command • 97
- Console display • 97
- controlling the displays • 113
- CPU command • 98
- cross-system
 - displaying capable commands • 171
 - displaying data • 169
 - monitoring resources • 167
- Cross-System Resource Monitoring • 16
 - displaying System Overview information • 36
- CTASKS command • 129
- CTRANLOG command • 132
- CWAITS command • 133

D

- DASD
 - command • 93
 - device status • 93
 - Units display • 93
- data collection and monitoring • 17
- data fields, changing on display screens • 84
- data on a display
 - changing the format for • 79
 - changing the name of a field • 82
 - changing the order of columns • 85
 - displaying particular rows • 88
 - excluding fields • 81
- DATACOM

- Directory Areas display • 150
- Directory Databases display • 152
- MUF Active Tasks display • 153
- MUF Identity display • 153
- PARMLIB member • 149
- System Activity display • 149
- DCAREAS command • 150
- DCDBASES command • 152
- DCLIST command • 149
- DCMUFS command • 153
- DCTASKS command • 153
- default format display
 - areas described • 43
 - command line • 43
 - divider lines • 44
 - header line • 46
 - information area • 46
 - parameter line • 46
 - status line • 45
 - title line • 43
- default parameters, specifying for a command in your profile • 78
- description • 15
- display
 - a list of line commands • 54
 - areas on the default display • 43
 - customizing • 90
- display format
 - changing • 72
 - changing for a command display • 79
 - default • 41
 - initial • 73
 - section of the general profile • 73
 - using one you have created • 82
- displays
 - job and output management • 105
 - system overview • 113
- Divider Line Character field • 74
- divider lines on a display • 44

E

Event Capture Option • 33

F

FIND command • 56
FINDHELP command • 60
fixed length masking character • 52, 78

H

header line of a display • 46
HELP command • 58
help, obtaining • 58

I

IMS

Dependent Region List display • 146
displays • 143
Exception Alerts display • 144
Option • 32
Pools display • 145
Subsystem List display • 143
Toolkit and Utilities • 33
IMSALERT command • 144
IMSLIST command • 143
IMSPOOLS command • 145
IMSREGNS command • 146
information area of a display • 46
initialization options • 73, 78
integration, with CA OPS/MVS • 18
interfaces • 19
ISPF key setting, changing • 77

J

JCL for writing reports • 176
JES option • 24
job and output management displays • 105
Job Queues display • 108
Job Summary display • 107
JOBSUM command • 107

K

keywords

- for the FIND command • 56
- for the SET command • 115, 169

L

level number on a display • 44
line commands, entering • 54
LINK command • 78
LINKLIST command • 100
Linklist Libraries display • 100
list line commands for a display • 54
LISTJOBS command • 108

M

macros for canned reports

- FILTERID • 199
- SMFDATE • 199
- SMFTIME • 200
- STCKCONV • 200
- SYSVCDEF • 196
- SYSVFOR • 201
- SYSVPROC • 196, 198
- TOP • 202

masking characters

- changing default characters • 52
- changing defaults • 78
- default • 51

MENU

- command • 40
- DATAKOM • 149
- JES command • 105

menus

- not available at your site • 40
- Primary Option Menu • 40
- structure • 39

message, deleting from the MVS console screen • 98

MIB Browser • 36

monitor cross-system resources • 167

MQ

- Channel Status display • 138
- Exception Alerts display • 137
- Local Queues display • 139
- Queue Manager display • 141
- Subsystem List display • 135

MQALERTS command • 137

MQCHSTAT • 138

MQLIST command • 135

MQMGR command • 141

MQLOCAL command • 139

MVS

- Exception Alerts display • 95
- resource displays • 93

O

omitting parameters • 51

online Help

- default PF key • 58
- obtaining • 58
- reference materials for the Options and Components • 62
- TOPICS command • 62

using the FINDHELP command in • 60

using the LOCATE command in • 64

using the PRINT command in • 63

Options • 20

JES • 24

system • 21

Options, list of • 20

P

parameter area of a display, typing over current value • 83

parameter line of a display, default format • 46

parameters

- entering • 50
- entering with PF keys • 53
- examples • 51
- masking characters • 51
- omitting • 51
- on the FIND command • 56

PF keys

- changing definitions for • 76
- changing definitions for each display • 77
- default settings • 49
- FIND • 57
- showing settings • 49

PF message lines field • 48, 76

PFSHOW command • 49

positional parameters • 51

Primary Option Menu • 40

PRINT command • 63, 91

PRINTER command • 110

Printers display • 110

printing • 91

Processor Information display • 98

profile

- acquiring settings from another user • 68
- changing • 68
- command • 71
- GENERAL • 71
- updating • 72

PROFILE command • 68

accessing displays • 70

options you can change • 71

Q

queue managers, MQ • 141

R

- realtime performance monitoring • 17
- RECALL command • 55
- record types • 202
- reports
 - canned • 176
 - creating • 175
- REVIEW command • 55
- rows and columns, in display format • 74

S

- SCM, overview • 36
- SCMSYS command • 163
- SCREEN command • 90
- Scroll field on a display • 43
- scrolling displays and commands • 48
- SELECT command • 88
- selection parameters, setting initial • 73
- separator area • 75
- SET CMDLINE TOP command • 73
- SET COLS command • 75
- SET command • 69
- SET FLM command • 78
- SET FORMAT command • 82
- SET PROFILE SAVE command • 72
- SET SEPCHAR command • 75
- SET SEPLINE command • 75
- SET VLM command • 78
- SMF record types • 202
- SORT command • 85
- sort parameters, setting initial • 73
- sorting data • 85
- spaces, separating parameters • 50
- status line of a display • 45
- storage, CICS • 130
- string, finding on a display • 56
- subcommands • 53
- SUBSYS command • 102
- Subsystem display • 102
- synonyms for commands • 68
- SYSLOG command • 111
- System Activity display • 105
- System Condition Monitor • 163
- System Configuration Options display • 126
- System Configuration Toolkit and Utilities • 23
- System Log display • 111
- System Overview component • 36
 - display fields • 118

- menu • 113

T

- TCP/IP
 - Connections display • 158
 - IP Devices display • 160
 - IP Users display • 157
 - MIB browser • 36
 - option • 33
 - Stacks display • 155
 - System Activity display • 155
- Threshold-based alerts • 18
- title line of a display • 43
- Toolkit and Utilities • 21
- TOPICS command • 62

U

- UNIX System Services (USS) • 34
 - Address Space List display • 123
 - displays • 123
 - Mounted File Systems display • 125
- user interface • 19
- USSLIST command • 123
- USYSCONF command • 126

V

- variable length masking character • 52, 78
- verifying data sets in the APF list • 100

W

- WebSphere MQ
 - Channel Status display • 138
 - Exception Alerts display • 137
 - Local Queues display • 139
 - Queue Manager display • 141
 - Subsystem List display • 135
- WebSphere MQ component
 - Channels • 29
 - Queue Managers • 29
 - Queues • 29
 - Toolkit and Utilities • 30
- Workload Manager component • 35
- writing reports
 - guidelines for • 175
 - sample JCL • 176

X

XSCMDS command • 171

XSCONN command • 168

XSLIST command • 168

Z

z/OS component

CA Roscoe • 36

System Overview • 36

UNIX System Services • 34

Workload Manager • 35

z/OS option • 21

JES • 24

JES resource definitions • 24

JES toolkit • 25

system resources monitored • 21

z/OS Toolkit • 23