

# **CA ARCserve® Backup for Windows**

## **Enterprise Module Guide**

**r15**



This documentation and any related computer software help programs (hereinafter referred to as the "Documentation") are for your informational purposes only and are subject to change or withdrawal by CA at any time.

This Documentation may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of CA. This Documentation is confidential and proprietary information of CA and may not be used or disclosed by you except as may be permitted in a separate confidentiality agreement between you and CA.

Notwithstanding the foregoing, if you are a licensed user of the software product(s) addressed in the Documentation, you may print a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all CA copyright notices and legends are affixed to each reproduced copy.

The right to print copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to CA that all copies and partial copies of the Documentation have been returned to CA or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, CA PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL CA BE LIABLE TO THE END USER OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF CA IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is CA.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2010 CA. All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

## CA Product References

This document references the following CA products:

- BrightStor® Enterprise Backup
- CA Antivirus
- CA ARCserve® Assured Recovery™
- CA ARCserve® Backup Agent for Advantage™ Ingres®
- CA ARCserve® Backup Agent for Novell Open Enterprise Server for Linux
- CA ARCserve® Backup Agent for Open Files on NetWare
- CA ARCserve® Backup Agent for Open Files on Windows
- CA ARCserve® Backup Client Agent for FreeBSD
- CA ARCserve® Backup Client Agent for Linux
- CA ARCserve® Backup Client Agent for Mainframe Linux
- CA ARCserve® Backup Client Agent for NetWare
- CA ARCserve® Backup Client Agent for UNIX
- CA ARCserve® Backup Client Agent for Windows
- CA ARCserve® Backup Enterprise Option for AS/400
- CA ARCserve® Backup Enterprise Option for Open VMS
- CA ARCserve® Backup for Microsoft Windows Essential Business Server
- CA ARCserve® Backup for Windows
- CA ARCserve® Backup for Windows Agent for IBM Informix
- CA ARCserve® Backup for Windows Agent for Lotus Domino
- CA ARCserve® Backup for Windows Agent for Microsoft Exchange Server
- CA ARCserve® Backup for Windows Agent for Microsoft SharePoint Server
- CA ARCserve® Backup for Windows Agent for Microsoft SQL Server
- CA ARCserve® Backup for Windows Agent for Oracle
- CA ARCserve® Backup for Windows Agent for Sybase
- CA ARCserve® Backup for Windows Agent for Virtual Machines
- CA ARCserve® Backup for Windows Disaster Recovery Option
- CA ARCserve® Backup for Windows Enterprise Module

- CA ARCserve® Backup for Windows Enterprise Option for IBM 3494
- CA ARCserve® Backup for Windows Enterprise Option for SAP R/3 for Oracle
- CA ARCserve® Backup for Windows Enterprise Option for StorageTek ACSLS
- CA ARCserve® Backup for Windows Image Option
- CA ARCserve® Backup for Windows Microsoft Volume Shadow Copy Service
- CA ARCserve® Backup for Windows NDMP NAS Option
- CA ARCserve® Backup for Windows Serverless Backup Option
- CA ARCserve® Backup for Windows Storage Area Network (SAN) Option
- CA ARCserve® Backup for Windows Tape Library Option
- CA ARCserve® Backup Patch Manager
- CA ARCserve® Backup UNIX and Linux Data Mover
- CA ARCserve® D2D
- CA ARCserve® High Availability
- CA ARCserve® Replication
- CA VM:Tape for z/VM
- CA 1® Tape Management
- Common Services™
- eTrust® Firewall
- Unicenter® Network and Systems Management
- Unicenter® Software Delivery
- Unicenter® VM:Operator®

# Contact CA

## Contact Technical Support

For your convenience, CA provides one site where you can access the information you need for your Home Office, Small Business, and Enterprise CA products. At [CA ARCserve Backup Support](#), you can access the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- CA Support policies and guidelines
- Other helpful resources appropriate for your product

## Provide Feedback

If you have comments or questions about CA product documentation, you can send a message to [techpubs@ca.com](mailto:techpubs@ca.com).

If you would like to provide feedback about CA product documentation, complete our short [customer survey](#), which is also available on the CA Support website, found at <http://ca.com/docs>.

## Documentation Changes

The following documentation updates have been made since the last release of this documentation:

- [Installation Prerequisites Exclusive for Enterprise Tape Library 3494](#) (see page 56)—updated to include details for 32-bit software.
- [Installation Prerequisites Exclusive for StorageTek ACSLS](#) (see page 60)—updated to include details for 32-bit software.

# Contents

---

<b>Chapter 1: Introducing the CA ARCserve Backup Enterprise Module</b>	<b>9</b>
Introduction to the Enterprise Module .....	9
Purpose of the Guide .....	10
<b>Chapter 2: Image Option</b>	<b>11</b>
Introducing the Image Option .....	11
How the Option Works .....	12
Backup Method .....	13
Installing the Image Option .....	13
Installation Prerequisites .....	13
Install the Image Option .....	14
Post-Installation Tasks .....	14
Using the Image Option .....	14
General Considerations .....	15
Backup Job Definition .....	15
Define Backup Jobs Using the Backup Manager .....	17
Image/Serverless Backup Option Dialog .....	18
View Job Status .....	19
Job Monitor Dialog .....	20
Restore Methods .....	22
Restore a Drive .....	23
Restore Individual Files .....	24
<b>Chapter 3: Serverless Backup Option</b>	<b>25</b>
Introducing the Serverless Backup Option .....	25
Backup Methods .....	25
Unsupported Functions .....	28
Operational Considerations .....	28
Installing the Serverless Backup Option .....	29
Installation Prerequisites .....	30
Install the Serverless Backup Option .....	30
Using the Serverless Backup Option .....	30
Define Backup Jobs Using the Backup Manager .....	31
Image/Serverless Backup Option Dialog .....	32
Restore Methods .....	33

---

<b>Chapter 4: Enterprise Tape Library 3494 and StorageTek Options</b>	<b>35</b>
Introducing Enterprise Tape Library 3494 and StorageTek ACSLS .....	36
Enterprise Tape Library IBM 3494 .....	37
StorageTek ACSLS .....	38
Option Architecture .....	38
Enterprise Tape Library 3494 .....	39
StorageTek ACSLS .....	45
Installing and Configuring .....	54
Installation Prerequisites .....	55
Installation Process .....	61
How Library Configuration Updating Works .....	71
Using Enterprise Tape Library 3494 and StorageTek ACSLS .....	74
Backup and Restore Operations .....	74
Detect Tape Volume Updates .....	75
Enterprise Tape Library 3494 Command Line Interface .....	75
StorageTek Tape Library Queries .....	76
<b>Appendix A: Troubleshooting</b>	<b>79</b>
Backup Process is Slow .....	79
Image Option: Drive Cannot be Frozen .....	80
Enterprise Tape Library 3494: Drives Cannot be Mapped to the Library .....	81
Serverless Backup Option: Drive Locking Problems .....	81
<b>Index</b>	<b>83</b>

# Chapter 1: Introducing the CA ARCserve Backup Enterprise Module

---

This section contains the following topics:

[Introduction to the Enterprise Module](#) (see page 9)

[Purpose of the Guide](#) (see page 10)

## Introduction to the Enterprise Module

CA ARCserve Backup is a distributed comprehensive storage solution for application, databases, distributed servers, and file systems. It provides backup and restore capabilities for databases, business-critical applications, and network clients.

The CA ARCserve Backup Enterprise Module (Enterprise Module) is a separately-installed component that includes the following options and features:

- Multistreaming: two or more streams of backup data.
- Disk staging backups and tape staging backups with multistreaming and transmit three to 32 streams of backup data.

**Note:** If you do not license the Enterprise Module, CA ARCserve Backup lets you transmit two streams of backup data for disk staging and tape staging backup jobs, and one stream for custom backup jobs. A "custom" job is a job that does not utilize a rotation schedule, a grandfather-father-son (GFS) rotation, or media pools. For more information, see the *Administration Guide*.

- Media Management Option.
- Raw backup and restore of physical disks and volumes.
- Enterprise Option for VSS Hardware Snap-Shot.
- Enterprise Option for IBM 3494.
- Enterprise Option for StorageTek ACSLS.
- Image Option.
- Serverless Backup Option.

**Note:** The license for the Enterprise Module is registered on the primary or the stand-alone CA ARCserve Backup server.

## Purpose of the Guide

The Enterprise Module Guide describes the following tasks:

- Executing backup and restore jobs using the CA ARCserve Backup Image Option.
- Executing backup and restore jobs using the CA ARCserve Backup Serverless Backup Option.
- Executing backup and restore jobs using IBM® TotalStorage® Enterprise Automated Tape Library 3494 and StorageTek Automated Cartridge System Library Software.

**Note:** For more information about using the Enterprise Option for VSS Hardware Snap-Shot, see the Agent for Microsoft Volume Shadow Copy Service Guide. For more information about using multistreaming, multiplexing, disk staging backups, the MM Admin, and Raw Backup and Restore, see the Administration Guide or the online help.

# Chapter 2: Image Option

---

This section contains the following topics:

[Introducing the Image Option](#) (see page 11)

[Installing the Image Option](#) (see page 13)

[Using the Image Option](#) (see page 14)

## Introducing the Image Option

CA ARCserve Backup offers the Image option, which backs up data at a high speed. The option bypasses the file system, creates a snapshot image of the drive, and reads data blocks from the disk. The option treats the entire drive like a single file, and replaces the traditional method of traversing the file system file-by-file.

The option provides device independence. It writes to any device supported by CA ARCserve Backup, including media devices, media libraries, and media RAID devices.

Using the CA ARCserve Backup Image Option, you can do the following:

- Scan files to optimize performance. During this process the drives are scanned, and the information about the files present on the drive is used to optimize backup and restore performance.
- Perform optimized image drive level backup and restore operations. When backing up and restoring at the drive level, the option bypasses the file system to optimize the process.
- Restore individual files as well as full drives. The option can restore data at the file level and at the drive level.
- Back up both Windows NT File System (NTFS) and File Allocation Table (FAT) file systems. In addition, back up NTFS with compressed and encrypted files, directories, and drives.
- Maintain all of the file information, such as file name, file size, date, and security.

## How the Option Works

The CA ARCserve Backup Image Option performs a backup job in two phases.


### 1. Scanning phase

The option collects information about all of the files on a drive including file name, file size, date, time, attributes, clusters used by the file, file security attributes, and any other information required to back up the file during the backup phase.

File Scanning is always enabled for FAT/FAT32. File scanning for NTFS is only done when Enable File Level Restore is selected from the Image/Serverless Backup Options dialog. The option still does a minimal scan of the drive to find the occupied drive spaces to back up.

### 2. Backup phase

The CA ARCserve Backup Image Option backs up data in this phase. The backup engine reviews the information from the scanning phase, and then streams the data as fast as possible on to the backup media.



## Backup Method

The CA ARCserve Backup Image Option backs up data by taking a snapshot of the drive at a specific point in time. Although the drive appears to be frozen at a particular time, it functions normally and lets other applications send read and write requests. This feature is known as the Snapshot feature, and it is automatically installed when you install the option.

This method has the following advantages:

- At the start of the backup process, the option does not attempt to lock the drive about to be backed up.
- If applications write to the drive while a backup operation is in progress, the integrity of the backup data is maintained at all times. The backup operation continues and is successful even when files are being written to during the backup process.

## Installing the Image Option

To install the Image option, you should be familiar with the characteristics and requirements of the specified Windows operating systems, and with administrator responsibilities on those operating systems.

### Installation Prerequisites

Before installing the option, verify the following:

- Your system configuration meets the minimum requirements needed to install the option.  
For a list of requirements, see the readme file.
- You have administrator privileges on the computers on which you want to install the option.
- You have the following applications installed and working properly:
  - CA ARCserve Backup
  - CA ARCserve Backup Enterprise Module

**Important!** You must install the Enterprise Module (which automatically includes this option) and CA ARCserve Backup on the same computer. This computer can be located either locally or remotely.

## Install the Image Option

The Image Option is installed locally when you install the Enterprise Module.

### To install and configure the option

1. Install and configure the option using the Enterprise Module Configuration utility (EMConfig.exe) during the post-installation process.  
**Note:** You can also access the EMConfig.exe utility from the Windows Start menu (click Start, All Programs, CA, ARCserve Backup, Enterprise Module Configuration).
2. Complete the installation and configuration procedure, and restart your computer when prompted.

## Post-Installation Tasks

You must complete two post-installation tasks before you start using the CA ARCserve Backup Image Option:

- Verify that the driver for the CA ARCserve Backup Image Option is loaded successfully by checking the registry key for the presence of the driver. An example of a registry key location is:  
`HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\hbmnt`
- After rebooting, check the Windows Event Viewer to ensure that the driver HBMNT5.SYS loaded successfully. The driver is installed in the following location:  
`[System Root]\System32\drivers\hbmnt5.sys`

## Using the Image Option

This section explains how you can use the CA ARCserve Backup Image Option Backup Manager to configure your backup jobs and restore data.

## General Considerations

To run successful backup and restore jobs, consider the following:

- Keep some empty space on the drive where the option is installed. Because the option creates logs and temporary files to enhance performance, it needs space on this drive. Ideally, 15-20 MB free space should be sufficient.
- To accommodate the Snapshot feature, the option creates a temporary storage file on a local drive that has the greatest amount of free space available. In addition to the 15-20 MB free space suggested in the previous point, you must have at least 20 MB free for the Snapshot feature.
- While restoring an active system drive, you must have at least 50 MB available on the drive. This amount of space is needed to store additional temporary files and registry files when you back up and restore data.

## Backup Job Definition

You can use the Backup Manager to configure and set up your backup jobs. You can back up an image only on a computer where CA ARCserve Backup and the option are both installed.

You can back up a partition to a File System Device. The File System Device can be on the same partition, but the backup job may fail if the other drives do not have sufficient disk space. We recommend that you have the File System Device on a different drive.

During backup, the Snapshot feature is required to freeze the drive. The drive is then synchronized, which means that it waits for a period when nothing is being written to the drive. If this write-inactivity period cannot be found, the synchronization times out after a specified time and the freeze request fails. The inactivity period is the number of seconds of inactivity on the drive before the drive is deemed safe to freeze.

To change the default registry value for SyncTimeout, InactivityPeriod, and PreviewFilename, you must create the following key and set the values for these parameters:

Software\ComputerAssociates\CA ARCserve Backup\Base\TapeEngine\Image

While SyncTimeout is 80 seconds by default, the Inactivity Period is 3 seconds by default.

If the registry contains a value and a key for PreviewFilename, the path name identifies the location of the preview file. If the file name is not specified, the path name identifies the volume that contains the most free space and is on a drive that is not being backed up. (If there is only one drive, the path name identifies the only drive). If the PreviewFilename specifies one or more subdirectories, the subdirectories will automatically be created.

**Note:** There is no attempt to validate the directory. During backup, if the directory cannot be accessed or created (usually due to an invalid volume), the backup job fails.

The global backup option, *Encryption* is not supported at this time.


## Define Backup Jobs Using the Backup Manager

You can use the Backup Manager to configure and set up your backup jobs.

### To configure and set up backup jobs

1. Open the Backup Manager and select the Source tab.  
All sources available for backup are listed in the left pane.
2. Right-click on a *computer* node listed in the Source tab of the Backup Manager and select Use Image/Serverless Backup Option.

The Image/Serverless Backup Options dialog opens.



3. Complete the fields in the dialog, and then click OK.
4. Right-click a *disk* node listed in the Source tab of the Backup Manager and select Use Image/Serverless Backup Option.

The Image/Serverless Backup Options dialog opens.

5. Repeat steps 3 and 4.

You have configured and set up your backup jobs with the help of Backup Manager.

For more information on backing up using the Backup Manager, see the online help.

**More information:**

[Image/Serverless Backup Option Dialog](#) (see page 18)

## Image/Serverless Backup Option Dialog

The Image/Serverless Backup Options dialog lets you configure a backup job.

The Image/Serverless Backup dialog displays the following fields:

**These settings take precedence over machine options**

Indicates that the settings on this dialog override any options that you may have set on the disk or volume.

**Enable Image/Serverless Backup for this drive/volume**

Sets values for the entire computer.

The dialog has the following options:

**Enable file level restore (Slows down backups for NTFS volumes)**

Enables restoring at the file level. However, this slows down the process when you back up NTFS volumes, because the IO has to generate the file/folder information by parsing the file system layout on the disk.

**Add file records to database**

Adds details of files to the database. This is helpful when you choose to enable restoring at file level, as the backup sessions will have the details of files in the database. If you do not add these details to the database, when you restore at the file level, you will have to merge the backup sessions with the file details before restoring.

The following fields let you specify the action when a volume freeze fails:

**Fail backup immediately**

Stops the backup process when a volume freeze fails.

**Continue with backup**

Continues with the backup process although a volume freeze has failed.

**Retry specified number of times then fail backup**

Attempts to continue the backup process for a preset number of times.

**Number of retries**

Specifies the number of times that the option attempts to complete the backup process.

**Interval between retries (mins)**

Specifies the number of minutes that the option waits after a failed backup attempt.


## View Job Status

You can check the status of the backup jobs you have submitted, from the Job Status window.

**To check the status of the backup job**

1. On the Job Queue tab, select the job.
2. Right-click and choose Properties from the pop-up menu.

The Job Monitor dialog opens.



The Job Monitor dialog displays the current job attributes and the job complete percentage.

**More Information:**

[Job Monitor Dialog](#) (see page 20)

## Job Monitor Dialog

The Job Monitor dialog displays the current job's attributes and the percentage of completion.

The dialog displays the following:

**Job Name**

Displays the type of job that is running, such as backup or restore.

**Source**

Displays the backup source computer name, the size of the backup and restore file, and the drive that is currently being backed up or restored.

**Status**

Displays the current job status.

**Files**

Displays the total number of files in the backup or restore job.

The Statistics pane displays the following:

**Total Streams**

Displays the total number of streams in the backup or restore job.

**MB/Minute**

Displays the current transfer rate used to transfer files during a backup or restore job.

**Files Backed Up**

Displays the total number of files in the backup job.

**MB Processed**

Displays the number of megabytes processed at this time.

**MB Estimated**

Displays the estimated number of megabytes in the current backup or restore job.

**Elapsed Time**

Displays the number of minutes and seconds that have elapsed from the time backup or restore started.

**Remaining Time**

Displays the number of estimated minutes and seconds remaining to complete the backup or restore job.

The Log tab displays the following:

**Error**

Displays the errors occurred during the backup or restore process.

**Error and Warning**

Displays the errors and warnings occurred during the backup or restore process.

**All**

Displays the backup or restore job information.

## Restore Methods

Use one of the following methods to restore data backed up by the CA ARCserve Backup Image Option:

### ■ **Restore by Image**

Restores the entire drive in one pass. To be successful, the restore job must be completed from beginning to end. Canceling leaves the drive in an inconsistent stage, and therefore inaccessible. The following are the limitations of this method:

- The Restore by Image method supports only full volume restores. When you use the Restore by Image method, the agent overwrites the target volume, so be sure that the target drive selected is the one that you want to restore.

**Important!** The Restore by Image option overwrites your drive completely. Be sure this is what you want to do.

- In the Restore by Image method, selecting multiple sources is only permitted when using the Restore to Original Location option.
- The Restore by Image method supports cluster sizes up to 16 KB for NTFS partitions, and requires multiple drives or partitions to function properly. This option does not support single partitions.
- The Restore by Image method always overwrites existing files during restore operations, regardless of the restore options selected.

- The Restore by Image sessions cannot be restored to network drives. They require the same or greater local hard disk drive.
- During a Restore by Image session, the drive cannot have any open files. The option attempts to lock the drive before the restore process begins, and, if any files are open, the drive cannot be locked and the restore job fails.

- **Restore by Session**

Restores individual files and directories. Canceling a job that is in progress can leave many incomplete restored files on the drive.

The following global restore options are *not* supported at this time:

- **Destination**

Directory Structure and File Conflict Resolution

- **Operation**

Restore Registry Files and Event Logs

- **Virus**

Enable Virus Scanning, Skip, Rename, and Delete

The CA ARCserve Backup Image Option does not support the Restore by Backup Media method at this time.

## Restore a Drive

CA ARCserve Backup restores the entire drive backed up by the CA ARCserve Backup Image Option.

### To restore a drive

1. Open the Restore Manager.
2. On the Source tab, select the Restore by Image/Serverless option in the drop-down list.
3. Select the drives containing the backup taken using the option.
4. (Optional) On the Destination tab, select the destination where you want to restore.
5. Click Submit on the toolbar.

The restore process starts or is scheduled to be executed.

## Restore Individual Files

CA ARCserve Backup restores individual files backed up by the CA ARCserve Backup Image Option.

### **To restore individual files**

1. Open the Restore Manager.
2. On the Source tab, select Restore by Session from the drop-down list.  
The sessions appear in the session directory tree.
3. Select the files, folders, or both that you want to restore.  
(Optional) On the Destination tab, clear the check mark next to Restore files to their original location(s) and then specify the location where you want to restore the data.  
Click Submit on the toolbar.  
The restore process starts or is scheduled to be executed.

# Chapter 3: Serverless Backup Option

---

This section contains the following topics:

[Introducing the Serverless Backup Option](#) (see page 25)

[Installing the Serverless Backup Option](#) (see page 29)

[Using the Serverless Backup Option](#) (see page 30)

## Introducing the Serverless Backup Option

Among the options CA ARCserve Backup offers is the CA ARCserve Backup Serverless Backup Option. This option helps you do the following:

- Back up data with near-zero impact to the system CPU.
- Let applications on servers continue to run while the backup job is in progress.
- Eliminate the need for a backup window, ensuring the highest possible backup and restore performance.
- Let applications continue to access the data while the data is being backed up.


The Serverless Backup Option is implemented using the *extended copy* command and currently supports SAN environments with devices that support this command.

## Backup Methods

The following sections describe the different backup methods available in the Serverless Backup Option.

## Traditional Server-Based Backup

In traditional backup operations, the backup application reads the data from the primary storage device to the system memory, and does the necessary formatting. It then sends the data back to the media storage devices, requiring use of CPU, I/O channels, and the system memory. The data path is illustrated in the following diagram:



Typically, when backup operations are in progress, application processing on servers is impacted. This is one of the reasons for which system administrators prefer to perform backup operations at a time when the application load on the server is at a minimum.


## SAN Backup

SANs have improved system administration by addressing the potential limitations of traditional backup operations. In traditional backup operations, one network server is connected to a device and, as a result, is the only server to receive the benefits of high-speed backup operations. SANs allow several servers to directly link to a device, thus eliminating the LAN bottleneck and slower transmission.

SANs improve backup operations by:

- Centralizing backup hardware and media
- Economizing by allowing servers to share multiple tape libraries
- Reducing processing time by eliminating the need for remote backup operations


The basic SAN architecture is shown in the following diagram:



### High Performance Serverless Backup

SANs incorporate various devices referred to as *data movers*. These devices support the extended copy (or sometimes called third party copy) command. The Serverless Backup Option uses these data movers to extend SAN technology by facilitating the fastest possible backup and restore speeds.

Using the extended copy command, the option completely eliminates the server from the data transfer path and achieves direct disk-to-media or media-to-disk data transfer. Initiating the data transfer is the only activity that occurs at the server level; the actual data transfer occurs at the level of the data mover on the SAN. Serverless operation is illustrated in the following diagram:



The Serverless Backup Option uses data movers to transfer data between media. This eliminates the need for moving the data to the server, and achieves the shortest data path. Data movers enhance the backup performance considerably, and yield the highest possible backup and restore speeds.

The option freezes the backup drive at a consistent point in time (like a snapshot), but still allows applications to continue to access volumes while the backup job is in progress. This functionality eliminates the need to schedule backup jobs when the application load on the server is at a minimum, and lets system administrators back up data at any time.

## Unsupported Functions

The following CA ARCserve Backup functions are *not* available when using the Serverless Backup Option:

- The CA ARCserve Backup Tape RAID Option
- The CA ARCserve Backup Disk Staging Option
- Filters for backup
- Multiplexing
- Virus scan
- Encryption

## Operational Considerations

The Serverless Backup Option allows you to perform serverless backup and restore of hard drives in a SAN environment, with the following considerations:

- The option does not support restore using the Restore by Media method.
- The option supports full volume backup in serverless mode.
- The option supports full volume restore using the Restore by Image/Serverless method.

**Note:** Because serverless backup is a full volume backup, you will overwrite the target volume if you use the Restore by Image/Serverless from the Restore Manager. You must make sure that the target drive you have selected is the one you really want to restore.

- The Serverless Backup Option supports restore using the Restore by Session method and Restore by Tree method.
- The option always overwrites existing files during restore, regardless of whether the restore options are used.
- The option supports cluster sizes up to 16 KB for NTFS partitions.

## Global Option Restrictions

The following section lists the CA ARCserve Backup global options that are *not* supported by the Serverless Backup Option:

- Global backup options:
  - **Methods**  
Keep Archive Bit, Clear Archive Bit, Incremental, and Differential
  - **Operation**  
Delete Files After Backup, Disable File Estimate, Calculate and Store CRC Value on Backup Media, and Back Up CA ARCserve Backup Database files
  - **Virus**  
Enable Virus Scanning, Skip, Rename, Delete, and Cure
  - **Other options**  
Microsoft Volume Shadow Support Service and Traverse Directory Functions
- Global restore options:
  - **Destination**  
Directory Structure and File Conflict Resolution
  - **Virus**  
Enable Virus Scanning, Skip, Rename, Delete, and Cure

## Installing the Serverless Backup Option

This section lists the installation prerequisites for the option and explains how you can install the option.

## Installation Prerequisites

Before installing the option, verify the following:

- Your system configuration meets the minimum requirements needed to install the option.  
For a list of requirements, see the readme file.
- You have administrator privileges on the computers on which you want to install the option.
- You have the following applications installed and working properly:
  - CA ARCserve Backup
  - CA ARCserve Backup Enterprise Module
  - CA ARCserve Backup Tape Library Option
  - CA ARCserve Backup SAN Option

**Important!** You must install the Enterprise Module (which automatically includes this option) and CA ARCserve Backup on the same computer. This computer can be located either locally or remotely.

## Install the Serverless Backup Option

The Serverless Backup Option is installed locally when you install the Enterprise Module.

### To install and configure the option

1. Install and configure the option using the Enterprise Module Configuration utility (EMConfig.exe) during the post-installation process.  
**Note:** You can also access the EMConfig.exe utility from the Windows Start menu (click Start, All Programs, CA, ARCserve Backup, Enterprise Module Configuration).
2. Complete the installation and configuration procedure, and restart your computer when prompted.

## Using the Serverless Backup Option

This section provides information about how you can back up and restore data using the Serverless Backup Option.


## Define Backup Jobs Using the Backup Manager

You can define backup jobs to back up data using the Backup Manager.

### To back up with the Backup Manager

1. In the Backup Manager window, click the Source tab.  
The available systems and servers are displayed.
2. Select and right-click the drive on the computer that you want to back up.  
**Note:** You must select a drive name for serverless backup.
3. Select Use Image/Serverless Backup Option from the pop-up menu.

The Image/Serverless Backup Options dialog opens.



4. Complete the fields in the dialog, and then click OK.
5. In the Destination tab, specify the destination.
6. Click Submit on the toolbar.

The backup job starts or is scheduled to be executed.

For more information about how to back up, see the online help.

### More information:

[Image/Serverless Backup Option Dialog](#) (see page 18)

## Image/Serverless Backup Option Dialog

The Image/Serverless Backup Options dialog lets you configure a backup job.

The Image/Serverless Backup dialog displays the following fields:

### **These settings take precedence over machine options**

Indicates that the settings on this dialog override any options that you may have set on the disk or volume.

### **Enable Image/Serverless Backup for this drive/volume**

Sets values for the entire computer.

The dialog has the following options:

### **Enable file level restore (Slows down backups for NTFS volumes)**

Enables restoring at the file level. However, this slows down the process when you back up NTFS volumes, because the IO has to generate the file/folder information by parsing the file system layout on the disk.

### **Add file records to database**

Adds details of files to the database. This is helpful when you choose to enable restoring at file level, as the backup sessions will have the details of files in the database. If you do not add these details to the database, when you restore at the file level, you will have to merge the backup sessions with the file details before restoring.

The following fields let you specify the action when a volume freeze fails:

### **Fail backup immediately**

Stops the backup process when a volume freeze fails.

### **Continue with backup**

Continues with the backup process although a volume freeze has failed.

### **Retry specified number of times then fail backup**

Attempts to continue the backup process for a preset number of times.

#### **Number of retries**

Specifies the number of times that the option attempts to complete the backup process.

#### **Interval between retries (mins)**

Specifies the number of minutes that the option waits after a failed backup attempt.

## Restore Methods

You can use the following methods to restore data that is backed up by the Serverless Backup Option:

### Restore by Image/Serverless

Restores the entire drive in serverless mode. To be successful, the serverless restore must be completed from beginning to end.

**Important!** Using the Restore by Image/Serverless backup option overwrites your drive completely. Be sure that this is what you want to do.

### Restore by Session

Restores individual files and directories in file mode.

**Important!** Do not cancel a restore job that is in progress; it can leave many incomplete restored files on the drive.

## Restore a Drive

Using the Restore by Image/Serverless method, you can restore the entire drive backed up in serverless mode.

### To restore a drive

1. Open the Restore Manager.
2. On the Source tab, select the Restore by Image/Serverless option in the drop-down list.
3. Select the drives containing the backup taken using the option.
4. (Optional) On the Destination tab, select the destination where you want to restore.
5. Click Submit on the toolbar.

The restore process starts or is scheduled to be executed.

## Restore Individual Files and Directories

When you restore individual files and directories, the restore operation is performed in the traditional file mode, not in serverless mode.

### **To restore individual files or directories**

1. On the Source tab in the Restore Manager, select the Restore by Tree or Restore by Session view from the drop-down list.
2. In the tree view, select the source drive that contains the backup taken using the Image/Serverless Backup option. Expand the drive and select the files or folders that you want to restore.
3. In the Destination tab, select the destination drive.
4. Click Submit on the toolbar.

The restore process starts or is scheduled to be executed.

# Chapter 4: Enterprise Tape Library 3494 and StorageTek Options

---

This section contains the following topics:

- [Introducing Enterprise Tape Library 3494 and StorageTek ACSLS](#) (see page 36)
- [Option Architecture](#) (see page 38)
- [Installing and Configuring](#) (see page 54)
- [Using Enterprise Tape Library 3494 and StorageTek ACSLS](#) (see page 74)

## Introducing Enterprise Tape Library 3494 and StorageTek ACSLS

CA ARCserve Backup offers two solutions for tape libraries, namely the CA ARCserve Backup Enterprise Option for IBM 3494 and the CA ARCserve Backup Enterprise Option for StorageTek ACSLS. These options let you use the large tape volume capacities of the IBM® TotalStorage® Enterprise Automated Tape Library 3494, and the tape libraries controlled by StorageTek Automated Cartridge System Library Software (ACSLS) Manager software. CA ARCserve Backup server interfaces with the IBM TotalStorage Enterprise Automated Tape Library 3494 and StorageTek Automated Cartridge System Library Software to manage backup and restore operations, tape volume movement, and tape volume organization.

This section uses the following conventions:

### **Enterprise Tape Library 3494**

Identifies IBM TotalStorage Enterprise Automated Tape Library 3494.

### **StorageTek ACSLS**

Identifies StorageTek Automated Cartridge System Library Software.

### **the option**

Identifies Enterprise Option for IBM 3494 or Enterprise Option for StorageTek ACSLS in general.

### **tape library**

Identifies Enterprise Tape Library for 3494 or StorageTek ACSLS in general.

The options let several CA ARCserve Backup servers share a network-connected tape library. By using several CA ARCserve Backup servers, you can divide large, complex backup requirements into manageable subsets and maximize backup and restore efficiency. Backup and restore jobs run simultaneously on all CA ARCserve Backup servers with complete storage data integrity.

These options also provide services that let CA ARCserve Backup perform backup, restore, and device management operations on the tape volumes. Each CA ARCserve Backup server performs these operations as if it is controlling its own separate library. CA ARCserve Backup server interprets the assigned tape volumes on the tape library as local tape volumes; however, the physical movement of tape volumes is managed exclusively by the tape library.

**Important!** The tape volumes in the tape library must have bar codes to use the option.

## Enterprise Tape Library IBM 3494

After you install and configure the Enterprise Option for IBM 3494 on the CA ARCserve Backup server, you can use CA ARCserve Backup to manage backup and restore operations on the Enterprise Tape Library 3494.

Using the Enterprise Option for IBM 3494, the CA ARCserve Backup server can automatically associate known or discovered physical tape drives in the Enterprise Tape Library 3494 with a logical local library on the CA ARCserve Backup server. The option lets you assign tape volumes in the Enterprise Tape Library 3494 to the logical library on the CA ARCserve Backup server. This configuration lets you use the features of CA ARCserve Backup to control the Enterprise Tape Library 3494.

**Note:** Each CA ARCserve Backup server can be physically connected to one Enterprise Tape Library 3494 and can manage one logical library configuration for the Enterprise Tape Library 3494.

## StorageTek ACSLS

After you install and configure the Enterprise Option for StorageTek ACSLS on the CA ARCserve Backup server, you can use CA ARCserve Backup to perform the following functions:

- Manage backup and restore operations
- Update the configuration of the virtual library on the CA ARCserve Backup server with device or tape volume changes on the StorageTek ACSLS tape library

The Enterprise Option for StorageTek ACSLS lets several CA ARCserve Backup servers share a network-connected StorageTek ACSLS tape library. StorageTek ACSLS functions as a central service provider for StorageTek ACSLS library operations in heterogeneous environments. This configuration lets you manage different application-dedicated libraries using one centralized library or string of libraries.

**Note:** The term *mixed media* (or heterogeneous environment) refers to a mixture of tape drives and tape volumes in the StorageTek ACSLS tape library. In configurations where more than one tape drive is connected to a CA ARCserve Backup server, both tape drives must use media of the same type.

Using this option, the CA ARCserve Backup server can assign tape volumes in the StorageTek ACSLS tape library to the logical library on the CA ARCserve Backup server. This virtual library configuration lets you use the features of CA ARCserve Backup to control the remote StorageTek ACSLS tape library as if it were connected locally.

**Note:** Each CA ARCserve Backup server can manage one logical library configuration for the StorageTek ACSLS tape library. Each CA ARCserve Backup server can physically connect to multiple tape drives of the same type.

## Option Architecture

This section describes the architecture of each tape library.

The options are separate software components installed on servers running CA ARCserve Backup. Several CA ARCserve Backup servers can share one tape library.

While the CA ARCserve Backup server logical library essentially partitions a large Enterprise Tape Library 3494 into independent, user-defined logical libraries, the CA ARCserve Backup server virtual library essentially partitions a large StorageTek ACSLS tape library into independent user-defined logical libraries.

## Enterprise Tape Library 3494

The tape volume assignments on the CA ARCserve Backup server define the logical library. The tape volumes configured for the Enterprise Option for IBM 3494 are not part of a physical library connected to the CA ARCserve Backup server, but are interpreted by CA ARCserve Backup as a local library. The logical library configurations have a mutually exclusive set of tape volumes or a shared set of tape volumes, depending on whether the CA ARCserve Backup server is in a SAN.

**Note:** In configurations where multiple backup servers share the Enterprise Tape Library 3494, ensure that tape drives assigned to CA ARCserve Backup server are not assigned to any other backup servers.

### Communication Interface

Each backup server communicates directly and independently with the Enterprise Option for IBM 3494. Although multiple backup servers may exist on the same network, CA ARCserve Backup servers do not communicate with other backup servers.

**Note:** For more information about using CA ARCserve Backup in a SAN, see *Appendix A: Storage Area Network Support* in the *Administration Guide*.

Communication between the Enterprise Tape Library 3494 and the CA ARCserve Backup server occurs through the following communication interfaces:

- The IBM Automated Tape Library service on the CA ARCserve Backup server connects to the Enterprise Tape Library 3494 through an Ethernet LAN control path.
- Each CA ARCserve Backup server independently connects to one or more tape drives in the library through SCSI or fiber channel data paths.
- Other backup servers can also exist on the network and share the Enterprise Tape Library 3494.

### Library Request Flow for Enterprise Tape Library 3494


The IBM Automated Tape Library service sends library requests over the control path to the IBM Library Manager. The Library Manager queues and handles library requests from multiple backup servers in the order it receives the requests.

## Mutually Exclusive Tape Volumes

In configurations where the CA ARCserve Backup server is not in a SAN, each CA ARCserve Backup server is configured to control a mutually exclusive set of tape volumes in the Enterprise Tape Library 3494. As a result, each CA ARCserve Backup server manages a user-defined subset of tape volumes on the Enterprise Tape Library 3494 that are unique to that CA ARCserve Backup server.

## Mutually Exclusive Tape Volume Architecture

Each CA ARCserve Backup server has an autonomous view of the Enterprise Tape Library 3494 that shows only the locally assigned volumes. The following illustration shows the architecture of the CA ARCserve Backup Enterprise Option for IBM 3494 and the communication interfaces to the Enterprise Tape Library 3494:



If multiple backup servers are sharing the same Enterprise Tape Library 3494, you must ensure that each tape volume is assigned to only one backup server. The tape volumes assigned to each backup server should be mutually exclusive, which means they cannot be used or accessed by other backup servers attached to the network.

Assigning mutually exclusive tape volumes requires careful planning. To assist you in your planning effort, you should document the tape volume assignment for each backup server that will share the Enterprise Tape Library 3494.

**Important!** If tape volumes are not mutually exclusive, or, are shared between backup servers, you risk losing important backup data.


**Note:** If you are adding backup servers to an established configuration, avoid duplication by checking the current tape volume assignments before adding the new backup servers.

**More Information:**

[Library Configuration Tasks](#) (see page 62)

## Volume Configuration Example

The tape volume assignments determine the volume configuration for the logical user-defined library on each CA ARCserve Backup server. In the following example, a unique set of tape volumes defines the logical library for each CA ARCserve Backup server:



The example shows that the Enterprise Tape Library 3494 has four tape drives directly attached to several backup servers on the network. The unique tape volume assignments for each CA ARCserve Backup server are:

- Server A has six assigned tape volumes: MKT686, MKT710, MKT713, MKT547, MKT016, and MKT 980
- Server B has eight assigned tape volumes: MK1970, MK1963, MKT002, MKT355, MKT774, MKT345, MKT657, and MKT114
- Server C has four assigned tape volumes: MKT384, MKT674, MKT962, and MKT031

Another backup server on the network that is not running CA ARCserve Backup may have a different configuration. Other backup servers on the network can also share the Enterprise Tape Library 3494.


## Shared Tape Volumes in a SAN

In a SAN, each CA ARCserve Backup server connects directly to a SAN, which, in turn connects to at least one tape drive in the Enterprise Tape Library 3494. In configurations with multiple CA ARCserve Backup servers in a SAN, each backup server is configured to control and share the same set of tape drives and tape volumes in the Enterprise Tape Library 3494. As a result, each CA ARCserve Backup server in the SAN shares the same user-defined subset of tape volumes on the Enterprise Tape Library 3494.

In a SAN, the CA ARCserve Backup servers share the same logical library configuration, the same tape volume configuration, and the same tape drive configuration.


**Note:** For more information about using CA ARCserve Backup in a SAN, see *Appendix A: Storage Area Network Support in the Administration Guide*.

The Enterprise Option for IBM 3494 must reside on the Primary Server in the SAN. The following illustration shows the option architecture in a SAN and the SAN communication interface to the Enterprise Tape Library 3494:



## SAN Shared Volume Configuration Example

The tape volume assignments determine the logical user-defined library shared by all CA ARCserve Backup servers in the SAN. In the following example, a single set of tape volumes defines the logical library for the SAN:



The example shows that the Enterprise Tape Library 3494 has three tape drives directly attached to a SAN. The tape volume assignments are the same for each CA ARCserve Backup server in the SAN. Another backup server on the network that is not running CA ARCserve Backup may have a different configuration.

## Tape Categories

The Enterprise Tape Library 3494 tracks the category number of each tape volume in the library. A single category number identifies all tape volumes used for the same purpose or application. The tape volumes imported into the Enterprise Tape Library 3494 by the CA ARCserve Backup server are assigned to the CA ARCserve Backup category F00F.

### Insert Category

When a tape volume is first inserted into the library, either manually or automatically at the convenience I/O station, the tape volume is assigned to the insert category FF00. When tape volumes are imported into the CA ARCserve Backup server, the tape volumes move from the insert category FF00 to the CA ARCserve Backup category F00F.

### **Unique Application Category**

Each backup server that shares the Enterprise Tape Library 3494 has its own access defined by tape volume categories. Each backup server must use a unique set of category numbers to identify that application. The unique application category for CA ARCserve Backup server is F00F.

### **Eject Category**

When a tape volume is assigned to the eject category, the tape volume is unavailable to the CA ARCserve Backup server. The eject category is FF10.

### **StorageTek ACSLS**

The virtual library is defined and configured by tape volume assignments for the CA ARCserve Backup server. The virtual library configuration is defined with mutually exclusive sets of tape volumes or with a shared set of tape volumes, depending on whether the CA ARCserve Backup server is in a SAN.

## Communication Interface

Each backup server communicates directly and independently with the Enterprise Option for StorageTek ACSLS. Although multiple backup servers may exist on the same network, CA ARCserve Backup servers do not communicate with other backup servers unless they are in a SAN.

**Note:** For more information about using CA ARCserve Backup in a SAN, see *Appendix A: Storage Area Network Support* in the *Administration Guide*.

The communication interfaces between the StorageTek ACSLS tape library and the CA ARCserve Backup server consist of an Ethernet LAN control path and a (SCSI) Small Computer System Interface or fibre channel data path. The control path and the data path are two different paths.

### Control Path

The StorageTek ACSLS Library Attach software on the CA ARCserve Backup server is connected to the StorageTek ACSLS library through an Ethernet LAN control path. The StorageTek Library Attach software sends library requests over the Ethernet LAN control path directly to the ACSLS Manager software on the StorageTek ACSLS server.

**Note:** You can verify the network connectivity between the CA ARCserve Backup server and the StorageTek ACSLS tape library by using the StorageTek Library Attach software.

### Data Path

Each CA ARCserve Backup server is independently connected to one or more tape drives in the StorageTek ACSLS tape library through SCSI or fiber channel data paths. The CA ARCserve Backup server reads and writes data on tape volumes in the tape library managed by StorageTek ACSLS by interacting directly with tape drives through the SCSI or fibre channel data path. In SAN configurations, the CA ARCserve Backup servers are connected to the SAN that is connected to the StorageTek ACSLS tape drives.

The following configurations support fibre attached tape drives:


- The fibre attached tape drive is directly connected to the CA ARCserve Backup server
- The StorageTek ACSLS tape library is not shared by other CA ARCserve Backup servers
- In a SAN, where the CA ARCserve Backup SAN Option is installed on the primary SAN server

## Library Request Flow for StorageTek ACSLS

StorageTek ACSLS processes the requests for library operations as follows:

- The CA ARCserve Backup server initiates requests for library operations.
- The StorageTek Library Attached software on the CA ARCserve Backup server transmits these requests to the ACSLS Manager on the StorageTek ACSLS server.
- The ACSLS Manager receives and interprets a library request, and performs the requested operation on the StorageTek ACSLS library.
- The ACSLS Manager also forms and returns a response to the CA ARCserve Backup server.

The StorageTek ACSLS library request flow is shown in the following illustration:




## Mutually Exclusive Tape Volumes

In configurations where the CA ARCserve Backup server is not in a SAN, each CA ARCserve Backup server is directly connected to at least one tape drive in the StorageTek ACSLS tape library using independent SCSI data paths.

In configurations with multiple CA ARCserve Backup servers, each backup server is configured to control a mutually exclusive set of tape volumes in the StorageTek ACSLS tape library. Mutually exclusive tape volumes cannot be used or accessed by other backup servers attached to the network. As a result, each CA ARCserve Backup server manages a user-defined subset of tape volumes on the StorageTek ACSLS tape library that are unique to that CA ARCserve Backup server.

### Mutually Exclusive Tape Volume Architecture

The following illustration shows the architecture of the Enterprise Option for StorageTek ACSLS and the communication interfaces to the StorageTek ACSLS tape library:




Because multiple backup servers share the StorageTek ACSLS tape library, you must ensure that each tape volume is assigned to only one backup server. The tape volumes assigned to each backup server must be mutually exclusive.

**Important!** If your CA ARCserve Backup servers are not in a SAN, tape volumes must be mutually exclusive to each backup server or you could lose important backup data.

Assigning mutually exclusive tape volumes requires careful planning. To assist you in your planning effort, you should document the tape volume assignment for each backup server that will share the StorageTek ACSLS tape library.

## Mutually Exclusive Tape Volume Configuration

The tape volume assignments determine the volume configuration for the user-defined logical library on each CA ARCserve Backup server. In the following illustration, a unique set of tape volumes defines the logical library for each CA ARCserve Backup server:




The example shows that the StorageTek ACSLS tape library has four tape drives directly attached to several backup servers on the network. The unique tape volume assignments for each CA ARCserve Backup server are:

- Server A has six assigned tape volumes: CB0686, CB0710, CB0713, CB0547, SV345, and ISV349
- Server B has eight assigned tape volumes: ISV021, ISV034, ISV036, ISV067, ISV068, ISV069, ISV072, and ISV082
- Server C has four assigned tape volumes: D00761, D00764, D00767, and D02443

Another backup server on the network that is not running CA ARCserve Backup may have a different configuration.

## Multiple Server Connections to Tape Drive Configuration

The tape drives on the StorageTek ACSLS library can be distributed among several CA ARCserve Backup servers to maximize backup and restore efficiency, as shown in the following illustration:




**Note:** In configurations where more than one tape drive is connected to a CA ARCserve Backup server, both tape drives must use media of the same type.

## Shared Tape Volumes in a SAN

In a SAN, each CA ARCserve Backup server connects directly to a SAN, which, in turn, connects to at least one tape drive in the StorageTek ACSLS tape library. In configurations with multiple CA ARCserve Backup servers in a SAN, each backup server is configured to control and share the same set of tape drives and tape volumes in the StorageTek ACSLS tape library. As a result, each CA ARCserve Backup server in the SAN shares the same user-defined subset of tape volumes on the StorageTek ACSLS tape library.


In a SAN, the CA ARCserve Backup servers have the same virtual library configuration, the same tape volume configuration, and the same tape drive configuration.

The Enterprise Option for StorageTek ACSLS must reside on each CA ARCserve Backup server in the SAN. The following illustration shows the option architecture in a SAN and the SAN communication interface to the StorageTek ACSLS tape library:




## Shared Tape Volume Architecture

The following illustration shows the architecture of CA ARCserve Backup servers in a SAN and the SAN communication interface to the StorageTek ACSLS tape library:



## Shared Tape Volume Configuration in a SAN


The tape volume assignments determine the user-defined logical library shared by all CA ARCserve Backup servers in the SAN. In the following illustration, a single set of tape volumes defines the logical library for the SAN:



The illustration shows that the StorageTek ACSLS tape library has three tape drives directly attached to a SAN. The tape volume assignments are the same for each CA ARCserve Backup server in the SAN. Another backup server on the network that is not running CA ARCserve Backup may have a different configuration.

## SAN Server Connection to Tape Drive Configuration

The tape drives on the StorageTek ACSLS library can be connected to a SAN, which in turn is connected to several CA ARCserve Backup servers, as shown in the following illustration:



**Note:** In configurations where more than one tape drive is connected to a CA ARCserve Backup server, both tape drives must use media of the same type.

# Installing and Configuring

This section provides the information you need to install and configure the CA ARCserve Backup Enterprise Option for IBM 3494 and the CA ARCserve Backup Enterprise Option for StorageTek ACSLS.

To install these options, you must be familiar with the following:

- The characteristics and requirements of Windows operating system in general
- Administrator responsibilities of Windows operating systems in particular
- Enterprise Tape Library 3494
- StorageTek ACSLS

## Installation Prerequisites

Before installing the option, verify the following:

- Your system configuration meets the minimum requirements needed to install the option.  
For a list of requirements, see the readme file.
- You have administrator privileges on the computers on which you want to install the option.
- You have the following applications installed and working properly:
  - CA ARCserve Backup
  - CA ARCserve Backup Enterprise Module
  - CA ARCserve Backup Tape Library Option
  - IBM Automated Tape Library service or StorageTek ACSLS Library Attach software

**Important!** You must install the Enterprise Module (which automatically includes these options) and CA ARCserve Backup on the same computer.

- You know the host name, IP address, and password of the computer on which you are installing the option.
- You have the plan of your tape volume configuration.
- You have selected your library configuration method and gathered the required information to configure your library using the selected method.

**Note:** Contact your CA ARCserve Backup administrator to obtain the proper privileges.

## Installation Prerequisites Exclusive for Enterprise Tape Library 3494

Before installing Enterprise Tape Library 3494, ensure the following:

- You have installed the IBM Automated Tape Library service Version 5.4 for 32-bit on the CA ARCserve Backup server.

**Note:** CA ARCserve Backup works only with IBM Automated Tape Library service for 32-bit software.

- You have downloaded and installed the latest device drivers for the IBM Automated Tape Library service for the IBM TotalStorage Enterprise Automated Tape Library 3494.

**Important!** You must ensure these two points before installing the CA ARCserve Backup Tape Library Option and the Enterprise Option for IBM 3494.

- You have added the server where you will install CA ARCserve Backup as a LAN host to Enterprise Tape Library 3494.
- You have established and configured the communication between Enterprise Tape Library 3494 and the Automated Tape Library service on the computer where you will install CA ARCserve Backup.
- You have established and configured communication between the IBM Library Manager control service on the CA ARCserve Backup server and the Enterprise Tape Library 3494. You can use the mtlib program to verify library connectivity.
- You have included the logical library name, the IP address of the Enterprise Tape Library 3494, and the CA ARCserve Backup server identifier (typically the host name) in the library configuration file, ibmatl.conf.
- You have connected the empty Enterprise Tape Library 3494 tape drives to the CA ARCserve Backup server.
- You have developed a tape volume configuration plan to ensure mutually exclusive tape volume assignments for each CA ARCserve Backup server. In addition, you have identified which tape volumes on the Enterprise Tape Library 3494 will be assigned to the CA ARCserve Backup server.

**Note:** For more information about obtaining and installing Enterprise Tape Library 3494 software and device drivers, see the IBM software documentation.

### More Information:

[Library Configuration File](#) (see page 58)

[Library Configuration File Format](#) (see page 58)

## Data Path and Control Path Interfaces

Before starting the installation, you must establish the following Enterprise Tape Library 3494 communications:

- The SCSI or fibre channel data path between the CA ARCserve Backup server and the Enterprise Tape Library 3494 tape drives.
- The Ethernet LAN control path between the IBM Automated Tape Library service on the CA ARCserve Backup server and the Enterprise Tape Library 3494.

You can establish the Ethernet LAN connectivity by adding a LAN host to the Enterprise Tape Library 3494 server. The LAN host specified for the Enterprise Tape Library 3494 server must match the host name specified on the CA ARCserve Backup server.

**Note:** You can use the `mtlib` command to verify the status and connectivity of the Ethernet LAN control path between the IBM Library Manager Client and the IBM Library Manager Server.

### More Information:

[Add LAN Host to Enterprise Tape Library 3494](#) (see page 59)  
[Communication Interface](#) (see page 39)

## IBM Components

The Enterprise Tape Library 3494 client is installed on the CA ARCserve Backup server. This client software is the IBM Automated Tape Library service and is used to establish communication between the CA ARCserve Backup server and the Enterprise Tape Library 3494.

## IBM Library Manager

The IBM Library Manager controls the tape library robotics and maintains a database of tape volumes. The IBM Library Manager software resides on the Enterprise Tape Library 3494 and is controlled through the Enterprise Tape Library 3494 server console and by library requests received through the network.

## IBM Automated Tape Library Service

The IBM Automated Tape Library service is a separate software component installed on the CA ARCserve Backup server. This service must be running for successful communication between the CA ARCserve Backup server and the Enterprise Tape Library 3494.

## Library Configuration File

Before you install CA ARCserve Backup Enterprise Option for IBM 3494, you must configure communication between the CA ARCserve Backup server and the Enterprise Tape Library 3494 by editing the Enterprise Tape Library 3494 library configuration file. The name of the file is ibmatl.conf, and it is located in the c:\winnt directory.

**Note:** If the c:\winnt directory does not exist, it is created when you install the IBM Automated Tape Library service.

Use Notepad or any other text editor to edit the Enterprise Tape Library 3494 library configuration file before you install the Enterprise Option for IBM 3494.

## Library Configuration File Format

The library configuration file defines the symbolic library name, the IP address of the Enterprise Tape Library 3494, the identifier used by the IBM Library Manager control service, and an optional second Internet address for a high availability server. Any text following # is treated as a comment.

The format of the statements in the ibmatl.conf file is:

libraryname address identifier address2

The following list explains the parts of the statement:

### ***libraryname***

Indicates a symbolic name of the library.

Limits: 32 characters

### ***address***

Indicates a value that represents the IP address of the Enterprise Tape Library 3494.

### ***identifier***

Indicates the host name of the computer. The IBM Library Manager uses the identifier to locate the CA ARCserve Backup server. The *identifier* is also known as the *return alias*.

### ***address2***


(Optional) Specifies a second IP address for a high availability server.

**Note:** Do not specify the second IP address if you are not using a high availability server.

In the following example, the symbolic name of the library is 3494a, the IP address of the Enterprise Tape Library 3494 is 174.24.111.111, and the host name is host01:

```
3494a 174.24.111.111 host01
```

The first eight characters of the identifier defined in this file must match the first eight characters of the LAN host specified for the CA ARCserve Backup server in the Enterprise Tape Library 3494. The following example shows a definition of the LAN host on the Enterprise Tape Library 3494 and on the CA ARCserve Backup server:



## Add LAN Host to Enterprise Tape Library 3494

As part of the installation prerequisites, you must establish the Ethernet LAN connectivity by adding a LAN host to the Enterprise Tape Library 3494 server. The LAN host specified for the Enterprise Tape Library 3494 server must match the host name specified on the CA ARCserve Backup server.

### To add a LAN host to the Enterprise Tape Library 3494

1. Use the library operator console and click Commands, LAN options, Add LAN Host.
2. Enter the CA ARCserve Backup server IP address and the host name.
3. Use the mtlib commands and confirm the connectivity between the Enterprise Tape Library 3494 and the IBM Automated Tape Library service on the CA ARCserve Backup server.

## Installation Prerequisites Exclusive for StorageTek ACSLS

Before installing StorageTek ACSLS, ensure the following:

- You have installed and configured the StorageTek Library Attach software Version 1.4.2 for 32-bit on the CA ARCserve Backup server.  
**Note:** CA ARCserve Backup works only with 32-bit StorageTek LibAttach software.
- You have established communication between the StorageTek ACSLS server and the CA ARCserve Backup server.  
**Important!** Do this before installing the Enterprise Option for StorageTek ACSLS.
- You have established communication between the StorageTek ACSLS server and the StorageTek Library Attach software.
- You have configured the StorageTek ACSLS tape library and StorageTek ACSLS server.
- You have selected your library configuration method and gathered the required information to configure your library using the selected method.

## StorageTek ACSLS Components

The StorageTek ACSLS tape library control software consists of the ACSLS Manager and the ACSLS Client applications.

**Note:** In addition to supporting communication interfaces with StorageTek ACSLS tape libraries managed by the StorageTek ACSLS tape library control software, the Enterprise Option for StorageTek ACSLS also supports communication with StorageTek tape libraries managed by StorageTek Library Station control software.

The following StorageTek ACSLS communication interface software components are installed on the same computer as the Enterprise Option for StorageTek ACSLS:

- Library Attach software
  - Translates and routes messages between the ACSLS Manager and the CA ARCserve Backup server.
- Storage Server Interface (SSI)
  - Requests the movement of the tape volumes by sending requests to the Network Interface. It translates the library requests from the CA ARCserve Backup server into a format that can be interpreted by the ACSLS Manager software on the StorageTek ACSLS server.
- Network Interface
  - Handles the task of creating message packets for transfer across the network. The message packets consist of an address header, the actual data, and parity information. The parity information in the packet can be used for error correction.

## Installation Process

Make sure you have performed the required pre-installation tasks. When you have completed these tasks and gathered all of the required information, you are ready to start the installation process.

The highlights of the installation procedure include:

- Install the option.
- Configure the library during installation.
- Use the Quick Inventory option of the CA ARCserve Backup Device Manager and take an inventory of the device.

**Note:** For information about using the Device Manager, see the *Administration Guide*.

## Install the Option

The option (Enterprise Option for IBM 3494 or Enterprise Option for StorageTek ACSLS) is installed locally when you install the Enterprise Module.

### To install and configure the option

1. Install and configure the option using the Enterprise Module Configuration utility (EMConfig.exe) during the post-installation process.

**Note:** You can also access the EMConfig.exe utility from the Windows Start menu (click Start, All Programs, CA, ARCserve Backup, Enterprise Module Configuration).

2. Complete the installation and configuration procedure, and restart your computer when prompted.

**Note:** For more information about installing CA ARCserve Backup, see the *Implementation Guide*. For more information about installing and configuring the Tape Library Option, see the *Tape Library Option Guide*.

**Important!** The tape drive configuration occurs during the Tape Library Option installation. You must install the Tape Library Option before you install the option or during the same installation session. If the CA ARCserve Backup Tape Library Option is already installed, it will be reconfigured.

## Library Configuration Tasks

Configuring the logical library tape volumes is an integral and important part of the option installation process. Configure the library by performing the following tasks:

- Assign tape volumes to the CA ARCserve Backup server.
- Use the Quick Inventory option of the CA ARCserve Backup Device Manager and take an inventory of the device.

Configuring your tape volumes consists of assigning tape volumes to create the logical library on the CA ARCserve Backup server. Review your tape volumes assignment plan before you assign the tape volumes.

You will not assign any cleaning tape volumes as part of your tape volume configuration. Tape cleaning is managed exclusively by Enterprise Tape Library 3494. As a result, the cleaning slot designation is not applicable for any backup servers connected to the Enterprise Tape Library 3494. On the CA ARCserve Backup server, the cleaning slot information is always <None>.

**Note:** You can access the tape cleaning schedule by using the Enterprise Tape Library 3494 control console.

**More Information:**

[Introducing Enterprise Tape Library 3494 and StorageTek ACSLS](#) (see page 36)  
[Communication Interface](#) (see page 39)

## Configure Enterprise Tape Library 3494 Drives

You must configure Enterprise Tape Library 3494 drives before configuring its volumes.

### To configure Enterprise Tape Library 3494 drives

1. Click Start, Programs, CA, ARCserve Backup, Enterprise Module Configuration.  
The Configure Enterprise Module window appears.
2. Click Enterprise Tape Library 3494.  
The IBM 3494 Library Configuration dialog opens.
3. Click Auto Config.  
CA ARCserve Backup will search the library for any newly added drives and displays them in the drive list.

## Configure Library for Enterprise Tape Library 3494


After all tape drives are configured as part of the installation, all tape volumes in the Enterprise Tape Library 3494 appear in the Volume Configuration dialog.

### To configure your library tape volumes

1. Select one or more tape volumes that you want to assign to the logical library.

**Note:** Press and hold the Ctrl key to select multiple tape volumes.

2. Right-click the selected tape volumes, and select Assign.



**Note:** Initially the tape volumes are not assigned to the CA ARCserve Backup server. The unassigned status is indicated by a red slash through the tape volume icon.

3. Review your tape volume assignment and click Next.

A message reminds you to use the CA ARCserve Backup Device Manager to take an inventory before you use the Enterprise Tape Library 3494.

4. Click OK to close the message dialog.

A summary dialog opens to show the library tape drive configuration.

5. Click Finish to complete your library configuration.

A message appears to confirm your successful library configuration.

6. Click Exit.

The library configuration summary dialog opens.

7. Click Finish to complete your library configuration.

A message appears to confirm your successful library configuration.

8. Click Exit.

The Install Summary dialog opens.

9. After you configure your library, review the installation summary.

The Enterprise Option for IBM 3494 status shows Installation Completed and Configuration Completed.

10. Click Finish to complete the installation.

11. Use the Quick Inventory option and take an inventory of the Enterprise Tape Library 3494 to detect any changes that may have occurred while the Tape Engine was stopped.

## Configure Library for StorageTek ACSLS

Configuring your library is an important step in installing the Enterprise Option for StorageTek ACSLS. You must have the Tape Library Option installed to configure the library. You can install the Tape Library Option before or during installation of the Enterprise Option for StorageTek ACSLS. During the installation of the Tape Library Option, the tape drives attached to the CA ARCserve Backup server are detected and assigned to the server.

Before configuring, remove all tape volumes from the tape drives in the StorageTek ACSLS library. After you assign the tape drives to the server and remove the tape volumes from the tape drives, configure the library by choosing either the manual or the automatic configuration methods. During configuration, the tape volumes in the StorageTek ACSLS library are read and initialized.

## Library Configuration Tasks

Configuring the logical library is an integral and important part of the option installation process. Configure the library for the Enterprise Option for StorageTek ACSLS by completing the following library configuration tasks:

- Configure the tape drives, manually or automatically
- Assign tape volumes to the CA ARCserve Backup server to configure the logical library
- Use the Quick Inventory option of the Device Manager and take an inventory of the device

## Configure Library Manually

The manual library configuration method lets you manually enter tape drive parameters. Use the manual library configuration method to configure the logical library if the tape drives in the StorageTek ACSLS library use a mixture of different types of tape volumes or if the StorageTek ACSLS library is shared with other backup servers.

The process of entering tape drive parameters assigns the tape drive to the logical library on the CA ARCserve Backup server. A green tick mark next to the tape drive in the Manual Configuration dialog indicates that you have entered the tape drive parameters.

## Obtain Tape Drive Parameters

You can obtain the tape drive parameters by querying the status of the tape drives on the StorageTek ACSLS library.

Enter the following parameters for each tape drive:

- Automated Cartridge System (ACS)
- Logical Silo Module (LSM)
- Panel number (Panel)
- Drive ID number (ID)

### More Information:

[StorageTek Tape Library Queries \(see page 76\)](#)

## Configure Your Library Tape Drives Manually

You can configure the library tape drives either manually, or by using the wizard. This section gives you the procedure to configure the tape drives manually. Select Manual configuration if your StorageTek ACSLS library contains drives that use different types of media or if other libraries or stand-alone tape drives are present in your environment.


### To configure the library tape drives manually

1. Select the manual library configuration method.
2. Click Next.

The Manual Configuration dialog displays a list of the tape drives that are attached to the CA ARCserve Backup server.

3. Select a tape drive to be configured.
4. Click Configure to enter the parameters of the selected tape drive.

The Edit drive parameters dialog opens.



5. Enter the ACS, LSM, Panel, and ID of the tape drive in the Edit drive parameters dialog.
6. Click OK.

The Edit drive parameters closes and a green tick mark appears for each configured tape drive.
7. Repeat the manual configuration for each tape drive.
8. Click Next to verify the configuration information and to initialize the tape drives.

The Volume Configuration dialog opens showing a list of unassigned tape volumes.

**More Information:**

[Configure Library Manually](#) (see page 65)

## Automatic Library Configuration

The automatic library configuration method determines which tape drives in the StorageTek ACSLS library are connected to the CA ARCserve Backup server. Use this method if all tape drives in the StorageTek ACSLS library are of the same type.

The CA ARCserve Backup server performs the following device detection and verification tasks during automatic library configuration:

- Unloads all the tape drives in the StorageTek ACSLS library
- Loads the first tape drive
- Verifies the loaded tape drive
- Receives tape drive connection verification
- Unloads the first tape drive
- Repeats this verification process for each tape drive
- Reports the tape drive information on the Drive Configuration dialog

**Note:** The automatic library configuration method does not support a mixture of different types of tape volumes.

## Configure your Library Tape Drives Automatically

This section gives you the procedure to configure the tape drives automatically. Use this method if all drives within your StorageTek ACSLS library use the same type of media.

### **To use the automatic library configuration method**

1. Select the library automatic configuration method.
2. Click Next.  
The automatic library configuration process is initiated.
3. Click Next.  
The Volume Configuration dialog opens showing a list of unassigned tape volumes.

## How You Configure Library Tape Volumes

Configuring your tape volumes consists of assigning tape volumes to create the logical library on the CA ARCserve Backup server. Review your tape volume assignment plan before you assign the tape volumes.

After you configure the tape drives, all tape volumes in the StorageTek ACSLS library are shown in the Volume Configuration dialog. Initially, the tape volumes are not assigned to the CA ARCserve Backup server. The unassigned status is indicated by a red slash through the tape volume icon.

### **More Information:**

[StorageTek ACSLS](#) (see page 45)

## Configure the Logical Library

You can configure the logical library by assigning tape volumes to the CA ARCserve Backup server.


### **To configure your logical library**

1. Select one or more tape volumes.

**Note:** Press and hold the Ctrl key to select multiple tape volumes.

2. Right-click the selected tape volumes, and then select Assign.

The selected tape volumes are assigned to the CA ARCserve Backup server, as indicated by the tape volume icon (no red slash):



3. Click Next.

A message reminds you to take an inventory of the StorageTek ACSLS library.

4. Click OK.

The message dialog closes and a summary dialog opens to show the library tape drive configuration.

5. Click Finish.

A message appears to confirm your successful library configuration.

6. Click Exit.

The Install Summary dialog opens.

## Configure the Cleaning Volume

The cleaning tape volume is shared between backup servers when the backup servers are in a SAN, just as they share the same volume configuration for non-cleaning tape volumes. If the backup servers are not in a SAN, then each backup server has an assigned cleaning volume.

### To configure the cleaning tape volume

1. Open the StorageTek ACSLS Volume Configuration dialog, browse to the StorageTek ACSLS library and select a tape volume.
2. Right-click the tape volume and select Mark/Unmark Cleaning Cartridge from the pop-up menu.

The selected tape volume is marked as the cleaning cartridge.

### **To configure more cleaning tape volumes**

1. Ensure that the StorageTek ACSLS library is properly configured and initialized.
2. Open the Device Manager window.
3. Browse to and right-click the StorageTek ACSLS library. Select Library Properties from the pop-up menu.  
The Library Properties dialog opens.
4. Select the Cleaning tab.
5. Select the desired cleaning tapes and click OK.  
The Library Properties dialog closes. You have successfully configured the cleaning tape volumes.

### **Take Inventory of Slots**

To enable CA ARCserve Backup to recognize changes in tape volume assignments, you must take an inventory of slots in the tape library affected by tape volume assignment changes.

### **To take inventory of slots**

1. Log on to CA ARCserve Backup on the computer running the option.
2. Start CA ARCserve Backup.
3. Select Device from the CA ARCserve Backup home page.
4. Select the logical library.
5. Right-click the selected logical library, and select Inventory/Offline Slots.  
The Inventory/Offline Slots dialog opens to show the tape volumes in the tape library.
6. Click to select the slots in the option affected by tape volume assignment changes.
7. Click Quick Inventory.
8. Click OK.  
The inventory complete message appears.
9. Click OK.

### **Post-Installation Procedures**

The post-installation tasks consist of verifying the pre-installation tasks and making changes to the library configuration.

## How Library Configuration Updating Works

Library configuration involves tape drive configuration and tape volume assignment. Whenever you add or remove tape drives or change your tape volume assignments on the tape library, you must update the library configuration with these changes.

**Important!** You must stop the Tape Engine service to update the library configuration when tape drive and tape volume changes.

### Update Device Configuration

You can update the library configuration with changes to tape drives by using the Enterprise Module Configuration Wizard on the CA ARCserve Backup server. Before you reconfigure your library, you must remove all tape volumes from the tape drives in the tape library. When you configure the device, all the tape volumes in the tape library are read and initialized.

**Note:** Removing the tape volumes from the tape drives simplifies the device configuration. Since the Enterprise Tape Library 3494 can be shared among multiple backup servers on the network, tape volumes may be assigned to other backup servers. Not all tape volumes are assigned to the CA ARCserve Backup server.

#### To update the library configuration with tape drive changes

1. Log on with administrator privileges to CA ARCserve Backup on the computer running the option.
2. Click Start, Programs, CA, ARCserve Backup, Enterprise Module Configuration.  
The Enterprise Module Configuration dialog opens.
3. Click IBM 3494 or StorageTek ACSLS.  
A message appears reminding you to remove tape volumes from all tape drives.
4. Remove tape volumes from all tape drives and click Yes to continue.  
The <IBM 3494 or StorageTek ACSLS> Library Configuration dialog opens.
5. Select the manual or automatic library configuration method and configure your library.
6. Click Next.  
The Drive Configuration dialog opens.
7. Click Next.  
This completes updating library configuration.

**More Information:**

[Library Configuration Tasks](#) (see page 62)

**Update Volume Configuration**

You can update your volume configuration with changes to tape volumes on the tape library. After any changes to the tape volumes on the tape library, use the Volume Configuration option to change your tape volume configuration, and then use the CA ARCserve Backup Device Manager to take an inventory of the device.


**Note:** The import and export of tape volumes using the option is not supported.

**To update the tape volume configuration**

1. Log on with administrator privileges to CA ARCserve Backup on the computer running the option.
2. Click Start, Programs, CA, ARCserve Backup, Enterprise Module Configuration.  
The Configure Enterprise Module window appears.
3. Click Enterprise Tape Library 3494 or StorageTek ACSLS.  
The Volume Configuration welcome dialog opens.
4. Click Next.  
A message appears to show that the Tape Engine service will be stopped.  
Click Yes to continue.
5. Click Next to continue the volume configuration.  
The Volume Configuration dialog opens to show the current tape volume configuration; assigned tape volumes are followed by unassigned tape volumes.
6. Select one or more tape volumes that you want to assign to the logical library.

**Note:** Press and hold the Ctrl key to select multiple tape volumes.

7. Right-click the selected tape volumes, and select Assign.



8. Click Next.

A message appears to remind you to take an inventory for slots in the tape library affected by tape volume assignment changes.

9. Click OK to close the message.

The Volume Configuration Completed message appears.

10. Click Exit.

11. Click Yes to confirm the exit.

12. Use CA ARCserve Backup to take an inventory of the device.

#### **More Information:**

[Detect Tape Volume Updates](#) (see page 75)

[Take Inventory of Slots](#) (see page 70)

[Library Configuration Tasks](#) (see page 62)

[Configure Library for StorageTek ACSLS](#) (see page 65)

#### **Configure the Options with File System Devices**

Use this procedure if you already have File System Devices configured on the server and you have not configured the tape library yet.

### To configure with File System Devices

1. Connect the tape drives to the system.
2. Start the Tape Engine.
3. Once you see the tape drives in the Device Manager, stop the Tape Engine.
4. Follow the steps starting with Step 2 in the section titled "Update Device Configuration".

## Using Enterprise Tape Library 3494 and StorageTek ACSLS

This section contains information about using the options. After you install and configure the options on the CA ARCserve Backup server, you can use CA ARCserve Backup to perform the following tasks on the respective option:

- Enterprise Tape Library 3494--Manage backup and restore operations
- StorageTek ACSLS
  - Manage backup and restore operations
  - Update the configuration of the virtual library on the CA ARCserve Backup server with device or tape volume changes on the StorageTek ACSLS tape library

**Note:** CA ARCserve Backup supports disaster recovery using the Enterprise Option for StorageTek ACSLS. For more information on Disaster Recovery, see the *Disaster Recovery Option Guide*.

This section also contains information about using the following options:

- Enterprise Tape Library 3494 command line interface to query the status of the Enterprise Tape Library 3494
- StorageTek ACSLS cmd\_proc utility to query the status of the tape drives and tape volumes in the StorageTek ACSLS tape library

## Backup and Restore Operations

You can manage backup and restore operations with the option as if you are controlling a local library. Use the Backup Manager to perform backup operations and the Restore Manager to perform restore operations.

**Note:** For complete details on managing backup and restore operations, see the *Administration Guide*.

## Detect Tape Volume Updates

After the initial library configuration, you can add or remove tape volumes. Before you can use tape volumes in the tape library for a logical library (for Enterprise Tape Library 3494) or a virtual library (for StorageTek ACSLS) on the CA ARCserve Backup server, you must perform the following tasks:

- Physically add tape volumes to, and remove tape volumes from, the tape library.
- Update tape volume configuration.
- Take and inventory of the device to update the CA ARCserve Backup server with the changes made to the tape volume configurations.

**Note:** You can use the CA ARCserve Backup Device Manager to view the existing tape volume assignments before adding or removing tape volumes.

Importing and exporting of tape volumes from CA ARCserve Backup is not supported with these options. Perform physical import and export of tape volumes using the tape library.

### **More Information:**

[Take Inventory of Slots](#) (see page 70)  
[Update Volume Configuration](#) (see page 72)

## Enterprise Tape Library 3494 Command Line Interface

You can use the Enterprise Tape Library 3494 command line interface to manage the Enterprise Tape Library 3494. Use the mtlb program to query device and operational status, take an inventory of tape volumes, eject tape media, and verify connectivity between the Enterprise Tape Library 3494 and the IBM Library Manager control service on the CA ARCserve Backup server.

### Query Using the mtlb Command

Use the mtlb command to query device and operational status, take an inventory of tape volumes, eject tape media, and verify connectivity between the Enterprise Tape Library 3494 and the IBM Library Manager control service on the CA ARCserve Backup server.

#### **To use the mtlb command**

1. On the CA ARCserve Backup host, open a console window.
2. Execute the mtlb command using the logical name of the Enterprise Tape Library 3494.

**Note:** The -l argument is required for each mtlb command.

## mtlib Command--Query the Enterprise Tape Library 3494

Use the mtlib command as shown below to verify the status of the Enterprise Tape Library 3494. For the purpose of these sample commands, the logical name of the Enterprise Tape Library 3494 is assumed as 3494a.

This command has the following format:

**mtlib -l 3494a [-qL | -qI | -qI -v | -DE]**

### **-qL**

(Optional) Queries the Enterprise Tape Library 3494 and provides information on the library.

### **-qI**

(Optional) Queries the Enterprise Tape Library 3494 and provides information on the tape volumes in the Enterprise Tape Library 3494.

### **-qI -v**

(Optional) Queries the Enterprise Tape Library 3494 and provides verbose information on the tape volumes in the Enterprise Tape Library 3494. The verbose information includes the state of the tape volumes, whether a volume is logical, volume class, and volume type. This command is useful to determine if a tape is mounted.

### **-DE**

Queries the Enterprise Tape Library 3494 and returns device information.

**Note:** For complete information on using the mtlib command, see the Enterprise Tape Library 3494 documentation.

## StorageTek Tape Library Queries

The StorageTek ACSLS query commands provide an alternate method for determining the status of the tape drives and the tape volumes in the StorageTek ACSLS tape library. Use the cmd\_proc utility on the StorageTek ACSLS server to query the status of the tape drives and the tape volumes in the StorageTek ACSLS tape library.

## Query the Status of Tape Drives

The command, *query drive all*, provides information about the tape volumes, the tape drives, their state, their status, and their type in the StorageTek ACSLS tape library.

### To query the status of the tape drives

1. Start the cmd\_proc utility.
2. Enter

```
query drive all
```

The command displays the following information:

2004-03-18 12:51:31		Drive Status		
Identifier	State	Status	Volume	Type
0, 0, 0, 0	online	available		SGT-LTO
0, 0, 0, 1	online	available		SGT-LTO
0, 0, 0, 2	online	available		SGT-LTO
0, 0, 0, 3	online	available		SGT-LTO

The identifier consists of four digits, which represent the following:

- Automated Cartridge System (ACS)
- Logical Silo Module (LSM)
- Panel number (Panel)
- Drive ID number (ID)

In the preceding example, "0, 0, 0, 0" on the first line translates to ACS = 0, LSM = 0, Panel = 0, ID = 0 while "0, 0, 0, 3" on the fourth line translates to ACS = 0, LSM = 0, Panel = 0, Drive ID = 3.

## Query the Status of Tape Volumes

The command, *query volume all*, provides information about the tape volumes, their status, their current location, and their type in the StorageTek ACSLS tape library.

### To query the status of the tape volumes

1. Start the cmd\_proc utility.
2. Enter

```
query volume all
```

The command displays the following information:

2004-03-18 13:05:04		Volume Status	
Identifier	Status	Current Location	Type
000091	home	0, 0, 4, 0, 0	LTO-100G
000092	home	0, 0, 2, 3, 0	LTO-100G
000093	home	0, 0, 2, 1, 0	LTO-100G
000094	home	0, 0, 3, 0, 0	LTO-100G
000095	in drive	0, 0, 0, 0	LTO-100G
000096	ejected	0,-1, 0, 0, 0	LTO-100G
000097	ejected	0,-1, 0, 0, 0	LTO-100G

# Appendix A: Troubleshooting

---

This appendix provides troubleshooting information to help you resolve issues that you can encounter in the Enterprise Module options.

You can encounter job failures and errors while performing backup and restore operations. To check the problems that can occur, select the Activity Log tab in the Job Status Manager.

The Activity Log contains time-stamped events with applicable error descriptions. Error incidents have the prefix E followed by a number (for example, E11018).

This section contains the following topics:

[Backup Process is Slow \(see page 79\)](#)

[Image Option: Drive Cannot be Frozen \(see page 80\)](#)

[Enterprise Tape Library 3494: Drives Cannot be Mapped to the Library \(see page 81\)](#)

[Serverless Backup Option: Drive Locking Problems \(see page 81\)](#)

## Backup Process is Slow

### **Symptom:**

The backup process is very slow.

### **Solution:**

The most common reasons and solutions for which a backup process may be slow are:

#### **■ Slow processor**

Older computers have slow processors and may not be able to handle the volume of data processed during the backup and restore process. This is normal if you have an older computer with a slow processor. If your computer is up-to-date, check your hardware performance and reboot your computer.

#### **■ Poor processor performance**

Check your hardware performance and reboot your computer.

#### **■ Open applications**

You may have applications running that use excessive processing power. Close all of your applications before you begin the backup and restore process.

## Image Option: Drive Cannot be Frozen

### **Symptom:**

The drive cannot be frozen during a backup operation.

**Note:** This problem is specific to Image Option.

### **Solution:**

If there is any activity on the drive, the CA ARCserve Backup Image Option may not be able to freeze the drive. The following occurs if the drive cannot be frozen during a backup operation:

- If the drive does not freeze, and the Continue with Backup option has been selected for the freeze fail action, the option tries to lock the drive for exclusive access.
- If the drive cannot be locked and you change any data, the backup data may be inconsistent and unusable.

The drive cannot be locked for the following reasons:

- Windows Explorer has this drive expanded. Make sure the drive is not expanded.
- An MS-DOS command prompt dialog is opened with this drive letter. Close the MS-DOS command prompt dialog associated with the drive letter.
- An application has opened a file on the drive. Make sure you close all applications that may open a file on the drive that you are backing up.

## Enterprise Tape Library 3494: Drives Cannot be Mapped to the Library

### **Symptom:**

Drives cannot not be mapped to the library.

**Note:** This problem is specific to the Enterprise Option for IBM 3494.

### **Solution:**

The reason for drives not being mapped to the library could be a registry entry, named Device Name.

### **To determine if drives are mapped**

1. Click Settings, Control Panel, Administrative Tools, Computer Management, Device Manager.
2. Locate the IBM tape drives that are connected to the server from Enterprise Tape Library 3494.
3. If the tape drives appear under Other Drives, then you must download and install the latest device drivers for the tape drives from the IBM website.

## Serverless Backup Option: Drive Locking Problems

### **Symptom:**

Sometimes the drive lock fails.

**Note:** This problem is specific to the Serverless Backup Option.

### **Solution:**

During a serverless backup or restore operation, the option attempts to lock the drive before the backup or restore process begins. Under the following circumstances, the lock fails and therefore the backup or restore job also fails:

- The drive is expanded in Windows Explorer. Make sure the drive is not expanded.
- An MS-DOS command prompt dialog is opened with this drive letter. Close the MS-DOS command prompt dialog associated with the drive letter.
- An application has opened a file on the drive. Make sure you close all applications that may open a file on the drive that you are backing up.



# Index

---

## A

ACS, automated cartridge system • 66  
adding  
    tape drives • 71  
    tape volumes • 72  
architecture  
    example of mutually exclusive tape volumes  
        • 48  
    exclusive tape volume communication  
        interfaces • 48  
    mutually exclusive tape volumes • 47  
    SAN communication interface • 43, 52  
    SAN example • 43, 52  
    StorageTek ACSLS • 45  
    StorageTek ACSLS library • 45  
assigning tape volumes • 48  
    initial procedure • 62, 68  
    update • 72  
Automated Cartridge System, ACS • 66  
automatic library configuration • 67

## B

backing up  
    drive locking failure • 81  
    restrictions • 29  
backup data using Backup Manager  
    Image Option • 17  
    Serverless Backup Option • 31  
backup operations  
    Enterprise Tape Library 3494 • 74  
    serverless • 27  
backup operations, centralized • 26  
backup operations, traditional • 26  
backup server, adding • 40

## C

centralized backup • 26  
cluster size, NTFS • 28  
cmd\_proc • 76  
communication interfaces  
    control path • 61  
    StorageTek ACSLS • 46  
    StorageTek ACSLS components • 61  
configuration dependencies • 56  
configuring library

tape volume assignments • 68  
updating changes to Enterprise Tape Library  
    3494 • 71  
    updating changes to StorageTek ACSLS • 71  
configuring library automatically • 68  
configuring library manually • 65  
configuring the library • 65  
    during installation • 62  
    manually enter tape drive parameters • 66  
configuring, logical library • 65  
control path • 46

## D

data movers, serverless backup • 27  
data path • 46  
Destination tab • 17  
Device Configuration Wizard • 71  
differential backup restriction • 29  
directories, restoring • 34  
drive  
    locking problems • 81  
    restoring • 33  
Drive ID number tape drive parameter • 66

## E

Ethernet LAN control path • 46  
extended copy command • 27

## F

features, Serverless Backup Option • 28  
fibre channel data path • 46  
File Conflict Resolution • 22  
files and directories, restoring • 34  
full volume backup, results • 28  
full volume restore • 28

## G

global backup option restrictions • 29  
global restore option restrictions • 29  
Global restore options not supported • 22

## I

IBM Automated Tape Library Service • 57  
IBM library configuraiton file • 58  
ibmatl.conf library configuration file • 58

---

Image Option • 11  
incremental backup restriction • 29  
installation  
    configuration dependencies • 56  
    library configuration • 65  
installation prerequisites  
    Enterprise Option for IBM 3494 • 56  
    Serverless Backup option • 30  
installation procedure  
    Enterprise option for IBM 3494 • 62  
    Serverless Backup option • 30  
StorageTek ACSLS see Enterprise Option for  
    IBM 3494 • 62  
installing  
    Enterprise Option for IBM 3494-taking  
        inventory • 70  
installing the option  
    configuring the library • 62  
inventory, slot changes  
    Enterprise Tape Library 3494 • 70  
    StorageTek ACSLS • 70

## J

job failure, drive locking problem • 81  
Job Properties dialog • 19  
Job Properties, displaying • 19

## L

Library Attach software • 61  
library configuration file • 58  
library configuration file format • 58  
library configuration methods • 65  
    automatic • 67  
    manual • 65  
locking problems, drive • 81  
Logical Silo Module, LSM • 66  
LSM, Logical Silo Module • 66

## M

message packets • 61  
mtlib command • 75

## N

network interface, ACSLS • 61  
NTFS partition cluster size • 28

## O

operational considerations • 28

overwrite behavior during restore • 28, 33

## P

Panel tape drive parameter • 66  
problems, drive locking • 81

## Q

query Enterprise Tape Library 3494 • 75  
querying ACSLS tape volumes • 78  
querying the ACSLS • 76  
querying the ACSLS tape drives • 77

## R

RAID Option, interaction • 28  
recognizing tape volume changes • 75  
removing tape volumes • 75  
restore by file • 22  
restore by image • 22  
Restore by Image/Serverless option,  
    restrictions • 29, 33  
Restore by Media, limitation • 28  
restore methods • 22  
restore registry files and event logs • 22  
restore restrictions • 29  
restore selected file • 28  
restoring  
    drive • 23, 33  
    drive locking failure • 81  
    Enterprise Tape Library 3494 • 74  
    individual files • 24, 34  
    Serverless Backup Option • 33  
restoring by backup media • 22  
restrictions  
    backup • 29  
    global option • 29  
    operational • 28  
    restore • 29  
running backup and restore jobs • 15

## S

SAN • 43, 52  
    architecture • 52  
    data path • 46  
    fiber attached tape drives • 46  
    logical library configuration example • 44, 53  
    shared tape volumes • 43  
SAN (Storage Area Network) • 26  
SCSI data path • 46  
Serverless Backup Option

---

- benefits • 25
- diagram • 27
- features • 28
- introduction • 25
- operational considerations • 28
- restore selected file • 28
- restoring • 33
- restrictions • 28
- slots, inventory of changes
  - Enterprise Tape Library 3494 • 70
  - StorageTek ACSLS • 70
- Snapshot Feature • 13
- Source tab • 17
  - computer node • 17
  - disk node • 17
- SSI, Storage Server Interface on ACSLS • 61
- Storage Server Interface (SSI) on ACSLS • 61
- StorageTek ACSLS volume configuration • 72

## T

- tape drive
  - entering parameters for manual configuration • 66
- tape drive parameters • 66
- tape drives • 46
  - changes • 71
  - configuring automatically • 68
  - configuring manually • 66
  - physical connections • 46
  - querying the status • 77
- Tape RAID Option, interaction • 28
- tape volumes
  - assigning • 62, 68, 72
  - assignment changes, StorageTek ACSLS • 70
  - configuration example • 44, 49, 53
  - movement • 61
  - mutually exclusive set • 40, 47
  - planning • 40, 48
  - querying the status • 78
  - recognizing assignment changes • 70
  - shared in SAN • 43
- traditional backup • 26
- troubleshooting • 79

## U

- updating
  - device configuration • 71
  - library configuration • 71
  - volume configuration • 72

- using Quick Inventory to detect tape volume changes • 70
- StorageTek ACSLS • 70

## V

- virus scanning
  - delete • 22
  - enable • 22
  - rename • 22
  - skip • 22
- virus scanning, restriction • 29

## W

- wizard, Device Configuration • 71