

CA IDMS 19.0
CA RS 2105 Service List

1

Service	Description	Type
LU00103	SQL QUERY USING VIRTUAL KEYS MAY INCORRECTLY RECEIVE 0326	PTF
LU00160	EXCESSIVE RLES ALLOCATED REPEATEDLY LINKING TO SAME PROGRAM	PTF
LU00604	U3964 AT STARTUP AFTER DC200185	PTF
LU00620	ZIIP ENABLED CV SOE0-30 ABEND OR S23E-08 ABEND SHUTDOWN	PTF
LU00631	PROGRAM CHECK IN IDMSHLDB WITH LU00346 AND TRACING ENABLED	PTF
LU00660	CONFUSING MESSAGE REGARDING TIME WHEN ARCHIVING JOURNALS.	PTF
LU00800	NEW MESSAGES ADDED TO IDDXI5J0	PTF
SO14629	SYSGEN SYSTEM SYNTAX TO ADD A CUSHION FOR POOL 255	PTF
The CA RS 2105 service count for this release is 8		

CA IDMS
CA RS 2105 Service List for CAGJJ00

2

FMID	Service	Description	Type
CAGJJ00	LU00103	SQL QUERY USING VIRTUAL KEYS MAY INCORRECTLY RECEIVE 0326	PTF
	LU00160	EXCESSIVE RLES ALLOCATED REPEATEDLY LINKING TO SAME PROGRAM	PTF
	LU00604	U3964 AT STARTUP AFTER DC200185	PTF
	LU00620	ZIIP ENABLED CV S0E0-30 ABEND OR S23E-08 ABEND SHUTDOWN	PTF
	LU00631	PROGRAM CHECK IN IDMSHLDB WITH LU00346 AND TRACING ENABLED	PTF
	LU00660	CONFUSING MESSAGE REGARDING TIME WHEN ARCHIVING JOURNALS.	PTF
	LU00800	NEW MESSAGES ADDED TO IDDXI5J0	PTF
	SO14629	SYSGEN SYSTEM SYNTAX TO ADD A CUSHION FOR POOL 255	PTF
The CA RS 2105 service count for this FMID is 8			

CA IDMS 19.0
CA RS 2105 - PTF LU00103 Details

3

Service	Details
LU00103	LU00103 M.C.S. ENTRIES = ++PTF (LU00103) SQL QUERY USING VIRTUAL KEYS MAY INCORRECTLY RECEIVE 0326 PROBLEM DESCRIPTION: An SQL query that references more than one table of the same name may receive an unexpected 0326 error. The error can occur when using a virtual key schema accessing a record that does not contain owner pointers. The error can also occur when accessing a view that contains a table of the same name. SYMPTOMS: The query will abend with a DB001031 error: IDMS DB001031 C-7M321: DB error 0326; Tbl:table, Area:area ErrSet:error-set, ErrTbl:table, ErrArea:area IMPACT: The query will abend with a DB001031 error. CIRCUMVENTION: If the query is accessing a view, create a new view with a name that is different from any of the tables referenced in the view. PRODUCT(S) AFFECTED: CA IDMS Base Option Version 19.0 Related Problem: IDMS 12706 Copyright (C) 2021 CA. All rights reserved. R00702-AGJ190-SP2 DESC(SQL QUERY USING VIRTUAL KEYS MAY INCORRECTLY RECEIVE 0326). ++VER (Z038) FMID (CAGJJ00) PRE (R080871 R081289 R089206 R090312 R092114 R092366 R095296 R098684 S006940 S007829 S008356 S013172 S013926) SUP (LT00103 LT00346 LT00631 LU00346 LU00631 R080063 R083920 R088004 R090917 R092877 R094036 S006860 S007112 S009947 ST06860 ST07112 ST09039 ST09947 ST15882 TR80063 TR83920 TR87399 TR88004 TR90917 TR92877 TR94036)

CA IDMS 19.0
CA RS 2105 - PTF LU00160 Details

4

Service	Details
LU00160	LU00160 M.C.S. ENTRIES = ++PTF (LU00160) EXCESSIVE RLES ALLOCATED REPEATEDLY LINKING TO SAME PROGRAM PROBLEM DESCRIPTION: A program called over and over again may be loaded subsequently the same number of times for the same task and therefore, triggering an excessive allocation of RLEs (Resource Link Elements). This fix corrects the problem by checking that the program is already loaded and linked to the task resource elements before attempting to link it again. SYMPTOMS: The following is an example of the message displayed multiple times when the problem occurs: IDMS DC010007 Vn Tnnn THE NUMBER OF RLE'S HAS BEEN INCREASED TO nnnnn. IMPACT: After some time, the system may crash. CIRCUMVENTION: None. PRODUCT(S) AFFECTED: CA IDMS Base Option Version 19.0 Related Problem: IDMS 5636 Copyright (C) 2021 CA. All rights reserved. R00703-AGJ190-SP2 DESC (EXCESSIVE RLES ALLOCATED REPEATEDLY LINKING TO SAME PROGRAM) . ++VER (Z038) FMID (CAGJJ00) PRE (R079192 R081872 R092068 R092573 R095344) SUP (LT00160 R083099 R084550 ST14929 TR83099 TR84550)

Service	Details
LU00604	LU00604 M.C.S. ENTRIES = ++PTF (LU00604) U3964 AT STARTUP AFTER DC200185 PROBLEM DESCRIPTION: The customer upgraded their z system from z13 to z15 and then shutdown their IDMS CV. When they attempted to start and bring up their IDMS CV it abended with a U3964 after the message DC329011 All Transactions Recovered. It appears that during the resynchronization process we reference an address of all 0's in the "Low Core"/PSA address space that we should not be referencing. When the customer upgraded their systems, the Low Core 0 value's fields that were not being used was being filled in with nonzero values which caused us to point to an the address with random values. SYMPTOMS: The IDMS CV will Abend with a U3964 after the message DC329011 All Transactions Recovered. IMPACT: Customer cannot bring up their IDMS CV. CIRCUMENTION: None. PRODUCTS AFFECTED: CA IDMS Release 19.0 Related Problem: IDMS 5618 Copyright (C) 2021 CA. All rights reserved. R00709-AGJ190-SP2 DESC(U3964 AT STARTUP AFTER DC200185). ++VER (Z038) FMID (CAGJJ00) SUP (LT00604)

Service	Details
LU00620	LU00620 M.C.S. ENTRIES = ++PTF (LU00620) ZIIP ENABLED CV SOE0-30 ABEND OR S23E-08 ABEND SHUTDOWN PROBLEM DESCRIPTION: This PTF contains solutions for two distinct problems. 1) After applying 19.0 PTF S006651 (ADS zIIP Enablement) apars from the S1912 Pax file which includes the ADS zIIP Enablement code, a CV hang or SOE0-30 abend can occur during an ADS task abend, if zIIP has been disabled temporarily on the CV. 2) A rare S23E-08 abend can occur at CV shutdown on a multitasking CV. SYMPTOMS: 1) During an ADS task abend message DC027007 <ADS task code and dialog name> abended with code <nnn> is issued and the zIIP enabled CV hangs. A SOE0-30 abend (linkage stack full) can also occur during an ADS task abend if zIIP has been disabled temporarily on the CV. The following messages are displayed (partial display): CCSR010E RHDCOS00 SOE0 at 000170E2 LMOD IDMSDC CSECT RHDCOESA CCSR021I OWNER = CA IDMS R19.0 CCSR022I MODULE = RHDCOESA FMID = CAGJJ00 RMID = S008156 CCSR060I BREAKING EVENT ADDRESS: 00000000 000170A2 CCSR061I PSW: 07851E00 80000000 00000000 000170E2 CCSR067I COMPLETION CODE SOE0 REASON CODE 00000030 Note: RMID and instruction addresses may vary for the 19.0 CV. 2) Shutdown of a multitasking CV abends S23E-08 with the following messages: IEA995I SYMPTOM DUMP OUTPUT SYSTEM COMPLETION CODE=23E REASON CODE=00000008 IMPACT: 1) If the zIIP enabled CV hangs then it must be cancelled and restarted. The SOE0-30 (linkage stack full) abend is an IDMS internal error resulting in the abend of the zIIP enabled CV. 2) CV shutdown does not complete and some external rununits may not terminate normally after the S23E-08 abend occurs. CIRCUMVENTION: 1) Disable zIIP processing by specifying as a CV startup parameter ZIIP=N. Do not issue the DCMT VARY ZIIP OFF command after the zIIP enabled CV is up as this can result in the SOE0-30 abend if executing ADS tasks. 2) There is no circumvention for the S23E-08 abend. PRODUCTS AFFECTED: CA IDMS Base Option Version 19.0 Related Problem: IDMS 5666 Copyright (C) 2021 CA. All rights reserved. R00710-AGJ190-SP2 DESC(ZIIP ENABLED CV SOE0-30 ABEND OR S23E-08 ABEND SHUTDOWN). ++VER (Z038) FMID (CAGJJ00) PRE (R079192 R080760 R081229 R081872 R083713 R090447 R092068 R092366 R092573 R094240 R095151 R095344 R096807 R099627 S006651 S007073 S007191 S008156

CA IDMS 19.0
CA RS 2105 - PTF LU00620 Details

7

Service	Details
	SO12628 SO14305) SUP (AR81229 AS01055 LT00050 LT00160 LT00620 LU00160 RI82705 R078935 R079109 R079685 R082708 R083099 R084550 R088217 R089987 R091223 R092599 R094476 R094965 R096320 R097235 R098122 SI04932 S001055 S004934 S010951 S012950 S012964 ST00900 ST01055 ST01058 ST04193 ST04934 ST05719 ST10820 ST10951 ST12805 ST12950 ST12964 ST14929 TR78935 TR79109 TR79685 TR82708 TR83099 TR84550 TR88217 TR89987 TR91223 TR91485 TR92599 TR94476 TR94965 TR96320 TR97235 TR98122) ++HOLD (LU00620) SYSTEM FMID(CAGJJ00) REASON (ACTION) DATE (21091) COMMENT (+-----+ CA IDMS Base Option Version 19.0 +-----+ SEQUENCE After Apply +-----+ PURPOSE Update Messages. +-----+ USERS AFFECTED All IDMS users. +-----+ KNOWLEDGE REQUIRED Update definitions in the Dictionary. +-----+ ACCESS REQUIRED Ability to run IDMSDDDL in batch or use IDD online. +-----+ ***** * STEPS TO PERFORM * ***** After installing this PTF, please use the IDMSDDDL utility to update your SYSTEM dictionary's message area with the input in source member ABEND002 DIC. Please note using this member will result in the update of all messages contained within ABEND002 DIC. You may optionally decide to only update the specific message(s) associated with this correction. To do this simply include message ABND3951 as input to the IDMSDDDL utility. The source will be in the SMP/E CAGJSRC library.).

Service	Details
LU00631	LU00631 M.C.S. ENTRIES = ++PTF (LU00631) PROGRAM CHECK IN IDMSHLDB WITH LU00346 AND TRACING ENABLED PROBLEM DESCRIPTION: After application of LU00346, if internal tracing is enabled using CSALMGR1, CSALMGR3 or CSALMGR7, a random abend can occur in the module IDMSHLDB. SYMPTOMS: A task is abended by IDMS for some underlying reason. During task cleanup, a program check in IDMSHLDB at offset 00CE70 can occur if certain tracing options are enabled. IMPACT: The most probable result is a 3970 abend of the IDMS CV. It is possible, however, that only the requested abend of the task can occur. CIRCUMVENTION: Do not run CV with CSALMGR1, CSALMGR3 or CSALMGR7 enabled until a solution is available. PRODUCT(S) AFFECTED: CA IDMS Base Option Version 19.0 Related Problem: IDMS 13185 Copyright (C) 2021 CA. All rights reserved. R00711-AGJ190-SP2 DESC (PROGRAM CHECK IN IDMSHLDB WITH LU00346 AND TRACING ENABLED) . ++VER (Z038) FMID (CAGJJ00) PRE (R080871 R081289 R089206 R090312 R092114 R092366 R095296 R098684 S006940 S007829 S008356 S013172 S013926) SUP (LT00346 LT00631 LU00346 R080063 R083920 R088004 R090917 R092877 R094036 S006860 S007112 S009947 ST06860 ST07112 ST09039 ST09947 ST15882 TR80063 TR83920 TR87399 TR88004 TR90917 TR92877 TR94036)

CA IDMS 19.0
CA RS 2105 - PTF LU00660 Details

9

Service	Details						
LU00660	LU00660 M.C.S. ENTRIES = ++PTF (LU00660) CONFUSING MESSAGE REGARDING TIME WHEN ARCHIVING JOURNALS. PROBLEM DESCRIPTION: When the local time is set back to come off daylight savings time, Archive Journal may put out a message indicating the local time in one journal record is lower than a prior journal record. This message does not make it clear that the time is local and this may cause confusion as to the integrity of the archive file and what to do about it. The Archive Journal is valid for recovery, but there may be some issues if a local time is used as a START or STOP time in the overlapping hour. If this archive is used for ROLLFORWARD or ROLLBACK it is recommended to use the UTC keyword and specify a UTC START or STOP time. This fix replaces the old text-only message with a new UT014006 numbered message that makes it clear only the local time is affected, and the new message will be documented on techdocs.broadcom.com. SYMPTOMS: When running Archive Journal following a change in local time the jobs can receive message: ***WARNING*** DATE/TIME IN J-REC EARLIER THAN DATE/TIME IN PREVIOUS J-REC". IMPACT: No functional impact. Users may think their journal are lacking integrity when in fact they are good. CIRCUMVENTION: When using an Archive Journal for recovery which had this warning, specify the START or STOP times using the UTC keyword. PRODUCT(S) AFFECTED: CA IDMS Base Option Version 19.0 Related Problem: IDMS 13220 Copyright (C) 2021 CA. All rights reserved. R00713-AGJ190-SP2 DESC(CONFUSING MESSAGE REGARDING TIME WHEN ARCHIVING JOURNALS.). ++VER (Z038) FMID (CAGJJ00) PRE (R085839 R087776 R093872 R098995) SUP (GC79102 LT00660 NC79102 R080160 R090926 R091328 SO08436 ST08436 TR80160 TR90926 TR91328) ++HOLD (LU00660) SYSTEM FMID(CAGJJ00) REASON (ACTION) DATE (21091) COMMENT (<table border="1"> <tr> <td>CA IDMS Base Option</td><td>Version 19.0</td></tr> <tr> <td>SEQUENCE</td><td>After Apply</td></tr> <tr> <td>PURPOSE</td><td>Update Messages</td></tr> </table>	CA IDMS Base Option	Version 19.0	SEQUENCE	After Apply	PURPOSE	Update Messages
CA IDMS Base Option	Version 19.0						
SEQUENCE	After Apply						
PURPOSE	Update Messages						

Service	Details
	<pre> USERS AFFECTED All IDMS users +-----+ KNOWLEDGE REQUIRED Update definitions in the Dictionary +-----+ ACCESS REQUIRED Ability to run IDMSDDDL in batch or use IDD online +-----+ ***** * STEPS TO PERFORM * ***** After installing this PTF, please use the IDMSDDDL utility to update your SYSTEM dictionary's message area with the input in source member UT000. Please note using this member will result in the update of all messages contained within UT000. You may optionally decide to only update the specific message associated with this correction. To do this simply include message UT014006 as input to the IDMSDDDL utility. The source will be in the SMP/E CAGJSRC library.).</pre>

CA IDMS 19.0
CA RS 2105 - PTF LU00800 Details

11

Service	Details						
LU00800	LU00800 M.C.S. ENTRIES = ++PTF (LU00800) NEW MESSAGES ADDED TO IDDXI5J0 PROBLEM DESCRIPTION: Element IDDXI5J0 contains a list of messages and modules which have changed since 18.5. This member is used by CAISAG during an upgrade from 18.5 to 19.0 to only update changed members. This fix adds new messages to bring the list current. PRODUCT(S) AFFECTED: CA IDMS Base Option Version 19.0 Keyword(s): <table><tr><td>ABND3951</td><td>MESSAGES</td><td>CAISAG</td></tr><tr><td>19.0</td><td>IDMS/5666</td><td>IDDXIJ50</td></tr></table> Related Problem: IDMS 13277 Copyright (C) 2021 CA. All rights reserved. R00717-AGJ190-SP2 DESC(NEW MESSAGES ADDED TO IDDXI5J0). ++VER (Z038) FMID (CAGJJ00) PRE (R093158 S000341 S007404 S007598) SUP (LT00800 S001076 S008006 S009990 S010889 S012360 S012399 S013488 S014268 ST01076 ST08006 ST09990 ST10889 ST12360 ST12399 ST13488 ST14268)	ABND3951	MESSAGES	CAISAG	19.0	IDMS/5666	IDDXIJ50
ABND3951	MESSAGES	CAISAG					
19.0	IDMS/5666	IDDXIJ50					

Service	Details
S014629	M.C.S. ENTRIES = ++PTF (S014629) SYSGEN SYSTEM SYNTAX TO ADD A CUSHION FOR POOL 255 PROBLEM DESCRIPTION: There is no SYSGEN syntax to specify a cushion for subpool 255. SYMPTOMS: XA storage subpool 255 defaults to having a cushion size of 0. IMPACT: A cushion must be manually specified by issuing a DCMT command. CIRCUMVENTION: Issue DCMT VARY STORAGE POOL 255 CUSHION <cushion-size> command. PRODUCTS AFFECTED: CA IDMS Base Option Version 19.0 Related Problem: IDMS 5644 Copyright (C) 2021 CA. All rights reserved. R00657-AGJ190-SP2 DESC(SYSGEN SYSTEM SYNTAX TO ADD A CUSHION FOR POOL 255). ++VER (Z038) FMID (CAGJJ00) PRE (R080760 R093347 S006940 S007073 S007191 S009820 S012292) SUP (R096754 ST14629 TR96754) ++HOLD (S014629) SYSTEM FMID(CAGJJ00) REASON (ACTION) DATE (21084) COMMENT (<pre>+-----+ CA IDMS Base Option Version 19.0 +-----+-----+ SEQUENCE After Apply +-----+-----+ PURPOSE To describe the functionality included in this PTF +-----+-----+ USERS Those using the online or batch SYSGEN compilers AFFECTED +-----+-----+ KNOWLEDGE How to use the online or batch SYSGEN compilers REQUIRED +-----+-----+ ACCESS Access to a Central Version's SYSTEM Dictionary REQUIRED Authority to use the online or batch SYSGEN compilers +-----+-----+ ***** * STEPS TO PERFORM * ***** This PTF adds a new subparameter to the SYSGEN SYSTEM XA STORAGE statement. 'CUShion is = <cushion-amount>' can be used to define a storage cushion for subpool 255. The SYSGEN must be generated and the Central Version cycled for this cushion to be in effect. SYSTEM statement XA STOrage syntax: >-+-----+>< +- XA STOrage +- pool is +- 0 <-----+--+ </pre>

Service	Details	
	<pre> +- xa-storage-pool-size -----+ +- DYnamic EXPansion is +- OFF <-----++ +- ON ---++ +- CUShion is +- 0 <-----++ +- cushion-size --+). MCS LU00103 STARTS ON PAGE 0002 MCS LU00160 STARTS ON PAGE 0002 MCS LU00604 STARTS ON PAGE 0003 MCS LU00620 STARTS ON PAGE 0004 MCS LU00631 STARTS ON PAGE 0006 MCS LU00660 STARTS ON PAGE 0007 MCS LU00800 STARTS ON PAGE 0009 MCS SO14629 STARTS ON PAGE 0010 </pre>	

CA IDMS 19.0
CA RS 2105 Product/Component Listing

14

Product Family	Product	Release
Database	CA IDMS BASE OPTION	19.00.00
The CA RS 2105 Product/Component Count for this release is 1		

CA IDMS 19.0
All CA RS Levels Service List

CA RS Level	Service	FMID
CAR2105	S014629	CAGJJ00
	LU00800	CAGJJ00
	LU00660	CAGJJ00
	LU00631	CAGJJ00
	LU00620	CAGJJ00
	LU00604	CAGJJ00
	LU00160	CAGJJ00
	LU00103	CAGJJ00
CAR2104	S015100	CAGJJ00
	LU00444	CAGJJ00
	LU00346	CAGJJ00
	LU00229	CAGJJ00
CAR2103	S015759	CAGJJ00
	LU00069	CAGJJ00
	LU00042	CAGJJ00
CAR2102	S015370	CAGJJ00
CAR2101	S015666	CAGJJ00
	S015663	CAGJJ00
	S015643	CAGJJ00
	S015642	CAGJJ00
	S015025	CAGJJ00
	S014627	CAGJJ00
	LU00027	CAGJJ00
	LU00022	CAGJJ00
	LU00020	CAGJJ00
CAR2012	S015638	CAGJJ00
	S015611	CAGJJ00
	S015493	CAGJJ00
	S015332	CAGJJ00
	S013854	CAGJJ00
CAR2011	S015089	CAGJJ00
	S015041	CAGJJ00
	S014798	CAGJJ00
	S014503	CAGJJ00
CAR2010	S014691	CAGJJ00
	S014636	CAGJJ00
	S014605	CAGJJ00
	S014305	CAGJJ00
	S013295	CAGJJ00
	S012390	CAGJJ00
CAR2009	S014268	CAGJJ00
CAR2008	S014181	CAGJJ00
	S013926	CAGJJ00
	S013831	CAGJJ00
	S013449	CAGJJ00
	S012964	CAGJJ00
	S012825	CAGJJ00

CA IDMS 19.0
All CA RS Levels Service List

CA RS Level	Service	FMID
	S012811	CAGJJ00
	S012810	CAGJJ01
	S012734	CAGJJ00
CAR2007	S013488	CAGJJ00
	S013345	CAGJJ00
	S013172	CAGJJ00
	S012206	CAGJJ00
	S012008	CAGJJ00
CAR2006	S013164	CAGJJ00
	S012950	CAGJJ00
	S012798	CAGJJ00
	S012755	CAGJJ00
	S012693	CAGJJ00
	S012009	CAGJJ01
	S011859	CAGJJ00
CAR2005	S012628	CAGJJ00
	S012383	CAGJJ00
	S012379	CAGJJ00
	S012104	CAGJJ00
	S011961	CAGJJ00
	S010291	CAGJJ00
	S009998	CAGJJ00
	S009657	CAGJJ00
CAR2004	S012434	CAGJJ00
	S012399	CAGJJ00
	S012360	CAGJJ00
	S012292	CAGJJ00
	S012262	CAGJJ00
	S012198	CAGJJ00
	S011908	CAGJJ00
	S011556	CAGJJ00
	S010951	CAGJJ00
	S009336	CAGJJ00
	S004416	CAGJJ00
CAR2003	S011594	CAGJJ00
	S011232	CAGJJ00
	S010839	CAGJJ00
	S010249	CAGJJ00
	S009600	CAGJJ00
	S009362	CAGJJ01
CAR2002	S011517	CAGJJ00
	S011156	CAGJJ00
	S011138	CAGJJ00
	S011091	CAGJJ00
	S010947	CAGJJ00
	S010516	CAGJJ00
	S010031	CAGJJ00

CA IDMS 19.0
All CA RS Levels Service List

CA RS Level	Service	FMID
	S009476	CAGJJ00
	S009172	CAGJJ00
CAR2001	S009820	CAGJJ00
	S008599	CAGJJ00
CAR1912	S010889	CAGJJ00
	S010753	CAGJJ00
	S010396	CAGJJ00
	S010358	CAGJJ00
	S010227	CAGJJ00
	S008855	CAGJJ00
	S007433	CAGJJ00
CAR1911	S009501	CAGJJ00
	S009041	CAGJJ00
CAR1910	S010133	CAGJJ00
	S010103	CAGJJ00
	S009990	CAGJJ00
	S009980	CAGJJ00
	S009947	CAGJJ00
	S009808	CAGJJ00
	S009376	CAGJJ00
	S008919	CAGJJ00
	S008757	CAGJJ00
CAR1909	S009645	CAGJJ00
	S009609	CAGJJ00
	S009579	CAGJJ00
	S009502	CAGJJ00
	S009465	CAGJJ00
	S008527	CAGJJ00
	S008382	CAGJJ00
	S007788	CAGJJ00
	S007579	CAGJJ00
CAR1908	S009453	CAGJJ00
	S009122	CAGJJ00
	S008699	CAGJJ00
	S008620	CAGJJ00
	S008401	CAGJJ00
	S008292	CAGJJ00
	S008257	CAGJJ01
	S008256	CAGJJ00
	S008246	CAGJJ00
	S008199	CAGJJ00
CAR1907	S008436	CAGJJ00
	S008356	CAGJJ00
	S008277	CAGJJ00
	S007873	CAGJJ00
	S006677	CAGJJ00
CAR1906	S008179	CAGJJ00

CA IDMS 19.0
All CA RS Levels Service List

CA RS Level	Service	FMID
	S008151	CAGJJ00
	S008100	CAGJJ00
	S008058	CAGJJ00
CAR1905	S008156	CAGJJ00
	S008006	CAGJJ00
	S007995	CAGJJ00
	S007979	CAGJJ00
	S007852	CAGJJ00
	S007829	CAGJJ00
	S007705	CAGJJ00
	S007598	CAGJJ00
	S007073	CAGJJ00
	S006693	CAGJJ00
CAR1904	S007638	CAGJJ01
	S007448	CAGJJ00
	S007420	CAGJJ00
	S007191	CAGJJ00
	S006940	CAGJJ00
	S006629	CAGJJ01
	S006628	CAGJJ00
	S005933	CAGJJ00
	S005345	CAGJJ00
CAR1903	S007404	CAGJJ00
	S007112	CAGJJ00
	S007092	CAGJJ00
	S006860	CAGJJ00
	S006651	CAGJJ00
CAR1902	S006820	CAGJJ00
	S006346	CAGJJ00
CAR1812	S006075	CAGJJ00
	S005694	CAGJJ00
CAR1811	S005897	CAGJJ00
	S004421	CAGJJ00
CAR1809	S005151	CAGJJ00
	S004972	CAGJJ00
	S004934	CAGJJ00
	S004673	CAGJJ00
	S004635	CAGJJ00
	S004477	CAGJJ00
	S000238	CAGJJ00
	S000198	CAGJJ00
CAR1808	S004083	CAGJJ00
CAR1807	S004177	CAGJJ00
	S004062	CAGJJ00
	S003823	CAGJJ00
	S001912	CAGJJ00
	S001778	CAGJJ00

CA IDMS 19.0
All CA RS Levels Service List

CA RS Level	Service	FMID
	S001224	CAGJJ00
CAR1806	S001809	CAGJJ00
	S001578	CAGJJ00
	S000511	CAGJJ00
CAR1805	S001393	CAGJJ00
	S001206	CAGJJ00
	S001076	CAGJJ00
	S000677	CAGJJ00
	S000041	CAGJJ00
	R099709	CAGJJ00
	R098688	CAGJJ00
	R098615	CAGJJ00
CAR1804	S001055	CAGJJ00
	S000802	CAGJJ00
	S000360	CAGJJ00
	S000341	CAGJJ00
CAR1803	S000266	CAGJJ00
	S000195	CAGJJ00
	S000160	CAGJJ00
	S000145	CAGJJ00
	S000013	CAGJJ00
	R099638	CAGJJ00
	R099580	CAGJJ00
	R099577	CAGJJ00
	R098991	CAGJJ00
CAR1802	R099897	CAGJJ00
	R099627	CAGJJ00
	R099525	CAGJJ00
CAR1801	R099550	CAGJJ00
	R099485	CAGJJ00
	R099380	CAGJJ00
	R099096	CAGJJ00
	R098995	CAGJJ00
	R098831	CAGJJ00
	R098811	CAGJJ00
	R098745	CAGJJ00
	R098703	CAGJJ00
	R098684	CAGJJ00
	R098452	CAGJJ00
	R098122	CAGJJ00
	R098072	CAGJJ00
CAR1711	R098392	CAGJJ00
	R098349	CAGJJ00
	R098318	CAGJJ00
	R098221	CAGJJ00
	R098060	CAGJJ00
	R097807	CAGJJ00

CA IDMS 19.0
All CA RS Levels Service List

CA RS Level	Service	FMID
	R097698	CAGJJ00
	R097668	CAGJJ00
	R097631	CAGJJ00
	R097601	CAGJJ00
	R097492	CAGJJ00
	R097235	CAGJJ00
	R096997	CAGJJ00
	R096980	CAGJJ00
CAR1710	R097690	CAGJJ00
	R094655	CAGJJ00
CAR1709	R097401	CAGJJ00
	R097259	CAGJJ00
	R097217	CAGJJ00
	R097195	CAGJJ01
	R097168	CAGJJ00
	R097151	CAGJJ00
	R097014	CAGJJ00
	R096911	CAGJJ00
	R096889	CAGJJ00
	R096758	CAGJJ00
CAR1708	R097013	CAGJJ00
	R096918	CAGJJ00
	R096807	CAGJJ00
	R096754	CAGJJ00
	R096677	CAGJJ00
	R096339	CAGJJ00
	R096320	CAGJJ00
CAR1707	R096611	CAGJJ00
	R096512	CAGJJ00
	R096408	CAGJJ00
	R096127	CAGJJ00
CAR1706	R095899	CAGJJ00
	R095860	CAGJJ00
	R095661	CAGJJ00
	R095311	CAGJJ00
	R095296	CAGJJ00
	R095270	CAGJJ00
	R095241	CAGJJ00
	R095214	CAGJJ00
	R092219	CAGJJ00
CAR1705	R095411	CAGJJ00
	R095344	CAGJJ00
	R095319	CAGJJ00
	R095151	CAGJJ00
	R095076	CAGJJ00
	R095021	CAGJJ00
	R094965	CAGJJ00

CA RS Level	Service	FMID
	R094717	CAGJJ00
CAR1704	R094911	CAGJJ00
	R094476	CAGJJ00
	R093224	CAGJJ00
CAR1703	R094540	CAGJJ00
	R094431	CAGJJ00
	R094367	CAGJJ00
	R094240	CAGJJ00
	R094188	CAGJJ00
	R094058	CAGJJ00
	R094036	CAGJJ00
	R093920	CAGJJ01
	R093891	CAGJJ00
	R093849	CAGJJ00
	R093347	CAGJJ00
CAR1702	R093975	CAGJJ00
	R093872	CAGJJ00
	R093739	CAGJJ00
	R093622	CAGJJ00
	R093389	CAGJJ01
CAR1701	R093431	CAGJJ00
	R093357	CAGJJ00
	R093292	CAGJJ00
	R093266	CAGJJ00
	R093233	CAGJJ00
CAR1612	R093158	CAGJJ00
	R093102	CAGJJ00
	R092992	CAGJJ00
	R092927	CAGJJ00
	R092877	CAGJJ00
	R092672	CAGJJ00
	R092599	CAGJJ00
	R092573	CAGJJ00
	R092524	CAGJJ00
	R092452	CAGJJ00
	R090583	CAGJJ00
CAR1611	R092665	CAGJJ00
	R092643	CAGJJ00
	R092547	CAGJJ00
	R092371	CAGJJ00
	R092366	CAGJJ00
	R092321	CAGJJ00
	R092187	CAGJJ00
	R092185	CAGJJ00
	R092176	CAGJJ00
	R092157	CAGJJ00
	R092114	CAGJJ00

CA IDMS 19.0
All CA RS Levels Service List

CA RS Level	Service	FMID
	R092068	CAGJJ00
	R091986	CAGJJ00
	R091960	CAGJJ00
	R091870	CAGJJ00
	R091328	CAGJJ00
	R091223	CAGJJ00
	R090671	CAGJJ00
CAR1610	R091903	CAGJJ00
	R091297	CAGJJ00
	R091251	CAGJJ00
	R091070	CAGJJ00
	R090917	CAGJJ00
CAR1609	R091237	CAGJJ00
	R091229	CAGJJ00
	R091091	CAGJJ00
	R091050	CAGJJ00
	R090721	CAGJJ00
	R090707	CAGJJ00