

CA Mainframe Application Tuner 12.0
CA RS 2102 Service List

1

Service	Description	Type
S015822	CICS SRB LOOPING	PTF
S015933	NO AUTOMATIC GENERATION OF PMA REPORTS	PTF
S016062	PMA OPTION MISSING AT MAT PRIMARY PANEL	PTF
S016203	MAT RESTFUL API ENDPOINTS FOR DB2	PTF
The CA RS 2102 service count for this release is 4		

CA Mainframe Application Tuner
CA RS 2102 Service List for CEESC00

2

FMID	Service	Description	Type
CEESC00	S015822	CICS SRB LOOPING	PTF
	S015933	NO AUTOMATIC GENERATION OF PMA REPORTS	PTF
	S016062	PMA OPTION MISSING AT MAT PRIMARY PANEL	PTF
	S016203	MAT RESTFUL API ENDPOINTS FOR DB2	PTF
The CA RS 2102 service count for this FMID is 4			

Service	Details		
SO15822	SO15822 M.C.S. ENTRIES = ++PTF (SO15822) CICS SRB LOOPING PROBLEM DESCRIPTION: When measuring CICS application the CA MAT GLOBAL SRB can end up in a loop due to the application save area pointer leads to the same address in the previous and next save area. This PTF introduces a check to compare previous and current save area and prevents such a situation to happen. SYMPTOMS: CICS address space hang IMPACT: SRB LOOPING IN THE CICS ADDRESS SPACE CIRCUMVENTION: N/A PRODUCT(S) AFFECTED: CAMAT CA MAT base component Version 12.0 Related Problem: MATUNE 904 Copyright (C) 2021 CA. All rights reserved. R00274-EES120-SP1 DESC(CICS SRB LOOPING) . ++VER (Z038) FMID (CEESC00) PRE (R095409 R096674 R099194 S001740 S004661 S007230 S008560 S013439 S015065) SUP (S003810 S008523 S011963 ST03810 ST08523 ST11963 ST15822) ++HOLD (SO15822) SYSTEM FMID(CEESC00) REASON (ACTION) DATE (21011) COMMENT (<table border="1"> <tr> <td>CA MAT base component</td><td>Version 12.0</td></tr> </table> SEQUENCE After Apply PURPOSE Restart of CAMAT USERS AFFECTED All CAMAT Users KNOWLEDGE REQUIRED CAMAT Administration ACCESS REQUIRED CAMAT Administration Libraries ***** * STEPS TO PERFORM * ***** After PTF Installation restart the CAMAT server).	CA MAT base component	Version 12.0
CA MAT base component	Version 12.0		

CA Mainframe Application Tuner 12.0
CA RS 2102 - PTF SO15933 Details

4

Service	Details																		
SO15933	SO15933 M.C.S. ENTRIES = ++PTF (SO15933) NO AUTOMATIC GENERATION OF PMA REPORTS PROBLEM DESCRIPTION: Automatic generation of PMA reports at the end of measurements does not work. Neither when requested by ISPF online monitor Definition nor by TUNCALL. Error message observed is - TN0057E THE XML_REPOSITORY_DIR VARIABLE IS NOT AVAILABLE. SYMPTOMS: NO PMA reports and error message displayed on MAT SERVER log as - TN0057E THE XML_REPOSITORY_DIR VARIABLE IS NOT AVAILABLE. IMPACT: Inability to generate PMA report. CIRCUMVENTION: PRODUCT(S) AFFECTED: CA MAT base component Version 12.0 Related Problem: MATUNE 906 Copyright (C) 2021 CA. All rights reserved. R00276-EES120-SP1 DESC(NO AUTOMATIC GENERATION OF PMA REPORTS). ++VER (Z038) FMID (CEESC00) PRE (R099194 R099706 S000527 S008897 S011045 S013439) SUP (ST15933) ++HOLD (SO15933) SYSTEM FMID(CEESC00) REASON (ACTION) DATE (21005) COMMENT (<table border="1"> <tr> <td>CA MAT base component</td><td>Version 12.0</td></tr> <tr> <td>SEQUENCE</td><td>After Apply</td></tr> <tr> <td>PURPOSE</td><td>In order to reflect the changes made with PC routines</td></tr> <tr> <td>USERS</td><td>ALL MAT USers</td></tr> <tr> <td>AFFECTED</td><td></td></tr> <tr> <td>KNOWLEDGE</td><td>MAT Administration</td></tr> <tr> <td>REQUIRED</td><td></td></tr> <tr> <td>ACCESS</td><td>MAT Administration Libraries</td></tr> <tr> <td>REQUIRED</td><td></td></tr> </table> ***** * STEPS TO PERFORM * ***** Restart the MAT server).	CA MAT base component	Version 12.0	SEQUENCE	After Apply	PURPOSE	In order to reflect the changes made with PC routines	USERS	ALL MAT USers	AFFECTED		KNOWLEDGE	MAT Administration	REQUIRED		ACCESS	MAT Administration Libraries	REQUIRED	
CA MAT base component	Version 12.0																		
SEQUENCE	After Apply																		
PURPOSE	In order to reflect the changes made with PC routines																		
USERS	ALL MAT USers																		
AFFECTED																			
KNOWLEDGE	MAT Administration																		
REQUIRED																			
ACCESS	MAT Administration Libraries																		
REQUIRED																			

Service	Details
SO16062	SO16062 M.C.S. ENTRIES = ++PTF (SO16062) PMA OPTION MISSING AT MAT PRIMARY PANEL PROBLEM DESCRIPTION: The CA MAT Primary Option Menu does not provide "point and shoot" functionality for option P - PMA. SYMPTOMS: When the cursor is placed on the PMA option and the ENTER key is pressed, the cursor is simply returned to the Command Line and no other action is taken. The same is true if a mouse is used to click on the PMA option. IMPACT: Point and shoot functionality is not available for the PMA option. CIRCUMVENTION: The P option can be entered at the Command Line to invoke PMA from MAT. PRODUCT(S) AFFECTED: CA MAT base component Version 12.0 Related Problem: MATUNE 909 Copyright (C) 2021 CA. All rights reserved. R00281-EES120-SP1 DESC(PMA OPTION MISSING AT MAT PRIMARY PANEL). ++VER (Z038) FMID (CEESC00) PRE (S007227 S010479 S012185) SUP (S012789 ST12789 ST16062)

CA Mainframe Application Tuner 12.0
CA RS 2102 - PTF SO16203 Details

6

Service	Details	
SO16203	SO16203 M.C.S. ENTRIES = ++PTF (SO16203)	
	MAT RESTFUL API ENDPOINTS FOR DB2	
	ENHANCEMENT DESCRIPTION:	
	This enhancement PTF provides a range of REST API endpoints to retrieve DB2View and available SQL Statements for a line command 'S - Select SQL' from CA Mainframe Application Tuner.	
	PRODUCT(S) AFFECTED:	
	CA MAT base component	Version 12.0
	Related Problem:	
	MATUNE 910	
	Copyright (C) 2021 CA. All rights reserved. R00286-EES120-SP1	
	DESC(MAT RESTFUL API ENDPOINTS FOR DB2).	
	++VER (Z038)	
	FMID (CEESC00)	
	PRE (R099194 S001740 S004661 S013439 S015133)	
	SUP (ST16202 ST16203)	
	MCS	S015822 STARTS ON PAGE 0002
	MCS	S015933 STARTS ON PAGE 0003
	MCS	S016062 STARTS ON PAGE 0004
	MCS	S016203 STARTS ON PAGE 0005

CA Mainframe Application Tuner 12.0
CA RS 2102 Product/Component Listing

Product Family	Product	Release
Application Development	CA MAT @DAM COMPONENT	12.00.00
	CA MAT BASE COMPONENT	12.00.00
	PERFORMANCE MANAGEMENT ASSISTANT	12.00.00
	TESTING TOOLS COMMON SYMBOLIC COMPONENT	09.00.00
The CA RS 2102 Product/Component Count for this release is 4		

CA RS Level	Service	FMID
CAR2102	S016203	CEESC00
	S016062	CEESC00
	S015933	CEESC00
	S015822	CEESC00
CAR2101	S015801	CEESC00
CAR2012	S015354	CEESC00
	S015155	CEETC00
CAR2011	S015362	CEESC00
	S015133	CEESC00
	S015065	CEESC00
	S014990	CEESC00
	S014974	CEESC00
	S014931	CEESC00
	S014831	CEETC00
	S014001	CEESC00
	S013698	CEESC00
CAR2010	S014809	CEESC01
	S014662	CEESC00
	S014479	CEESC00
	S013981	CEESC00
CAR2009	S014455	CEESC00
CAR2008	S013756	CEETC00
	S013755	CEESC00
CAR2007	S013561	CEESC00
	S013440	CEESC01
	S013439	CEESC00
	S013397	CEETC00
	S012818	CEESC00
CAR2006	S013367	CEESC00
	S013246	CEY3C00
	S013236	CEETC00
	S013025	CEESC00
	S012789	CEESC00
	S010222	CEESC00
CAR2005	S012697	CEESC00
	S012055	CEY3C00
CAR2004	S012337	CEESC00
	S012213	CEESC00
	S012185	CEESC00
	S012123	CEETC00
	S010901	CEESC00
CAR2003	S012019	CEESC00
	S011963	CEESC00
	S011902	CEESC00
CAR2002	S011672	CEESC01
	S011590	CEESC01
	S011589	CEESC00

CA RS Level	Service	FMID
	S011308	CEESC00
CAR2001	S011303	CEESC00
	S011142	CEESC00
	S011045	CEESC00
CAR1912	S010640	CEESC00
	S010403	CEESC00
CAR1911	S010529	CEESC00
	S010479	CEESC00
	S010161	CEESC01
	S009473	CEESC00
CAR1910	S010215	CEESC00
	S010122	CEESC00
	S009819	CEESC00
CAR1909	S009410	CEESC00
CAR1908	S009221	CEESC00
	S009173	CEESC00
	S009140	CEESC00
	S009087	CEESC00
	S008897	CEESC00
	S008842	CEESC00
CAR1907	S009066	CEESC00
	S008989	CEESC00
	S008951	CEESC00
	S008745	CEESC00
	S008720	CEESC00
	S008636	CEESC00
CAR1906	S008560	CEESC00
	S008523	CEESC00
	S008514	CEESC01
	S008237	CEESC00
	S008107	CEESC00
	S007889	CEESC00
CAR1905	S008134	CEESC00
	S007984	CEESC00
	S007956	CEESC00
	S007925	CEESC01
	S007728	CEESC00
CAR1904	S007840	CEESC00
	S007761	CEESC01
	S007689	CEESC01
	S007641	CEESC00
	S007631	CEESC00
	S007566	CEESC00
	S007230	CEESC00
	S007227	CEESC00
CAR1902	S006959	CEESC00
	S006770	CEESC00

CA RS Level	Service	FMID
CAR1901	S006642	CEESC00
	S006631	CEESC01
	S006630	CEESC00
	S006615	CEESC00
	S006575	CEESC00
CAR1812	S006498	CEESC00
	S006378	CEESC01
	S006377	CEESC00
	S006316	CEESC00
	S006253	CEESC00
	S006193	CEESC00
	S006101	CEY3C00
	S006100	CEESC00
CAR1811	S005786	CEESC01
	S005785	CEESC00
	S005773	CEESC00
	S005588	CEESC00
	S005295	CEESC00
	S004766	CEESC00
CAR1810	S005304	CEESC00
CAR1809	S005204	CEESC01
	S005203	CEESC00
	S004801	CEESC00
	S004126	CEESC00
CAR1808	S004661	CEESC00
	S003999	CEESC01
CAR1807	S003810	CEESC00
	S003789	CEETC00
	S003592	CEESC00
	S001561	CEESC00
CAR1806	S003716	CEESC01
	S001898	CEESC00
	S001740	CEESC00
CAR1805	S001628	CEESC00
	S001094	CEESC01
	S000905	CEESC01
	S000904	CEESC00
	S000526	CEESC00
	S000337	CEESC00
CAR1804	S000940	CEESC00
	S000918	CEESC00
	S000826	CEESC00
CAR1803	S000672	CEESC00
	S000592	CEESC00
	S000528	CEESC01
	S000527	CEESC00
	S000390	CEESC00

CA RS Level	Service	FMID
	S000366	CEESC00
	S000196	CEESC00
CAR1802	S000073	CEETC00
	S000033	CEESC00
	R099940	CEESC00
	R099707	CEESC01
CAR1801	R099706	CEESC00
	R099698	CEESC00
	R099416	CEESC00
CAR1712	R099194	CEESC00
	R098930	CEETC00
	R098929	CEY3C00
	R098861	CEESC00
	R098484	CEESC00
CAR1710	R097752	CEESC00
	R097689	CEESC00
CAR1709	R097599	CEESC00
	R097281	CEESC00
CAR1708	R097178	CEESC00
	R096915	CEESC00
	R096895	CEESC00
	R096873	CEESC00
	R096868	CEESC00
	R096841	CEESC00
	R096768	CEESC00
CAR1707	R096885	CEESC00
	R096751	CEESC00
	R096674	CEESC00
	R096572	CEESC00
	R096511	CEESC00
	R096507	CEESC00
	R096358	CEESC00
	R095389	CEESC00
CAR1706	R096177	CEESC00
	R096173	CEESC00
	R096082	CEESC00
	R095904	CEESC00
	R095591	CEETC00
	R095146	CEESC00
CAR1705	R095427	CEESC00
	R095409	CEESC00
	R095398	CEESC00
	R095096	CEESC00
CAR1704	R095014	CEESC00
	R094986	CEESC00
	R094896	CEESC00
	R094695	CEESC00

CA RS Level	Service	FMID
CAR1703	R094523	CEESC00
	R094521	CEESC00
	R094511	CEESC00
	R094455	CEESC00
CAR1609	R077654	CAVH900
CAR1604	R086339	CAVH900
CAR1511	R085682	CAVH900
CAR1510	R083674	CAVH900
	R075531	CAVH900
CAR1509	R083178	CAVH900
	R076680	CAVH900
	R074918	CAVH900
CAR1508	R083076	CAVH900
	R079534	CAVH900
CAR1501	R073218	CAVH900
	R072020	CAVH900
CAR1411	R067798	CAVH900
CAR1403	R065745	CAVH900
	R065202	CAVH900
	R063322	CAVH900
CAR1312	R061892	CAVH900
	R061210	CAVH900
CAR1309	R060135	CAVH900
	R059970	CAVH900
	R056472	CAVH900
	R037810	CAVH900